

# VSI OpenVMS

## DCL Dictionary: N–Z

**Operating System and Version:** VSI OpenVMS IA-64 Version 8.4-1H1 or higher  
VSI OpenVMS Alpha Version 8.4-2L1 or higher  
VSI OpenVMS x86-64 Version 9.2-1 or higher

---

## DCL Dictionary: N–Z



VMS Software

---

Copyright © 2024 VMS Software, Inc. (VSI), Boston, Massachusetts, USA

### Legal Notice

Confidential computer software. Valid license from VSI required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

The information contained herein is subject to change without notice. The only warranties for VSI products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. VSI shall not be liable for technical or editorial errors or omissions contained herein.

All other trademarks and registered trademarks mentioned in this document are the property of their respective holders.

# Table of Contents

<b>Preface .....</b>	<b>vii</b>
1. About VSI .....	vii
2. Intended Audience .....	vii
3. Documents Structure .....	vii
4. Related Documents .....	vii
5. VSI Encourages Your Comments .....	viii
6. OpenVMS Documentation .....	viii
7. Conventions .....	viii
<b>DCL Commands .....</b>	<b>1</b>
NCS .....	1
ON .....	1
OPEN .....	4
PASSWORD .....	7
PATCH .....	8
PHONE .....	12
PIPE .....	13
PPPD .....	21
PRINT .....	22
PRODUCT .....	35
PURGE .....	35
READ .....	39
RECALL .....	43
RENAME .....	46
REPLY .....	51
REQUEST .....	59
RETURN .....	61
RUN (Image) .....	62
RUN (Process) .....	64
RUNOFF .....	75
SEARCH .....	75
SET .....	84
SET ACCOUNTING .....	87
SET AUDIT .....	89
SET BOOTBLOCK (Integrity servers Only) .....	101
SET BROADCAST .....	102
SET CACHE/RESET .....	104
SET CARD_READER .....	105
SET CLUSTER/EXPECTED_VOTES .....	106
SET COMMAND .....	107
SET CONTROL .....	110
SET CPU .....	112
SET DAY .....	118
SET DEFAULT .....	119
SET DEVICE .....	122
SET DEVICE/SERVED .....	129
SET DIRECTORY .....	130
SET DISPLAY .....	134
SET ENTRY .....	146
SET FILE .....	156
SET HOST .....	167

SET HOST/DTE .....	170
SET HOST/DUP .....	177
SET HOST/HSC .....	178
SET HOST/LAT .....	179
SET HOST/RLOGIN .....	183
SET HOST/TELNET .....	185
SET HOST/TN3270 .....	186
SET IMAGE (Alpha/Integrity servers Only) .....	187
SET KEY .....	191
SET LOGINS .....	191
SET MAGTAPE .....	192
SET MESSAGE .....	196
SET NETWORK .....	198
SET ON .....	201
SET OUTPUT_RATE .....	202
SET PASSWORD .....	202
SET PREFERRED_PATH .....	206
SET PREFIX .....	208
SET PRINTER .....	209
SET PROCESS .....	212
SET PROMPT .....	225
SET PROTECTION/DEFAULT .....	225
SET QUEUE .....	226
SET RESTART_VALUE .....	234
SET RIGHTS_LIST .....	236
SET RMS_DEFAULT .....	238
SET ROOT .....	244
SET SECURITY .....	244
SET SERVER ACME_SERVER (Alpha/Integrity servers Only) .....	253
SET SERVER REGISTRY_SERVER (Alpha/Integrity servers Only) .....	260
SET SERVER SECURITY_SERVER .....	262
SET SHADOW (Alpha/Integrity servers Only) .....	263
SET SYMBOL .....	275
SET TERMINAL .....	277
SET TIME .....	291
SET VERIFY .....	293
SET VOLUME .....	295
SET WORKING_SET .....	301
SHOW .....	303
SHOW ACCOUNTING .....	304
SHOW AUDIT .....	306
SHOW BROADCAST .....	310
SHOW CLUSTER .....	311
SHOW CPU .....	312
SHOW DEFAULT .....	322
SHOW DEVICES .....	323
SHOW DEVICES/SERVED .....	335
SHOW DISPLAY .....	339
SHOW ENTRY .....	343
SHOW ENTROPY (x86-64 only) .....	348
SHOW ERROR .....	349
SHOW FASTPATH (Alpha/Integrity servers Only) .....	352

SHOW IMAGE (Alpha/Integrity servers Only) .....	353
SHOW INTRUSION .....	356
SHOW KEY .....	358
SHOW LICENSE .....	360
SHOW LOGICAL .....	371
SHOW MEMORY .....	376
SHOW NETWORK .....	393
SHOW PRINTER .....	397
SHOW PROCESS .....	400
SHOW PROTECTION .....	409
SHOW QUEUE .....	410
SHOW QUEUE/CHARACTERISTICS .....	416
SHOW QUEUE/FORM .....	417
SHOW QUEUE/MANAGERS .....	419
SHOW QUOTA .....	421
SHOW RMS_DEFAULT .....	422
SHOW ROOT .....	423
SHOW SECURITY .....	423
SHOW SERVER ACME_SERVER (Alpha/Integrity servers Only) .....	427
SHOW SERVER REGISTRY_SERVER (Alpha/Integrity servers Only) .....	430
SHOW SHADOW (Alpha/Integrity servers Only) .....	431
SHOW STATUS .....	439
SHOW SYMBOL .....	440
SHOW SYSTEM .....	441
SHOW TERMINAL .....	451
SHOW TIME .....	453
SHOW TRANSLATION .....	453
SHOW USERS .....	455
SHOW WORKING_SET .....	459
SORT .....	461
SPAWN .....	461
START/CPU .....	467
START/NETWORK .....	468
START/QUEUE .....	469
START/QUEUE/MANAGER .....	480
START/ZONE .....	484
STOP .....	484
STOP/CPU .....	487
STOP/NETWORK .....	489
STOP/QUEUE .....	490
STOP/QUEUE/ABORT .....	491
STOP/QUEUE/ENTRY .....	492
STOP/QUEUE/MANAGER/CLUSTER .....	493
STOP/QUEUE/NEXT .....	494
STOP/QUEUE/REQUEUE .....	495
STOP/QUEUE/RESET .....	497
STOP/QUEUES/ON_NODE .....	498
STOP/ZONE .....	500
SUBMIT .....	500
SUBROUTINE .....	512
SYNCHRONIZE .....	513
TYPE .....	514

UNLOCK .....	522
VIEW .....	522
WAIT .....	523
WRITE .....	524
XAUTH (Alpha/Integrity servers Only) .....	526

**Appendix A. Obsolete Commands ..... 529**

**Appendix B. Handling Numeric Values Outside the Range of DCL Integer**

**Representation ..... 531**

B.1. Preface .....	531
B.2. Introduction .....	531
B.2.1. Problem Statement .....	531
B.2.2. Prerequisites .....	532
B.3. DCL Examples .....	532
B.3.1. DCL code checking a value in range 0 to 2147483647 .....	532
B.3.2. DCL code checking a value in range 0 to 4294967295 .....	532
B.3.3. Checking the percentage of free blocks on a disk .....	533
B.3.4. F\$CUNITS() lexical function description .....	534
B.4. Identifying Suspect DCL Code .....	537
B.4.1. DCL Code Search Example .....	537

# Preface

## 1. About VSI

VMS Software, Inc. (VSI) is an independent software company licensed by Hewlett Packard Enterprise to develop and support the OpenVMS operating system.

## 2. Intended Audience

This manual is intended for all users of the VSI OpenVMS operating system. It includes descriptions of all DIGITAL Command Language (DCL) commands and lexical functions. If a command has any restrictions or requires special privileges, they are noted in reference information for that command.

Readers of this manual should be familiar with the material covered in the *VSI OpenVMS User's Manual* [<https://docs.vmssoftware.com/vsi-openvms-user-s-manual/>].

## 3. Documents Structure

This manual contains detailed descriptions of each command and lexical function. The commands are listed in alphabetical order. The lexical functions are grouped under the heading Lexical Functions and are listed alphabetically within that grouping.

The hardcopy version of the *VSI OpenVMS DCL Dictionary* is a two-part manual. The first volume contains commands beginning with the letters A to M (including the lexical functions); the second volume contains commands beginning with the letters N to Z.

Appendix A of this manual (in the second volume of the hardcopy manual) lists the obsolete DCL commands and the current services that replace them.

The commands that invoke language compilers and other OpenVMS optional software products are not included in this manual; they are included in the documentation provided with those products.

## 4. Related Documents

For an introduction to the OpenVMS operating system and for information on using DCL, refer to the *VSI OpenVMS User's Manual* [<https://docs.vmssoftware.com/vsi-openvms-user-s-manual/>]. This manual is especially recommended for novice users or users lacking experience with interactive computer systems.

The *VSI OpenVMS User's Manual* [<https://docs.vmssoftware.com/vsi-openvms-user-s-manual/>] provides an overview of DCL command language concepts and defines and illustrates good practices in constructing command procedures with DCL commands and lexical functions.

Refer to the various utilities reference manuals for detailed information about utilities. These manuals describe the DCL commands that invoke the various utilities, describe any commands that you can enter while running a utility, and provide reference information. The *VSI OpenVMS DCL Dictionary* provides only a brief description and format information for each utility.

For message descriptions, use the online Help Message utility.

## 5. VSI Encourages Your Comments

You may send comments or suggestions regarding this manual or any VSI document by sending electronic mail to the following Internet address: <docinfo@vmssoftware.com>. Users who have VSI OpenVMS support contracts through VSI can contact <support@vmssoftware.com> for help with this product.

## 6. OpenVMS Documentation

The full VSI OpenVMS documentation set can be found on the VMS Software Documentation webpage at <https://docs.vmssoftware.com>.

## 7. Conventions

The following conventions are used in this manual:

Convention	Meaning
<b>Ctrl/x</b>	A sequence such as <b>Ctrl/x</b> indicates that you must hold down the key labeled <b>Ctrl</b> while you press another key or a pointing device button.
<b>PF1 x</b>	A sequence such as <b>PF1 x</b> indicates that you must first press and release the key labeled <b>PF1</b> and then press and release another key or a pointing device button.
. . .	A horizontal ellipsis in examples indicates one of the following possibilities: <ul style="list-style-type: none"><li>• Additional optional arguments in a statement have been omitted.</li><li>• The preceding item or items can be repeated one or more times.</li><li>• Additional parameters, values, or other information can be entered.</li></ul>
. . . .	A vertical ellipsis indicates the omission of items from a code example or command format; the items are omitted because they are not important to the topic being discussed.
( )	In command format descriptions, parentheses indicate that you must enclose choices in parentheses if you specify more than one.
[ ]	In command format descriptions, brackets indicate optional choices. You can choose one or more items or no items. Do not type the brackets on the command line. However, you must include the brackets in the syntax for OpenVMS directory specifications and for a substring specification in an assignment statement.
	In command format descriptions, vertical bars separate choices within brackets or braces. Within brackets, the choices are optional; within braces, at least one choice is required. Do not type the vertical bars on the command line.
{ }	In command format descriptions, braces indicate required choices; you must choose at least one of the items listed. Do not type the braces on the command line.
<b>bold type</b>	Bold type represents the name of an argument, an attribute, or a reason. Bold type also represents the introduction of a new term.

Convention	Meaning
<i>italic type</i>	Italic type indicates important information, complete titles of manuals, or variables. Variables include information that varies in system output (Internal error <i>number</i> ), in command lines ( <b>/ PRODUCER=name</b> ), and in command parameters in text (where <i>dd</i> represents the predefined code for the device type).
UPPERCASE TYPE	Uppercase type indicates the name of a routine, the name of a file, or the abbreviation for a system privilege.
monospace type	Monospace type indicates code examples, command examples, and interactive screen displays. In text, this type also identifies URLs, UNIX commands and pathnames, PC-based commands and folders, and certain elements of the C programming language.
<b>bold monospace type</b>	Bold monospace type indicates a DCL command or command qualifier.
-	A hyphen at the end of a command format description, command line, or code line indicates that the command or statement continues on the following line.
numbers	All numbers in text are assumed to be decimal unless otherwise noted. Nondecimal radices – binary, octal, or hexadecimal – are explicitly indicated.



# DCL Commands

## NCS

NCS — Invokes the OpenVMS National Character Set (NCS) utility, which provides a convenient method of implementing alternative (non-ASCII) string collating sequences, typically using subsets of the DEC Multinational character set. NCS also facilitates the implementation of string conversion functions. For more information about the NCS utility, see the *OpenVMS National Character Set Utility Manual* or online help.

## Format

**NCS** [*filespec*[,...]]

## ON

ON — Performs a specified action when a command or program executed within a command procedure encounters an error condition or is interrupted by **Ctrl/Y**. The specified actions are performed only if the command interpreter is enabled for error checking or **Ctrl/Y** interrupts (the default conditions). Use the **ON** command only in a command procedure.

## Format

**ON***condition* **THEN** [\$] *command*

## Parameters

*condition*

Specifies either the severity level of an error or a **Ctrl/Y** interrupt. Specify one of the following keywords, which may be abbreviated to one or more characters:

WARNING	Return status of warning occurs (\$SEVERITY equals 0).
ERROR	Return status of error occurs (\$SEVERITY equals 2).
SEVERE_ERROR	Return status of error occurs (\$SEVERITY equals 4).
CONTROL_Y	<b>Ctrl/Y</b> character occurs on SYS\$INPUT.

The default error condition is **ON ERROR THEN EXIT**.

*command*

Specifies the DCL command line to be executed. Optionally, you can precede the command line with a dollar sign (\$).

If you specified an error condition as the condition parameter, the action is taken when errors equal to or greater than the specified level of error occur.

## Description

During the execution of a command procedure, the command interpreter checks the condition code returned from each command or program that executes. With the **ON** command, you can establish a course of action for the command interpreter to take based on the result of the check.

The system places condition codes in the global symbol `$STATUS`. The severity of the condition code is represented in the first 3 low-order bits of `$STATUS`. This severity level is also represented by the global symbol `$SEVERITY`. See the description of the **EXIT** command in the *VSI OpenVMS DCL Dictionary: A-M* [[https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\\_110](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_110)] for information on severity level values.

If an **ON** command action specifies the severity level of an error, the command interpreter executes the **ON** command action for errors at the specified severity level or greater. For example, the following command causes a procedure to exit on warnings, errors, or severe errors:

```
$ ON WARNING THEN EXIT
```

The default action is as follows:

```
$ ON ERROR THEN EXIT
```

That is, the command interpreter continues when a warning occurs, and executes an **EXIT** command when an error or severe error occurs. An **ON** command action that specifies a severity level is executed only once; after the **ON** command action is taken, the default **ON** action is reset. There is an exception to the default **ON** action. If you use the **CALL**, **GOSUB**, or **GOTO** commands and specify a label that does not exist in the current command procedure, the procedure issues a warning message and exits.

The action specified by an **ON** command applies only within the command procedure in which the command is executed; therefore, if you execute an **ON** command in a procedure that calls another procedure, the **ON** command action does not apply to the nested procedure. An **ON** command executed at any command procedure level does not affect the error condition handling of procedures at any other level.

To disable error checking with the **ON** command, use the **SET NOON** command. You can enable error checking with the **SET ON** command, or by entering another **ON** command.

The **ON** command also provides a way to define an action routine for a **Ctrl/Y** interrupt that occurs during execution of a command procedure. The default (**Ctrl/Y**) action is to prompt for command input at the **Ctrl/Y** command level. The **Ctrl/Y** command level is a special command level where you can enter DCL commands. If you enter a command that is executed within the command interpreter, you can resume execution of the procedure with the **CONTINUE** command. (For a list of commands that are executed within the command interpreter, see the *VSI OpenVMS User's Manual* [<https://docs.vmssoftware.com/vsi-openvms-user-s-manual/>].)

If you enter any other DCL command, the command interpreter returns to command level 0 and executes the image invoked by the command. If you interrupt the command procedure while it is executing an image that contains an exit handler, the exit handler is allowed to execute before the new command (image) is executed. (However, if you enter the **STOP** command after you interrupt a command procedure by pressing **Ctrl/Y**, exit handlers declared by the interrupted image are not executed.)

You can use the **ON** command to change the default action for a **Ctrl/Y** interrupt. If you change the default **Ctrl/Y** action, the execution of a **Ctrl/Y** interrupt does not automatically reset the default **Ctrl/Y** action. A **Ctrl/Y** action remains in effect until one of the following occurs:

- The procedure terminates (as a result of an **EXIT** or **STOP** command, or as a result of a default error condition handling action).
- Another **ON CONTROL\_Y** command is executed.
- The procedure executes the **SET NOCONTROL=Y** command.

A **Ctrl/Y** action can be specified for each active command level; the **Ctrl/Y** action specified for the currently executing command level overrides actions specified for previous levels.

---

## Note

The **ON CONTROL\_Y** and **SET NOCONTROL=Y** commands are intended for special applications. VSI does not recommend, in general, that you disable **Ctrl/Y** interrupts. For example, if a procedure that disables **Ctrl/Y** interrupts begins to loop uncontrollably, you cannot gain control to stop the procedure from your terminal.

---

## Examples

1. `$ ON SEVERE_ERROR THEN CONTINUE`

A command procedure that contains this statement continues to execute normally when a warning or error occurs during execution. When a severe error occurs, the **ON** statement signals the procedure to execute the next statement anyway. Once the statement has been executed as a result of the severe error condition, the default action (**ON ERROR THEN EXIT**) is reinstated.

2. 

```
$ ON ERROR THEN GOTO BYPASS
$ RUN A
$ RUN B
.
.
.
$ EXIT
$ BYPASS:
$      RUN C
```

If either program A or program B returns a status code with a severity level of error or severe error, control is transferred to the statement labeled BYPASS and program C is run.

3. 

```
$ ON WARNING THEN EXIT
.
.
.
$ SET NOON
$ RUN [SSTEST]LIBRA
$ SET ON
.
.
.
```

The **ON** command requests that the procedure exit when any warning, error, or severe error occurs. Later, the **SET NOON** command disables error checking before executing the **RUN** command. Regardless of any status code returned by the program LIBRA.EXE, the procedure continues. The next command, **SET ON**, re-enables error checking and reestablishes the most recent **ON** condition.

4. `$ ON CONTROL_Y THEN GOTO CTRL_EXIT`

```
.  
. .  
$ CTRL_EXIT:  
$ CLOSE INFILE  
$ CLOSE OUTFILE  
$ EXIT
```

The **ON** command specifies action to be taken when **Ctrl/Y** is pressed during the execution of this procedure: the **GOTO** command transfers control to the line labeled CTRL\_EXIT. At CTRL\_EXIT, the procedure performs cleanup operations (in this example, closing files and exiting).

## OPEN

OPEN — Opens a file for reading, writing, or both; assigns a logical name to a file; and places the name in the process logical name table. **See the qualifier descriptions for restrictions.**

### Format

**OPEN** *logical-name[:]* *filespec*

### Parameters

*logical-name[:]*

Specifies the logical name and a character string to be assigned to the file.

*filespec*

Specifies the name of the file or device being opened for input or output. The file type defaults to DAT. The asterisk (\*) and the percent sign (%) wildcard characters are not allowed.

To create a new, sequential file, specify the **/WRITE** qualifier. See the description of the [/WRITE](#) qualifier for more information.

### Description

A file can be opened for either reading or writing, or for both reading and writing. After the file is opened, it is available for input or output at the command level with the **READ** and **WRITE** commands.

The **OPEN** command opens files as process permanent. Therefore, these files remain open until you close them with the **CLOSE** command, or until you log out. If a command procedure that opens a file terminates without closing an open file, the file remains open; the command interpreter does not automatically close it. The **OPEN** command uses OpenVMS RMS to open files, and is subject to RMS restrictions on using process-permanent files. The **OPEN** command opens sequential, relative, or indexed sequential files.

The logical devices SYS\$INPUT, SYS\$OUTPUT, SYS\$COMMAND, and SYS\$ERROR do not have to be opened explicitly before they can be read or written at the command level. All other files must be opened explicitly.

Do not use the same logical name when you open different files. If you specify a logical name with the **OPEN** command and the logical name is currently assigned to another file, no warning message is issued;

however, the file is not opened, and the next **READ** request will access the file to which the logical name was originally assigned.

You can enter more than one **OPEN** command for the same file and assign it different logical names if you use the **/SHARE** qualifier the first time the file is opened. Also, if you open the file by using the **/SHARE=READ** or the **/SHARE=WRITE** qualifier, other users can access the file with the **TYPE** or the **SEARCH** command.

When you use the **OPEN** command to create a new file, variable fixed control (VFC) record format is used. Concatenating a file of this record format with a file of another record format might be impossible due to record format incompatibilities. To avoid the VFC format, use the **CREATE** command to create the file.

When the **OPEN** command is specified on an existing file, the record type of that file is used.

## Qualifiers

### **/APPEND**

Opens an existing file for writing and positions the record pointer at the end-of-file (EOF). New records are added to the end of the file.

Only sequential files allow more than one user to append records concurrently.

Use the **/APPEND** qualifier only to add records to an existing file. The **/APPEND** and the **/WRITE** qualifiers are mutually exclusive.

### **/ERROR=label**

Transfers control to the location specified by the label keyword (in a command procedure) if the open operation results in an error. The error routine specified for this qualifier overrides any **ON** condition action specified. If the **/ERROR** qualifier is not specified, the current **ON** condition action is taken.

If an error occurs and the target label is successfully given control, the global symbol \$STATUS retains the code for the error that caused the error path to be taken.

### **/READ (default)**

Opens the file for reading. If you open a file with **/READ**, other users are also allowed read access to the file, but no user is allowed write access. If you open a file with **/READ/WRITE**, no other users are allowed access while the file is open. If you specify the **/READ** qualifier without the **/WRITE** qualifier, you must specify an existing file.

### **/SHARE[=option]**

#### **/NOSHARE (Alpha/Integrity servers only)**

Opens the specified file as a shareable file to allow other users read or write access. If you specify the **/SHARE=READ** qualifier, other users are allowed read (R) access to the file, but not write (W) access. If you specify the **/SHARE=WRITE** or the **/SHARE** qualifier with no option, users are allowed read and write access to the specified file.

To open a file with no shared access, specify **/NOSHARE** or use **OPEN/READ/WRITE**.

### **/WRITE**

Opens the file for writing. The following restrictions apply to the **/WRITE** qualifier:

- Use the **/WRITE** qualifier to open and create a new, sequential file. If the file specification on an **OPEN/WRITE** command does not include a file version number, and if a file with the specified file name and file type already exists, a new file with a version number one greater than the existing file is created.
- Use the **/READ** qualifier with the **/WRITE** qualifier to open an existing file. While the file is open, no other user will have access to it. When the file is first opened, the pointer is positioned to the beginning of the file. (This differs from **OPEN/APPEND**, which positions the pointer at the end of the file.) You cannot use **OPEN/READ/WRITE** to create a new file.
- The **/WRITE** and the **/APPEND** qualifiers are mutually exclusive.

## Examples

```
1. $ OPEN INPUT_FILE AVERAGE.DAT
$ READ_LOOP:
$ READ/END_OF_FILE=ENDIT INPUT_FILE NUM
.
.
.
$ GOTO READ_LOOP
$ ENDIT:
$ CLOSE INPUT_FILE
```

The **OPEN** command opens the file named `AVERAGE.DAT` as an input file and assigns it the logical name `INPUT_FILE`. The file is opened with read access because the **/READ** qualifier is present by default. The **READ** command reads a record from the logical file `INPUT_FILE` into the symbol named `NUM`. The procedure executes the lines between the labels `READ_LOOP` and `ENDIT` until the end of the file is reached. At the end of the file, the **CLOSE** command closes the file.

```
2. $ OPEN/WRITE/ERROR=OPEN_ERROR OUTPUT_FILE TEMP.OUT
$ COUNT = 0
$ WRITE_LOOP:
$ COUNT = COUNT + 1
$ IF COUNT .EQ. 11 THEN GOTO ENDIT
$ WRITE OUTPUT_FILE "Count is '"COUNT'."
.
.
.
$ GOTO WRITE_LOOP
$ ENDIT:
$ CLOSE OUTPUT_FILE
$ EXIT
$
$ OPEN_ERROR:
$ WRITE SYS$OUTPUT "Cannot open file TEMP.OUT"
$ EXIT
```

The **OPEN** command with the **/WRITE** qualifier creates the file `TEMP.OUT` and assigns it the logical name `OUTPUT_FILE`. `TEMP.OUT` is a sequential file.

The **/ERROR** qualifier specifies that if any error occurs while opening the file, the command interpreter should transfer control to the line at the label `OPEN_ERROR`. The command procedure writes records to the file `TEMP.OUT` until the symbol `COUNT` equals 11.

```
3. $ OPEN/READ INPUT_FILE TRNTO::DKA0:[COST]INVENTORY.DAT
```

```
$ READ_LOOP :  
$ READ/END_OF_FILE=ENDIT  INPUT_FILE  NUM  
$ FIRST_CHAR = F$EXTRACT(0,1,NUM)  
$ WRITE SYS$OUTPUT FIRST_CHAR  
$ GOTO READ_LOOP  
$ ENDIT:  
$ CLOSE INPUT_FILE
```

This command procedure opens the file `INVENTORY.DAT` located at remote node `TRNTO` as an input file, and assigns it the logical name `INPUT_FILE`. The **READ** command reads a record from the logical file `INPUT_FILE` into the symbol named `NUM`. The next two commands extract the first character from the record and write the character to the `SYS$OUTPUT` device. These two steps occur for all records in the file until the procedure reaches the end-of-file (EOF). At this point, the **CLOSE** command closes the file and deassigns the logical name `INPUT_FILE`.

## PASSWORD

**PASSWORD** — Provides the password associated with the user name that you specify with the **JOB** card when you submit a batch job through a card reader. Although the **PASSWORD** card is required, the password on the card is optional if the account has a null password. **The **PASSWORD** command is valid only in a batch job submitted through a card reader and requires that a dollar sign (\$) precede the **PASSWORD** command on the card.**

### Format

**PASSWORD**[*password*]

### Parameter

*password*

Specifies the password associated with the user name specified with the **JOB** command. The password can be 1 to 31 characters long.

If you are submitting the job from an account with a null password, omit the password specifier on the **PASSWORD** card.

### Description

The **PASSWORD** command is used in conjunction with the **JOB** command. The **JOB** card identifies the user submitting the batch job through a card reader and is followed by a **PASSWORD** card giving the password. The password is checked by the system to verify that it matches the password associated with the user name on the **JOB** card. If the passwords do not match, the job is rejected.

Note that you might want to suppress printing when you originally key punch the **PASSWORD** card to prohibit other users from seeing the password when the **PASSWORD** card is in use.


---

### Note

To change your password, use the **SET PASSWORD** command. For information on this command, see the description of [SET PASSWORD](#).

---

## Example



The **JOB** and **PASSWORD** commands precede a batch job submitted from the card reader. An **EOJ** command marks the end of the job.

## PATCH

**PATCH** — On Alpha and Integrity servers, invokes **PATCH/ABSOLUTE** by default, which patches a file at absolute virtual addresses. For more information, see the online help inside the Patch Utility.

## Format

**PATCH***filespec*

## Parameter

*filespec*

Specifies the image file to be patched or a command procedure that contains both the name of the image file to be patched and **PATCH** commands.

If the file specification denotes an image file, the file specification must contain the file name. If you omit the remaining fields (device, directory, file type, and version number), **PATCH** uses your default device and directory, assumes a file type of **EXE**, and uses the highest version of the image file.

If the file specification denotes a command procedure, the *filespec* parameter must be preceded by an at sign (**@**). Only the file name is required. If you omit the remaining fields (device, directory, file type, and version number), **PATCH** uses your default device and directory, assumes a file type of **COM**, and locates the highest version of the command procedure.

The asterisk (**\***) and the percent sign (**%**) wildcard characters are not allowed in the file specification.

## Qualifiers

**/ABSOLUTE**

Patches a file at absolute virtual addresses. This is the default for Alpha and Integrity server systems. The **/ABSOLUTE** function allows a user to patch any file (not just image files) at absolute virtual addresses relative to the beginning of the file. This feature allows replacement of existing data with

new data of the same length. If the data is smaller than that of the original data, PATCH uses the appropriate fill character for the mode in use. For example, if the current mode is instruction mode, a NOP is used for fill; if it is data (numeric or ASCII) mode, a NULL is used for fill. Any PATCH operation that results in a data replacement longer than the length of the original data generates an error message and terminates the command in progress; either the PATCH or DCL prompt is then displayed, whichever is appropriate.

Also, note that there is no default patch area, and none will be created, because of the tendency to corrupt a file. Patch area is meaningless in any file other than an image file.

If you patch a file in absolute mode, remember that there are no symbols available to assist you in locating data locations. You must exercise great care to ascertain that the correct locations are modified.

Most **PATCH** commands will work in their normal fashion. However, only **REPLACE** and **DEPOSIT** should be used for write operations; other commands are acceptable for read operations. Commands that attempt to expand the file, such as **ALIGN** and **INSERT**, should be avoided because they will probably corrupt the file. (These commands will be trapped by PATCH and an error message will be issued indicating that the replacement data must not exceed the length of the original data.)

File attributes are propagated from the original input file to the output file. These include ALQ, TYPE, MRS, RAT, RFM, and RAC.

#### **/JOURNAL[=*filespec*]**

Indicates an alternate journal file specification. By default, PATCH creates a journal file with a file specification that consists of the current defaults. Use the **/JOURNAL** qualifier when you want to specify an alternate file specification. If you omit fields in the file specification, PATCH supplies the following default values:

Field	Default Value
device and directory	Defaults of current process
file name	Name of input image file
file type	JNL
version	1

Subsequent PATCH sessions append information to the journal file, rather than create a new version of this file.

The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification.

#### **/NEW\_VERSION (default)**

#### **/NONEW\_VERSION**

Controls whether a new version of the patched file is created or the contents of the existing file are modified in place. The **/NEW\_VERSION** qualifier is used in conjunction with the **/ABSOLUTE** qualifier to control whether a new version of the patched file is created or the contents of the existing file are modified in place. **/NEW\_VERSION** is the default. If **/NONEW\_VERSION** is selected, the PATCH command **UPDATE** will act as a checkpoint operation, that is, all modifications made to the file are written back to the file instead of waiting until image exit. If **/ABSOLUTE** is not specified with **/NONEW\_VERSION**, **/NONEW\_VERSION** is ignored, that is, a new version of

the file will be created. **/NEW\_VERSION** will need to be used when patching large data files when there is not enough disk space to create a new version of the patched file.

---

## Note

If **/NEW\_VERSION** is specified, the file will be overwritten. No attempt on the part of the user, including pressing **Ctrl/Y**, will prevent this result. Therefore, you should have a back up copy of the file before making any attempt to patch it.

PATCH will always issue an informational message at image exit, indicating that the file is being overwritten.

---

## **/OUTPUT[=*filespec*]**

Indicates the output image file specification. By default, PATCH creates an output file with a file specification that consists of the current defaults. Use the **/OUTPUT** qualifier when you want to specify an alternate file specification.

If you omit fields in the file specification, PATCH supplies the following default values:

Field	Default Value
device and directory	Defaults of current process
file name	Name of input image file
file type	.EXE
version	One greater than the most recent copy of the input image file

The output image file is created only when you issue the PATCH command **UPDATE** at the end of the PATCH session. You can issue multiple **UPDATE** commands in a single session. The first **UPDATE** command creates the output image file; subsequent **UPDATE** commands overwrite this file.

The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification.

## **/VOLUME[=*n*]**

Requests that the output file be placed on a specified relative volume number of a multi-volume set. If you specify **/VOLUME** without a number, the number defaults to the relative volume number of the input image file.

If the **/VOLUME** qualifier is not specified, the file is placed in an arbitrary position within the multi-volume set.

## Examples

- ```
$ PATCH/ABSOLUTE IMAGE.EXE
PATCH>EX/INS 604
00000604: BBSS #07,R1,00000608
PATCH>REPLACE/INS 604='BBSS #07,R1,0608'
NEW> 'BBSS #07,R1,0608'
NEW> 'CLRL R0'
NEW> EXIT
old: 00000604: BBSS #07,R1,00000608
%PATCH-E-DATTOOLNG, length of new data may not exceed length of
```

```
old data
PATCH>EX/INS 684
00000684: MOV B #01, (R5)+
PATCH>REPLACE/INS 684='MOV B #01, (R5)+'
NEW> 'MOV B #02, (R5)+'
NEW> EXIT
old: 00000684: MOV B #01, (R5)+
new: 00000684: MOV B #02, (R5)+
PATCH>EX/INS 687
00000687: MOV B #00, (R5)+
PATCH>DEPOSIT/INS 687
NEW> 'CLRB (R5)+'
NEW> EXIT
old: 00000687: MOV B #00, (R5)+
new: 00000687: CLRB (R5)+
PATCH>INSERT/INS 68D
OLD> 'MOV B #10, (R5)+'
NEW> 'MOV B #20, (R5)+'
NEW> EXIT
old: 0000068D: MOV B #10, (R5)+
%PATCH-E-DATTOOLNG, length of new data may not exceed length of
old data
PATCH>UPDATE
%PATCH-I-WRTFIL, updating image file
DISK$STARWORK01:[NASR.PATCH]IMAGE.EXE;2
PATCH>EXIT
```

Example of the **/ABSOLUTE** qualifier with **/NEW\_VERSION** as the default. Note the error messages returned when the command tries to expand the file.

2. \$ PATCH/ABSOLUTE/NONEW\_VERSION LOGIN.COM

```
PATCH>EX/ASCII 57
00000057: 'MANA'
PATCH>REPLACE/ASCII 57='MANA'
NEW> 'mana'
NEW> 'test'
NEW> exit
old: 00000057: 'MANA'
%PATCH-E-REPLACEERR, replacement value too large for location
PATCH>replace/ascii 57='MANA'
NEW> 'mana'
NEW> exit
old: 00000057: 'MANA'
new: 00000057: 'mana'
PATCH>EX/ASCII 24
00000024: 'F$MO'
PATCH>INSERT/ASCII 24='F$MO'
NEW> 'test'
NEW> exit
%PATCH-E-INVCMDB, invalid command
PATCH>UPDATE
%PATCH-I-OVERLAY, DISK$STARWORK01:[NASR.PATCH]LOGIN.COM;1 being
overwritten
PATCH>EX 68:75
00000068: 4349544F
0000006C: 58542E45
00000070: 00010054
00000074: 00100024
```

```
PATCH>REPLACE 68
OLD> 4349544F
OLD> 58542E45
OLD> 00010054
OLD> EXIT
NEW> 6369746F
NEW> 68642E65
NEW> 00010074
NEW> EXIT
old: 00000068: 4349544F
old: 0000006C: 58542E45
old: 00000070: 00010054
new: 00000068: 6369746F
new: 0000006C: 68642E65
new: 00000070: 00010074
PATCH>EX/ASCII 68
00000068: 'otic'
PATCH>UPDATE
%PATCH-I-OVERLAY, DISK$STARWORK01:[NASR.PATCH]LOGIN.COM;1 being
overwritten
PATCH>EXIT
%PATCH-I-OVERLAY, DISK$STARWORK01:[NASR.PATCH]LOGIN.COM;1 being
overwritten
$
```

Example of a **PATCH/ABSOLUTE/NONEW\_VERSION** command. Note the error messages that are returned when the command tries to expand the file, and when the commands **UPDATE** and **EXIT** are performed; that is, (file) being overwritten.

3. \$ PATCH AVERAGE /JOURNAL=TEST /OUTPUT=TEST

This command invokes PATCH for an interactive PATCH session with the image file `AVERAGE.EXE`. The journal file and output image file created by this session are both named `TEST` and reside in the default device and directory. The journal file has a file type of `JNL`, and the output image file has a file type of `.EXE`.

4. \$ PATCH /UPDATE=(100,102) @ORION  
\$

This **PATCH** command executes the command procedure `ORION.COM`. The **/UPDATE** qualifier requests that only the patches identified by the ECO levels 100 and 102, contained in `ORION.COM`, be processed. The first record in `ORION.COM` must specify the input image file. The second DCL prompt (\$) indicates that the patches were successfully applied.

## PHONE

**PHONE** — Invokes the Phone utility, which lets you communicate with other users on your system or any other system connected to your system by DECnet-Plus or DECnet for OpenVMS. For more information about the Phone utility, see online help.

## Format

**PHONE**[*phone-command*]

# PIPE

**PIPE** — Executes one or more DCL command strings from the same command line. The **PIPE** command enables you to perform UNIX-style command processing, such as command pipelining, input/output redirection, and conditional and background execution.

## Format

**PIPE***command-sequence* [*separator command-sequence*]...

## Parameters

### *command-sequence*

A DCL command, a pipeline, or a subshell:

### **DCL command**

A DCL command string, which can include qualifiers, parameters, keywords, and values.

### **Pipeline**

A pipeline is a sequence of pipeline-segment commands connected by **pipes**, represented by the vertical-bar (|) separator. A pipeline-segment command is a DCL command that appears in a pipeline. The pipe connects the SYSS\$OUTPUT of one pipeline-segment command to the SYSS\$INPUT of the next command. The format of a pipeline is as follows:

```
pipeline-segment-command | pipeline-segment-command [|...]
```

### **Subshell**

A subshell is one or more command sequences separated by separators and enclosed in parentheses. The format of a subshell is as follows:

```
(command-sequence [separator command-sequence]...)
```

Input/output redirection is allowed in a command sequence. The command before an angle bracket (> or <) redefines its SYSS\$INPUT, SYSS\$OUTPUT, or SYSS\$ERROR during execution. You cannot use angle brackets (<>) to represent a directory specification in a **PIPE** command because the **PIPE** command interprets angle brackets as input/output redirection syntax.

### *separator*

Determines the processing action of the command sequences specified in a **PIPE** command. The valid **PIPE** separators are described in *Table 1, "PIPE Command Separators"*.

**Table 1. PIPE Command Separators**

| Separator | Action                                                                                                                                                                                                                                                                                               |
|-----------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|           | Key pipe separator. The pipe connects the SYSS\$OUTPUT of one pipeline-segment command to the SYSS\$INPUT of the next command.                                                                                                                                                                       |
| ;         | Sequential execution. The command sequence following the semicolon (;) is executed after the preceding command sequence is completed. You must precede this separator with a blank space; otherwise, it is parsed as the Record Management System (RMS) file specification version number delimiter. |

| Separator | Action                                                                                                                                                                                                                                                                                                                                                                                                   |
|-----------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| &&        | Conditional execution (upon success). The command sequence following the double ampersand (&&) is executed only if the preceding command sequence succeeds.                                                                                                                                                                                                                                              |
|           | Conditional execution (upon failure). The command sequence following the double vertical bar (  ) is executed only if the preceding command sequence fails.                                                                                                                                                                                                                                              |
| &         | Background execution. All command sequences that precede the ampersand (&) are executed asynchronously in a subprocess environment. The & separator is similar to the <b>SPAWN/NOWAIT</b> command.<br><br>Note that any ampersand that precedes a character string without spaces in between is parsed as a conventional DCL symbol substitution expression rather than the background execution syntax. |
| @TEE      | Command file, TEE.COM. Used for redirecting output to two targets (for example, one output is directed to the next stage in pipeline, and the other to a file). See the <a href="#">Examples</a> section for an example of how to use TEE.COM.                                                                                                                                                           |

In a **PIPE** command line, the "&" has the highest precedence, followed by "|", ";", "&&", and "||", which have equal precedence.

## Description

The **PIPE** command allows you to perform UNIX-style command processing by executing multiple DCL commands in a single command line. You can use the **PIPE** command to execute DCL commands in a number of ways:

### Multiple command execution

Multiple DCL commands are specified in a single PIPE command and executed sequentially. The syntax for multiple command execution is as follows:

```
PIPE    command-sequence ; command-sequence [ ; command-sequences ] ...
```

### Conditional command execution

A command sequence is executed conditionally depending on the execution result of the preceding command sequence.

Using the following form, *command-sequence2* only executes if *command-sequence1* succeeds:

```
PIPE    command-sequence1    &&    command-sequence2
```

Using the following form, *command-sequence2* only executes if *command-sequence1* fails:

```
PIPE    command-sequence1    ||    command-sequence2
```

### Pipeline command execution

A pipeline is formed by connecting DCL commands with pipes as follows:

```
PIPE    pipeline-segment-command | pipeline-segment-command [ | ... ]
```

Each pipeline-segment command runs in a separate subprocess with its SYS\$OUTPUT connected to the SYS\$INPUT of the next pipeline-segment command. These subprocesses execute in parallel;

however, they are synchronized to the extent that each pipeline-segment command, except the first, reads the standard output of its predecessor as its standard input. A pipeline finishes execution when the last pipeline-segment command is done.

It is very common to use filter applications in a pipeline. A filter application is a program that takes data from `SY$INPUT`, transforms it in a specific way, and writes it to `SY$OUTPUT`.

### Subshell execution

Command sequences can be executed in a subprocess environment by using the subshell execution form:

```
PIPE    ( command-sequence [separator command-sequence]... )
```

The command sequences in a subshell are executed in a subprocess environment. DCL waits for the subshell to complete before executing the next command sequence. The `( )` separator is similar to the **SPAWN/WAIT** command.

### Background execution

Command sequences can be executed in a subprocess environment by using the following form:

```
PIPE    command-sequence [ separator command-sequence]...  &
```

DCL does not wait for the command sequences to finish. Control passes back to DCL once the background subprocess is created.

### Input/output redirection

A command sequence can redirect its `SY$INPUT`, `SY$OUTPUT`, or `SY$ERROR` to a file during execution of the command as follows:

To redirect `SY$INPUT`:

```
PIPE    command-sequence < redirected-input-file
```

To redirect `SY$OUTPUT`:

```
PIPE    command-sequence > redirected-output-file
```

To redirect `SY$ERROR`:

```
PIPE    command-sequence 2> redirected-error-file
```

A pipeline-segment command can also redirect its `SY$INPUT`, `SY$OUTPUT`, or `SY$ERROR`; however, `SY$OUTPUT` redirection is allowed only for the last pipeline-segment command, and `SY$INPUT` redirection is allowed only for the first pipeline-segment command.

You can interrupt a **PIPE** command by pressing **Ctrl/Y**. If the **PIPE** command is executing in a pipeline or a subshell command sequence, the command sequence and the **PIPE** command are deleted. In this case, a **CONTINUE** command entered immediately after the interrupt will not resume the execution of the **PIPE** command.

If the **PIPE** command is executing a command sequence other than a subshell or a pipeline command sequence, DCL behaves as if the command sequence were entered as a DCL command without the **PIPE** command verb and interrupted by **Ctrl/Y**. See the relevant section in the [VSI OpenVMS User's Manual \[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#\\_46\\_CTRLYINTERRUPTS\]](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#_46_CTRLYINTERRUPTS) for more information on the **Ctrl/Y** interrupt.

Each command sequence sets the global symbol `$STATUS` with a returned value after it finishes execution. The return status of the **PIPE** command is the return status of the *last* command performed in the last segment. If all segments fail with some kind of error and the last segment returns with success, the status returned to DCL is the success.

When a **PIPE** command is executed in a command procedure with the ON condition processing, the conditional execution of command sequences (`&&`, `||`) takes precedence over the action previously specified by the ON condition statement.

## DCL Command Restrictions

The **PIPE** command creates a special execution context for its command sequences. The following DCL commands either do not work or exhibit new behavior in this context:

- **PIPE** – Nested **PIPE** commands in the same command procedure level are not allowed. There can only be one **PIPE** command context for each command procedure level; however, nested **PIPE** commands at different procedure levels are allowed. For example:

```
$ TYPE FOO.COM
$ ! FOO.COM
$ :
$ PIPE    ...
$ :
$
$ PIPE    @FOO.COM ; ...
```

In this example, the **PIPE** command inside `FOO.COM` is allowed because it is executed at a different command procedure level.

- **GOTO** and **EXIT** – These two commands, when executed as **PIPE** command sequences, delete the **PIPE** command context before the **GOTO** or **EXIT** command is executed. Any command sequences following these two commands in a **PIPE** command are flushed.
- **STOP** – The **STOP** command, when executed after a **PIPE** command is interrupted by **Ctrl/Y**, deletes the **PIPE** command context.
- **THEN**, **ELSE**, **ENDIF**, **SUBROUTINE**, **ENDSUBROUTINE**, **RETURN**, and DCL labels – These commands cannot execute as **PIPE** command sequences because it is not possible to realize their functions in a **PIPE** command context.

## Improving Subprocess Performance

A **PIPE** command can generate a number of subprocesses during execution. Often, the applications invoked by command sequences do not depend on the process logical names and symbol names. In this case, the spawning of subprocesses can be accelerated by using the **/NOLOGICAL\_NAMES** and **/NOSYMBOLS** qualifiers, which suppress the passing of process logical names and symbols to the subprocesses created by the **PIPE** command.

## Input/Output Redirection

DCL users can use the **DEFINE** or **ASSIGN** command to redirect `SY$INPUT`, `SY$OUTPUT`, or `SY$ERROR`. Such redirection can be created as either the user-mode (using the **/USER\_MODE** qualifier) or supervisor-mode (using the **/SUPERVISOR\_MODE** qualifier) redirection. A user-mode redirection only affects the environment of the next user-mode image.

In a **PIPE** command, redirection can be achieved by using the redirection syntax. A **PIPE** command redirection is quite different from that created by the **DEFINE** or **ASSIGN** command, as follows:

- Redirections are created in supervisor mode. This means that both user-mode applications and DCL commands are affected by the redirections.
- The redirected environment only applies to the command sequence or the pipeline-segment command that specifies the redirection syntax. After the execution of the command sequence or pipeline-segment command, the original process input/output environment (that is, SYS\$INPUT, SYS\$OUTPUT, and SYS\$ERROR) is restored before command execution continues.

When SYS\$OUTPUT is redirected, the redirected output file is always created, whether or not the command sequence actually writes to SYS\$OUTPUT. If a version of a file with the same name as the redirected output file already exists, a new version of that file is created. (This behavior is the same as using the **DEFINE** or **ASSIGN** command to redefine SYS\$OUTPUT in supervisor mode.) Note that the redirected file is created before the command sequence is executed. If the redirected file is also used in the command sequence, the operation may fail, as in the following example:

```
$ TYPE FOO.COM
$ ! FOO.COM
$ :
$ PIPE ...
$ :
$
$ PIPE @FOO.COM ; ...
```

In this example, a new version of TRANS.LOG is created and opened for write access; the **SEARCH** command then tries to get read access to the most recent version of TRANS.LOG instead of the expected previous version.

When SYS\$ERROR is redirected, the redirected error file is only created when the command sequence actually writes to the SYS\$ERROR during execution, and there is no existing file with the same name as the redirected error file. If a file with the same name as the redirected error file already exists, that file is opened as the redirected error file. The error output generated by this command sequence is then appended to the end of the redirected error file. (This behavior is the same as using the **DEFINE** or **ASSIGN** command to redefine SYS\$ERROR in supervisor mode.)

## Pipelines and TEEs

This section describes aspects of DCL that function differently in the context of a pipeline.

Some of the following constructs are used in the implementation of a TEE.

### Using SYS\$COMMAND

The SYS\$COMMAND of a subprocess is normally the same as its SYS\$INPUT (if no command procedures are involved). In a pipeline, however, the SYS\$COMMAND of a subprocess is set to the SYS\$COMMAND of the parent process instead of to the preceding pipe (which is the SYS\$INPUT of the pipeline-segment command).

### Using TEEs and SYS\$PIPE

In most cases, input from the pipe can be obtained by reading the data from SYS\$INPUT; however, when a command procedure is invoked as a pipeline segment command, SYS\$INPUT is redirected to the command procedure file. To obtain data from the pipe inside a command procedure, the logical SYS\$PIPE can be used.

The following is an example of a pipeline DCL application TEE.COM:

```
$ ! TEE.COM - command procedure to display/log data flowing through
$ ! a pipeline
$ ! Usage: @TEE log-file
$
$ OPEN/WRITE tee_file 'P1'
$ LOOP:
$ READ/END_OF_FILE=EXIT SYS$PIPE LINE
$ WRITE SYS$OUTPUT LINE ! Send it out to the next stage of the pipeline
$ WRITE tee_file LINE ! Log output to the log file
$ GOTO LOOP
$ EXIT:
$ CLOSE tee_file
$ EXIT
```

The **PIPE** command to use TEE.COM can be:

```
$ PIPE SHOW SYSTEM | @TEE showsys.log | SEARCH SYS$INPUT LEF
```

The command procedure TEE.COM is used to log the data flowing through the pipeline. It reads in the data from SYS\$PIPE instead of SYS\$INPUT.

## Image Verification in a Pipeline

In a pipeline, image verification is turned off by default, even when the command **SET VERIFY=IMAGE** is executed before the **PIPE** command is entered. This prevents duplication of data records going through the pipeline.

To turn on image verification in a pipeline, an explicit **SET VERIFY=IMAGE** command must precede the pipeline segment command. You can use a subshell to do this, as follows:

```
$ PIPE ... | (SET VERIFY=IMAGE ; ...) | ...
```

## File Access Methods in a Pipeline

A pipeline segment command can only use the RMS sequential file access method to read and write to the pipes. Certain OpenVMS utilities may access their input and output files using methods other than sequential access. These operations are not supported in a pipeline, and will fail, as in the following example:

```
$ PIPE CC/NOOBJ/NOLIS TEST.C | SEARCH SYS$INPUT/WIND=(1,1) "%CC-W-"
%SEARCH-F-RFAERR, RMS error using RFA access
-RMS-F-RAC, invalid record access mode
```

In this example, the **/WINDOW** qualifier for the **SEARCH** command requires the relative file access method.

## Qualifiers

**/LOGICAL\_NAMES (default)**

**/NOLOGICAL\_NAMES**

Copies process logical names and logical name tables to the subprocess of a command sequence. By default, all process logical names and logical name tables are copied to the subprocess except those explicitly marked **CONFINE** or created in executive or kernel mode.

**/PRIVILEGES={CURRENT|AUTHORIZED}**

Determines whether the subprocess inherits the current process's current or authorized privileges as its authorized privileges. By default, the authorized privilege mask for the subprocess is taken from the current privileges of its creator. (This corresponds to **/PRIVILEGES=CURRENT**.) If the **/PRIVILEGES=AUTHORIZED** qualifier is specified, the subprocess's authorized privileges are taken from the creator's authorized privileges.

**/SYMBOLS (default)****/NOSYMBOLS**

Determines whether global and current procedure level local symbols (except \$RESTART, \$SEVERITY, and \$STATUS) are passed to the subprocess. \$RESTART, \$SEVERITY, and \$STATUS symbols are never passed to the subprocess.

**/TRUSTED****/NOTRUSTED**

Indicates that the **PIPE** command input originates in a trusted command procedure. **PIPE** commands are not allowed in CAPTIVE accounts. The **/TRUSTED** qualifier provides a way for properly written captive command procedures to perform **PIPE** operations when the command input originates in the captive command procedure where it can be trusted. For more information about trusted command procedures, see the *VSI OpenVMS Guide to System Security* [<https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/>].

## Examples

1. `$ PIPE SHOW SYSTEM | SEARCH SYS$INPUT HIB`

This example uses the pipeline function to identify all hibernating processes on the system in one command.

2. `$ PIPE RUN TEST | SORT/SPECIFICATION=TEST.SRT SYS$INPUT SYS$OUTPUT -  
| DIFF SYS$INPUT TEST.BENCHMARK`

This example uses the pipeline function to run a test, sort the result, and compare the result to the benchmark file in a single command without generating unnecessary intermediate files.

3. `$ PIPE ( SET DEF WRK$:[WORK] ; RUN REPORT ) | MAIL SYS$INPUT SMITH`

This example shows one way a subshell can be specified as a pipe segment command in a pipeline.

4. `$ more == TYPE/PAGE=SAVE SYS$INPUT  
$ PIPE ANA/RMS PAGE.TXT | more`

```
Check RMS File Integrity
SYS$SYSDEVICE:[TEST]PAGE.TXT;2
```

26-DEC-2001 16:12:00.06 Page 1

FILE HEADER

```
File Spec: SYS$SYSDEVICE:[TEST]PAGE.TXT;2
File ID: (4135,58220,0)
Owner UIC: [PIPE]
Protection: System: RWED, Owner: RWED, Group: RE, World:
Creation Date: 26-NOV-2001 16:08:50.05
Revision Date: 26-NOV-2001 16:09:09.06, Number: 1
Expiration Date: none specified
```

```
Backup Date:      none posted
Contiguity Options: none
Performance Options: none
Reliability Options: none
Journaling Enabled: none
```

RMS FILE ATTRIBUTES

RETURN/SPACE=More, PREV/NEXT=Scroll, INS/REM=Pan, SELECT=80/132, Q=Quit

This example shows the use of the **/PAGE** qualifier within a pipeline. The **/PAGE** function exists in a number of other DCL commands as well, and can be used similarly in conjunction with the **PIPE** command to form other useful tools.

```
5. $ ! TEE.COM - command procedure to display/log data flowing through
$ !           a pipeline
$ ! Usage: @TEE log-file
$
$ OPEN/WRITE tee_file 'P1'
$ LOOP:
$ READ/END_OF_FILE=EXIT SYS$PIPE LINE
$ WRITE SYS$OUTPUT LINE ! Send it out to next stage of the pipeline
$ WRITE tee_file LINE ! Log output to the log file
$ GOTO LOOP
$ EXIT:
$ CLOSE tee_file
$ EXIT
```

This is an example of a pipeline DCL application TEE.COM.

The **PIPE** command to use TEE.COM can be:

```
$ PIPE SHOW SYSTEM | @TEE showsys.log | SEARCH SYS$INPUT LEF
```

The command procedure TEE.COM is used to log the data flowing through the pipeline. It reads in the data from SYS\$PIPE instead of SYS\$INPUT.

```
6. $ CD_WORK := PIPE SAVE_DIR=F$DIRECTORY() ; SET DEFAULT FOO:[WORK]
$ BACK := SET DEF 'SAVE_DIR'
$
$ CD_WORK ! Switch to working directory
$ :
$ :
$ BACK ! Switch back to home directory

$ GET_RECORD := PIPE READ/END_OF_FILE=CLEANUP IN RECORD ; -
F$EDIT(RECORD, "COMPRESS, TRIM")
$
$ OPEN IN EMPLOYEE.DAT
$ LOOP:
$ GET_RECORD
$ :
$ :
$ GOTO LOOP
$
$ CLEAN_UP:
$ :
```

This example shows two simple uses of multiple commands with symbol definitions to build useful tools in command procedures.

7. `$ PIPE cc foo.c && link foo`

If the compilation does not generate any error, the object file is linked to produce an executable image. If the program compilation generates an error, the linking step is skipped.

8. `$  
$ PIPE RUN COLLECT_DATA.EXE || GOTO CLEAN_UP  
$ :  
$ :  
$ EXIT  
$  
$ CLEAN_UP :  
$ :  
$ :`

Using conditional command execution, it is easy to set up simple error handling control flow in a command procedure. If the image COLLECT\_DATA fails, control is directed to CLEAN\_UP.

9. `$ PIPE COPY LARGE_FILE.DAT REMOTE"user password"::[DESTINATION]*.* &`

This **PIPE** command creates a background process to handle the copying of the large file.

10. `$ PIPE (SET DEF [.DATA_DIR] ; BACKUP DATA.SAV/SAV [...]) ; RUN FOO`

The subshell command sequence is done in a subprocess. This means that changing a process-specific characteristic (for example, the default directory) will not affect the current process after the subshell is finished. In this example, the save set is restored in a subdirectory to provide the necessary data to run the program FOO.

11. `$ RSH 0 PIPE SH DEC/FI | SH LOG/PR`

```
LNMS$PROCESS_TABLE  
  
"SYS$COMMAND" = "_NODE$MPA24:"  
"SYS$DISK" = "SYS$SYSDEVICE:"  
"SYS$ERROR" = "_BG9930:"  
"SYS$INPUT" [super] = "_BG9930:"  
"SYS$INPUT" [exec] = "_NODE$MPA24:"  
"SYS$OUTPUT" [super] = "_BG9930:"  
"SYS$OUTPUT" [exec] = "_BG9930:"  
"SYS$PIPE" = "_NODE$MPA24:"  
"TT" = "_MPA24:"
```

This example shows how SYS\$PIPE and SYS\$OUTPUT might differ.

## PPPD

PPPD — Invokes the Point-to-Point Protocol utility (PPPD) that you can use to initiate and manage an Internet Protocol (IP) network connection over an asynchronous, serial data line.

## Format

**PPPD**[ *subcommand* ] . . .

## Description

PPPD extends the networking capability of OpenVMS Alpha by enabling you to do the following:

- Establish temporary, high-speed network connections between remote hosts. This includes both *dial-in* capability from a remote host to an OpenVMS Alpha host and *dial-out* capability from an OpenVMS Alpha host to a remote system or server box that supports the Point-to-Point Protocol (PPP).
- Establish permanent, low-speed network connections between local hosts, such as between a laptop computer and an Alpha workstation connected by a serial data line.
- Set and display communication characteristics, such as address compression, flow control, and line speed.

---

## Note

This utility is enabled by your TCP/IP software during the network registration process. If you receive one of the following error messages, contact your system administrator to verify whether PPPD is currently available on your network.

```
%PPPD-E-PPPNOTAVAIL, point-to-point driver is not installed
%PPPD-E-NOTREG, network protocol has not been registered
```

For information about network registration, see the [SET NETWORK](#) command and see the *VSI OpenVMS System Management Utilities Reference Manual, Volume 2: M-Z* [<https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/>].

---

For a complete description of PPPD, see the relevant section in the *VSI OpenVMS System Management Utilities Reference Manual, Volume 2: M-Z* [<https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/#d0e8479>].

For detailed information about the asynchronous (ASN) and PPP device drivers that support this utility, see the documentation contained in the files PPP\_INTERFACES.PS and PPP\_INTERFACES.TXT located in the SYS\$SYSROOT:[SYSHLP.EXAMPLES.PPPD.DOC] directory.

## PRINT

**PRINT** — Queues one or more files for printing to an output queue. **Requires read (R) access to the file and submit (S) access to the queue. To specify functions unique to particular print symbionts, use the /PARAMETERS qualifier.**

## Format

```
PRINTfilespec[,...]
```

## Parameter

```
filespec[,...]
```

Specifies one or more files to be printed. The asterisk (\*) and the percent sign (%) wildcard characters are allowed in the directory specification, file name, file type, and version number fields. The default file

type is that of the preceding file. If no previous file specification contains an explicit file type, the default file type is .LIS.

If you specify more than one file, separate the file specifications with either commas (,) or plus signs (+).

If you specify a node name, you must use the **/REMOTE** qualifier.

## Description

The **PRINT** command places the specified files in an output queue for printing. By default, this queue is SYS\$PRINT. All files queued by a single **PRINT** command are processed serially as one job. By default, the name of the print job is the name of the first file specified in the **PRINT** command.

The system assigns a unique **entry number** to each print job in the queue. When you enter the **PRINT** command, by default, the system displays the job name, the queue name, the entry number, and the job status.

The system automatically creates or updates the local symbol \$ENTRY when a **PRINT** or **SUBMIT** command is completed successfully. The value of \$ENTRY is a string that identifies the entry number of the most recently queued job. If you want to refer to a job's entry number later, store the value of \$ENTRY in another symbol.

After you queue a print job, the version of the file submitted is printed, even if a newer version of the file is created before the print job runs. Also, another file with the same name and version number as the file queued cannot be substituted for the file that was queued.

## Qualifiers

**/AFTER=*time***

**/NOAFTER**

Holds the job until the specified time. The time can be specified as absolute time or a combination of absolute and delta times. If the specified time has passed, the job is queued for printing immediately.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\\_AND\\_TIME\\_SECT](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT)] or the online help topic Date.

**/BACKUP**

**/NOBACKUP**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/BACKUP** qualifier selects files according to the dates of their most recent backups. This qualifier is incompatible with the **/CREATED**, **/EXPIRED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

**/BEFORE[=*time*]**

**/NOBEFORE**

Selects only those files dated prior to the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: BOOT, LOGIN, TODAY (default), TOMORROW, or YESTERDAY. Specify one of the following qualifiers with the

**/BEFORE** qualifier to indicate the time attribute to be used as the basis for selection: **/BACKUP**, **/CREATED** (default), **/EXPIRED**, or **/MODIFIED**.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic Date.

**/BURST[=keyword]**  
**/NOBURST**

Positional qualifier.

Controls whether two file flag pages with a burst bar between them are printed preceding a file. If the **/BURST** qualifier is specified between the **PRINT** command and the file specifications, it can take either of the following keywords:

|     |                                                                         |
|-----|-------------------------------------------------------------------------|
| ALL | Prints the flag pages and a burst bar before each file in the job.      |
| ONE | Prints the flag pages and a burst bar before the first file in the job. |

If you want the **/BURST** qualifier to apply to individual files in a multi-file job, place the qualifier directly after each file that you want to have the flag pages and a burst bar.

Use the **/[NO]BURST** qualifier to override the **/DEFAULT** options that have been set for the output queue you are using. The **/[NO]BURST** qualifier does not override the **/SEPARATE** options set for the queue.

When you specify the **/BURST** qualifier for a file, the **/[NO]FLAG** qualifier does not add or subtract a flag page from the two flag pages that are printed preceding a file.

**/BY\_OWNER[=uic]**  
**/NOBY\_OWNER**

Selects only those files whose owner user identification code (UIC) matches the specified owner UIC. The default UIC is that of the current process.

Specify the UIC by using standard UIC format as described in the relevant section in the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC_SECTION) [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC\_SECTION].

**/CHARACTERISTICS= (characteristic[,...])**

Specifies the name or number of one or more characteristics to be associated with the job. Characteristics can refer to such things as color of ink. If you specify only one characteristic, you can omit the parentheses.

A characteristic's number must range from 0 to 127. To see which characteristics have been defined for your system, use the **SHOW QUEUE/CHARACTERISTICS** command. To see which characteristics are associated with a particular queue, use the **SHOW QUEUE/FULL** command.

A print job can be processed on an execution queue if the job's characteristics are a subset of the queue's characteristics. However, if any of the characteristics associated with the job are not associated with the queue, the job remains pending until one or more of the following occurs:

- The characteristics specified with the queue are changed to make the job's characteristics a subset of the queue's characteristics (using, for example, the **SET QUEUE/CHARACTERISTICS** command).

- The characteristics specified with the job are changed to make the job's characteristics a subset of the queue's characteristics (using, for example, the **SET ENTRY/CHARACTERISTICS** command).
- The job is moved to a queue on which all the job's characteristics have been specified (using, for example, the **SET ENTRY/REQUEUE** command).
- The job is deleted (using, for example, the **DELETE/ENTRY** command).

**/CONFIRM****/NOCONFIRM (default)**

Controls whether a request is issued before each file is queued for printing to confirm that the operation should be performed on that file. The following responses are valid:

|      |       |               |
|------|-------|---------------|
| YES  | NO    | QUIT          |
| TRUE | FALSE | <b>Ctrl/Z</b> |
| 1    | 0     | ALL           |

**Return**

You can use any combination of uppercase and lowercase letters for word responses. Word responses can be abbreviated to one or more letters (for example, T, TR, or TRU for TRUE), but these abbreviations must be unique. Affirmative answers are YES, TRUE, and 1. Negative answers include: NO, FALSE, 0, and pressing **Return**. Entering QUIT or pressing **Ctrl/Z** indicates that you want to stop processing the command at that point. When you respond by entering ALL, the command continues to process, but no further prompts are given. If you type a response other than one of those in the list, DCL issues an error message and redisplay the prompt.

**/COPIES=*n***

Positional qualifier.

Specifies the number of copies to print. The value of the parameter *n* can be from 1 to 255 and defaults to 1. If you place the **/COPIES** qualifier after the **PRINT** command name, each file in the parameter list is printed the specified number of times. If you specify the **/COPIES** qualifier following a file specification, only that file is printed the specified number of times.

**/CREATED (default)****/NOCREATED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/CREATED** qualifier selects files based on their dates of creation. This qualifier is incompatible with the **/BACKUP**, **/EXPIRED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

**/DELETE****/NODELETE (default)**

Positional qualifier.

Controls whether files are deleted after printing. If you place the **/DELETE** qualifier after the **PRINT** command name, all specified files are deleted. If you specify the **/DELETE** qualifier after a file specification, only that file is deleted after it is printed.

The protection applied to the file must allow delete (D) access for the life of the job. You need to have delete access when you submit the job and delete access when the system deletes your file at the end of the job.

**/DEVICE=queue-name[:]**

Places the print job in the specified queue (rather than the default queue SYSS\$PRINT). This qualifier is synonymous with the **/QUEUE** qualifier, except that the **/DEVICE** qualifier is reserved for special use by VSI. Its usage, therefore, is not recommended.

**/EXCLUDE=(filespec[,...])****/NOEXCLUDE**

Excludes the specified files from the print operation. You can include a directory but not a device in the file specification. The asterisk (\*) and the percent sign (%) wildcard characters are allowed in the file specification; however, you cannot use relative version numbers to exclude a specific version. If you specify only one file, you can omit the parentheses.

**/EXPIRED****/NOEXPIRED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/EXPIRED** qualifier selects files according to their expiration dates. (The expiration date is set with the **SET FILE/EXPIRATION\_DATE** command.) The **/EXPIRED** qualifier is incompatible with the **/BACKUP**, **/CREATED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

**/FEED****/NOFEED**

Positional qualifier.

Controls whether form feeds are inserted into the print job when the printer reaches the bottom margin of the form in use. You can suppress this automatic form feed (without affecting any of the other carriage control functions that are in place) by using the **/NOFEED** qualifier. The **/[NO]FEED** qualifier does not affect user-formatted files and can be used to override the installation-defined defaults that have been set for the output queue you are using.

**/FLAG[=keyword]****/NOFLAG**

Positional qualifier.

Controls whether a file flag page is printed preceding a file. The flag page contains the name of the user submitting the job, the job entry number, and other information about the file being printed. If the **/FLAG** qualifier is positioned between the **PRINT** command and the file specifications, it can take either of the following keywords:

| Keyword | Description                                               |
|---------|-----------------------------------------------------------|
| ALL     | Prints a file flag page before each file in the job.      |
| ONE     | Prints a file flag page before the first file in the job. |

If you want the **/FLAG** qualifier to apply to individual files in a multi-file job, place the qualifier directly after each file that you want to have a flag page.

Use the **/[NO]FLAG** qualifier to override the **/DEFAULT=[NO]FLAG** option that has been set for the output queue you are using. The **/[NO]FLAG** qualifier does not override the **/SEPARATE=[NO]FLAG** option set for the queue.

When you specify the **/BURST** qualifier for a file, the **/[NO]FLAG** qualifier does not add or subtract a flag page from the two flag pages that are printed preceding the file.

### **/FORM=*form***

Specifies the name or number of the form to be associated with the print job. If you omit the **/FORM** qualifier, the default form for the execution queue is associated with the job.

Forms have attributes such as print image width and length or paper stock, which the print symbiont associates with a job when the job is processed. To see which forms have been defined for your system, use the **SHOW QUEUE/FORM** command. To find out which form is mounted currently on a particular queue and which form is specified as that queue's default form, use the **SHOW QUEUE/FULL** command.

The stock of the form associated with the job must match the stock of the form mounted on the execution queue on which you want the job to be processed. If the stocks do not match, the job remains pending until one or more of the following occurs:

- A form with the same stock as the job's form is mounted on the queue (using, for example, the **SET QUEUE/FORM\_MOUNTED** command).
- A form with the same stock as the queue's mounted form is specified with the job (using, for example, the **SET ENTRY/FORM** command).
- The job is moved to a queue on which the stock of the mounted form matches the stock of the job's form (using, for example, the **SET ENTRY/REQUEUE** command).
- The job is deleted (using, for example, the **DELETE/ENTRY** command).

### **/HEADER**

#### **/NOHEADER (default)**

Positional qualifier.

Controls whether a heading line is printed at the top of each page.

### **/HOLD**

#### **/NOHOLD (default)**

Controls whether a job is available for printing immediately. The **/HOLD** qualifier holds the job until released by a **SET ENTRY/RELEASE** or **SET ENTRY/NOHOLD** command.

### **/IDENTIFY (default)**

#### **/NOIDENTIFY**

Displays the job name, queue name, entry number, and status of the job when it is queued.

### **/JOB\_COUNT=*n***

Prints the job *n* times. The value of the parameter *n* can be from 1 to 255 and defaults to 1.

**/LOWERCASE****/NOLOWERCASE (default)**

Indicates whether the print job must be printed on a printer that can print both lowercase and uppercase letters. The **/NOLOWERCASE** qualifier means that files can be printed on printers supporting only uppercase letters. If all available printers can print both uppercase and lowercase letters, you do not need to specify the **/LOWERCASE** qualifier.

**/MODIFIED****/NOMODIFIED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/MODIFIED** qualifier selects files according to the dates on which they were last modified. This qualifier is incompatible with the **/BACKUP**, **/CREATED**, and **/EXPIRED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time modifiers, the default is the **/CREATED** qualifier.

**/NAME=*job-name***

Names the job. The name consists of 1 to 39 alphanumeric characters. If characters other than alphanumerics, underscores (`_`), or dollar signs (`$`) are used in the name, enclose the name in quotation marks (`" "`). The default is the name of the first (or only) file in the job. The job name appears in the **SHOW ENTRY** and **SHOW QUEUE** command display and is printed on the flag page for the job.

**/NOTE=*string***

Specifies a message string of up to 255 characters to appear on the flag page of the job.

**/NOTIFY****/NONOTIFY (default)**

Controls whether a message is broadcast to your terminal session when the job is printed or aborted.

**/OPERATOR=*string***

Specifies a message of up to 255 characters to be sent to the operator when the job begins to print.

**/PAGES=(*[lowlim],[uplim]*)**

Positional qualifier.

Specifies the number of pages to print for the specified job. You can use the **/PAGES** qualifier to print portions of long files. By default, all pages of the file are printed.

The *lowlim* specifier refers to the first page in the group of pages that you want printed for that file. If you omit the *lowlim* specifier, the printing starts on the first page of the file.

The *uplim* specifier refers to the last page of the file that you want printed. If you want to print to the end of the file, but do not know how many pages the file contains, use quotation marks (`" "`) as the *uplim* specifier. You can omit the parentheses if you are including only a specific value for the *uplim* specifier. For example, **/PAGES=10** prints the first ten pages of the file; **/PAGES=(5,10)** prints pages 5 through 10; **/PAGES=(5,"")** starts printing at page 5 in the file and continues until the end of the file is reached.

**/PARAMETERS=** (*parameter*[(=value[,...])] [,...])

Specifies from 1 to 8 optional parameters that are unique to a particular print symbiont. Each parameter and its values are passed as a single text string directly to the print symbiont: logical names and DCL symbols are not translated by the **PRINT** command.

Each parameter can take from 1 to 8 values for a total of 255 characters. If you specify only one parameter or parameter value, you can omit the parentheses. Enclose parameter values containing lowercase letters or non-alphanumeric characters (such as spaces, parentheses, or commas) in quotation marks.

You can specify the **/PARAMETERS** qualifier only once in each **PRINT** command. For example, in the command **PRINT /PARAMETERS=(JJJ, KK) /PARAMETERS=(LL, MMM)**, the JJJ and KK are ignored because the second occurrence of the **/PARAMETERS** qualifier supersedes the first occurrence.

For information on parameters available for printing to PostScript printers using *DECprint Supervisor* software (DCPS), see the DCL Help topic **PRINT\_Parameter**.

**/PASSALL****/NOPASSALL** (default)

Positional qualifier.

Specifies whether the symbiont bypasses all formatting and sends the output QIO to the driver with format suppressed. All qualifiers affecting formatting, as well as the **/HEADER**, **/PAGES**, and **/SETUP** qualifiers, are ignored.

If the **/PASSALL** qualifier is placed between the **PRINT** command and any file specifications, all files are printed in PASSALL mode. To specify the **/PASSALL** qualifier for only some files in the job, place the qualifier after each file that you want printed in PASSALL mode.

**/PRIORITY=n**

Requires OPER (operator) or ALTPRI (alter priority) privilege to raise the priority above the queue's maximum scheduling priority.

Specifies the job-scheduling priority of the print job. The value of the parameter *n* can be from 0 through 255, where 0 is the lowest priority and 255 is the highest. The default value of *n* is the value of the system parameter DEFQUEPRI. No privilege is needed to set the priority lower than the queue's maximum scheduling priority.

**/QUEUE=queue-name[:]**

Queues the job to the specified output queue. The default queue is SYS\$PRINT. This qualifier is synonymous with the **/DEVICE** qualifier.

**/REMOTE**

Queues the job to SYS\$PRINT on the remote node specified in the file specification; the file *must* exist on the remote node. When you use the **/REMOTE** qualifier, you *must* include the node name in the file specification.

You can specify only the following qualifiers with the **/REMOTE** qualifier:

**/BACKUP**

**/BEFORE**  
**/BY\_OWNER**  
**/CONFIRM**  
**/CREATED**  
**/EXCLUDE**  
**/EXPIRED**  
**/MODIFIED**  
**/SINCE**

Note that, unlike the printing on the local node, multiple files queued by a single **PRINT/REMOTE** command are considered separate jobs.

**/RESTART (default)**  
**/NORESTART**

Indicates whether a job restarts after a system failure or after a **STOP/QUEUE/REQUEUE** command.

**/RETAIN=option**

Specifies the circumstances under which you want your jobs to be retained in a queue. When a job is retained in the queue, you can issue the **SHOW QUEUE** command after the job completes to see the status of the job. Without job retention, no record of a job is left in a queue after a job completes.

Use the following options to specify job retention:

- **ALWAYS** – Holds the job in the queue regardless of the job's completion status.
- **DEFAULT** – Holds the job in the queue as specified by the queue's retention policy.
- **ERROR** – Holds the job in the queue only if the job completes unsuccessfully.
- **UNTIL=time-value** – Holds the job in the queue for the specified length of time, regardless of the job's completion status.

---

## Note

You cannot specify a **/NORETAIN** qualifier with the **PRINT** command (as system managers can with the commands **INITIALIZE/QUEUE**, **START/QUEUE**, and **SET QUEUE**); however, you can specify **/RETAIN=DEFAULT** with the **PRINT** command. The default option holds the job in the queue as specified by the queue's retention policy. If the system manager has not specified retention for the queue, the job is not retained.

---

## How Job Retention Is Determined

Although you can specify job retention options for your own jobs, the job retention option you specify may be overridden by the job retention option of the queue on which your job executed. If you submit or print a job to a generic queue, the generic queue's job retention setting may also override the job retention option you specify. This section describes how job retention is determined.

An execution queue's job retention setting takes precedence over a generic queue's job retention setting; however, if the job's completion status does not match the job retention setting (if any) on the execution queue, then the generic queue's job retention setting attempts to control job retention. If the job's completion status does not match the job retention setting (if any) on the generic queue,

then the user-specified job retention setting is used. Jobs submitted directly to execution queues are not affected by job retention settings on generic queues.

If the execution queue's retention setting applies, the job is retained on the execution queue. Likewise, if the generic queue's retention setting applies, the job is retained on the generic queue. If the user-specified setting applies, the job is retained in the queue to which it was submitted.

The following example illustrates how the queue manager determines job retention:

Suppose you submit a job to a generic queue and specify **/RETAIN=ALWAYS**, and the job completes successfully.

First, the queue manager compares the job's completion status to the execution queue's retention setting. Suppose the queue is set with **/RETAIN=ERROR** (retains only jobs that complete unsuccessfully). The job is not retained in the execution queue because the error condition was not met.

The queue manager then compares the job's completion status to the generic queue's retention setting. Suppose the generic queue has no retention setting. The queue manager's comparison again fails to retain the job.

Finally, the queue manager compares the job's completion status to the retention setting you specified for the job. This comparison reveals that the job should be retained. Because the user-specified setting leads the queue manager to retain the job, the job is held in the queue to which the job was submitted – in this case, the generic queue.

For more information on types of queues, see the **INITIALIZE/QUEUE** command in the [VSI OpenVMS DCL Dictionary: A-M \[https://docs.vmsssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\\_119\]](https://docs.vmsssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_119). For more information on setting retention options for queues, see the **START/QUEUE** or **SET QUEUE** command, or the **INITIALIZE/QUEUE** command in the [VSI OpenVMS DCL Dictionary: A-M \[https://docs.vmsssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\\_119\]](https://docs.vmsssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_119).

## Timed Retention

Timed retention, which you specify using the **UNTIL=time-value** option, allows you to retain a job in the queue only as long as you need it. This eliminates the need to delete the job from the queue later.

For example, the following command retains the print job MYFILE in the queue until 7 : 31 on December 14, when the job will automatically be deleted from the queue.

```
$ PRINT/RETAIN=UNTIL=14-DEC-2001:07:31:0.0 MYFILE.DAT
```

However, depending on the queue's job retention policy, the job might be retained indefinitely. The job retention policy set on the queue takes precedence over the user-specified job retention setting. Because system managers cannot specify timed job retention for a queue, any jobs retained as a result of a queue's setting are retained indefinitely.

If you specify the **/RETAIN=UNTIL=time-value** option, you must supply a time value. The time value is first interpreted as a delta time, then as a combination time, and finally as absolute time. If you specify a delta time, the delta begins when the job completes. For example, if you specify **PRINT/RETAIN=UNTIL="+3:00"**, the job will be retained for three hours after the job completes. For information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual \[https://docs.vmsssoftware.com/vsi-openvms-user-s-manual/#DATE\\_AND\\_TIME\\_SECT\]](https://docs.vmsssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT).

**/SETUP=module[,...]**

Extracts the specified modules from the device control library (containing escape sequence modules for programmable printers) and copies the modules to the printer before a file is printed. By default, no device control modules are copied.

Note that the module names are not checked for validity until the time that the file is actually printed; therefore, **PRINT/SETUP** is susceptible to typing errors and other mistakes. It is recommended only for experimental setups.

For production setups, see the **/SETUP** qualifier for the **DEFINE/FORM** command in the [VSI OpenVMS DCL Dictionary: A–M \[https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\\_59\]](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_59).

**/SINCE[=time]****/NOSINCE**

Selects only those files dated on or after the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: **BOOT**, **JOB\_LOGIN**, **LOGIN**, **TODAY** (default), **TOMORROW**, or **YESTERDAY**. Specify one of the following qualifiers with the **/SINCE** qualifier to indicate the time attribute to be used as the basis for selection: **/BACKUP**, **/CREATED** (default), **/EXPIRED**, or **/MODIFIED**.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual \[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\\_AND\\_TIME\\_SECT\]](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) or the online help topic **Date**.

**/SPACE****/NOSPACE (default)**

Positional qualifier.

Controls whether print job output is double-spaced. The default is single-spaced output.

**/STYLE=keyword**

Specifies the file name format for display purposes.

The valid keywords for this qualifier are **CONDENSED** and **EXPANDED**. Descriptions are as follows:

| Keyword             | Description                                                                                                                                                                           |
|---------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CONDENSED (default) | Displays the file name representation of what is generated to fit into a 255-length character string. This file name may contain a DID or FID abbreviation in the file specification. |
| EXPANDED            | Displays the file name representation of what is stored on disk. This file name does not contain any DID or FID abbreviations.                                                        |

The keywords **CONDENSED** and **EXPANDED** are mutually exclusive. This qualifier specifies which file name format is displayed in the output message, along with the confirmation if requested.

File errors are displayed with the **CONDENSED** file specification unless the **EXPANDED** keyword is specified.

See the relevant section in the [VSI OpenVMS User's Manual \[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE\\_ACCESS\]](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE_ACCESS) for more information.

**/SYMLINK=*keyword***

The valid keywords for this qualifier are [NO]WILDCARD and [NO]ELLIPSIS. Descriptions are as follows:

| Keyword    | Description                                                                      |
|------------|----------------------------------------------------------------------------------|
| WILDCARD   | Indicates that symlinks are enabled during wildcard searches.                    |
| NOWILDCARD | Indicates that symlinks are disabled during directory wildcard searches.         |
| ELLIPSIS   | Equivalent to WILDCARD (included for command symmetry).                          |
| NOELLIPSIS | Indicates that symlinks are matched for all wildcard fields except for ellipsis. |

If the file named in the **PRINT** command is a symlink, the command operates on the symlink target.

**/TRAILER[=*keyword*]****/NOTRAILER**

Positional qualifier.

Controls whether a file trailer page is printed at the end of a file. The trailer page displays the job entry number as well as information about the user submitting the job and the files being printed. If the **/TRAILER** qualifier is positioned between the **PRINT** command and the file specifications, it can take either of the following keywords:

| Keyword | Description                                                |
|---------|------------------------------------------------------------|
| ALL     | Prints a file trailer page after each file in the job.     |
| ONE     | Prints a file trailer page after the last file in the job. |

If you want the **/TRAILER** qualifier to apply to individual files in a multi-file job, place the qualifier directly after each file that you want to have a trailer page.

Use the **/[NO]TRAILER** qualifier to override the **/DEFAULT=[NO]TRAILER** option that has been set for the output queue you are using. The **/[NO]TRAILER** qualifier does not override the **/SEPARATE=[NO]TRAILER** option set for the queue.

**/USER=*username***

Requires CMKRNL (change mode to kernel) privilege and read (R) and write (W) access to the user authorization file (UAF).

Allows you to print a job on behalf of another user. The print job runs exactly as if that user had submitted it. The print job runs under that user's user name and user identification code (UIC), and accounting information is logged to that user's account. By default, the user identification comes from the requesting process. The user name qualifier value can be any user name that is valid on your system. The name must be 1 to 12 alphanumeric characters.

## Examples

1. \$ PRINT/QUEUE=LPB0/COPIES=10/AFTER=20 RESUME  
Job RESUME (queue LPB0, entry 239) holding until 14-DEC-2001 20:00

The **PRINT** command in this example queues 10 copies of the file RESUME.LIS to printer LPB0, but requests that the copies not be printed until after 8:00 P.M.

2. \$ PRINT THETA.TXT + BETA/FLAG + GAMMA/FLAG + \*.LIS/FLAG  
Job THETA (queue SYS\$PRINT, entry 237) pending

The **PRINT** command in this example submits the files THETA.TXT, BETA.TXT, GAMMA.TXT, and the highest versions of all files with the file type .LIS as a single print job. Flag pages separate the individual files. Notice that the file type for BETA and GAMMA is .TXT, the file type of the first file in the list.

3. \$ PRINT/LOWERCASE THETA.TXT/COPIES=2, -  
\_BETA.DOC/COPIES=3  
Job THETA (queue SYS\$PRINT, entry 240) pending

The print job queued by the **PRINT** command in this example consists of two copies of THETA.TXT followed by three copies of BETA.DOC. This job must be printed on a printer that can print lowercase letters. If no such printer is available, the job waits in the queue.

4. \$ PRINT/JOB\_COUNT=3 THETA.TXT,BETA/NOIDENTIFY

The **PRINT** command in this example concatenates the files THETA.TXT and BETA.TXT into a single print job and prints three copies of the job. The **/NOIDENTIFY** qualifier requests that the job entry number and queue name not be displayed.

5. \$ COPY REPORT.MEM NODE3::  
\$ PRINT/REMOTE NODE3::REPORT.MEM

In this example, the two commands are entered at a node other than NODE3. The **COPY** command copies the file REPORT.MEM from the current node to the NODE3 node. The **PRINT** command queues the file REPORT.MEM located on the NODE3 node for printing at the NODE3 node. The job entry number and queue name are not displayed when the **/REMOTE** qualifier is used.

6. \$ PRINT/HOLD MASTER.DOC  
Job MASTER (queue SYS\$PRINT, entry 540) holding  
.  
.  
.  
\$ SET ENTRY 540/RELEASE

The **PRINT** command in this example queues a copy of the file MASTER.DOC to the default printer in a hold status. Later, the **SET ENTRY** command releases the hold status on the file and makes it available for printing.

7. \$ PRINT TEST.TXT  
Job TEST.TXT (queue SYS\$PRINT, entry 867) started on LPA0  
\$ SHOW ENTRY '\$ENTRY'  
Entry Jobname Username Blocks Status  
-----  
867 TEST.TXT Nisslert 135 Printing  
Submitted 10-DEC-2001 11:07 /FORM=DEFAULT /PRIORITY=100  
File: \$5\$DUA174:[NISSLERT]TEST.TXT;3

The **PRINT** command in this system example queues a copy of the file TEST.TXT to the default printer. It also creates the local symbol \$ENTRY to store the job entry number. The **SHOW ENTRY** command requests a display of the entry using the symbol \$ENTRY to identify it.

8. \$ PRINT/RETAIN=UNTIL=1 MYFILE.DAT  
.  
.

```
.  
$ SHOW QUEUE DOC$LN03  
Server queue DOC$LN03, stopped, on NEWTON::, mounted form DEFAULT  
Entry      Jobname      Username      Blocks      Status  
-----  
436        MYFILE        MIGDAL        8      Retained until 11-DEC-2001 16:56  
          %JBC-F-JOBABORT, job aborted during execution  
          Completed 11-DEC-2001 15:56 on queue DOC$LN03
```

The **SHOW QUEUE** display in this system example includes the date and time at which a retained job completed and the queue on which it executed. The user set job retention to be one hour after job completion. Depending on the queue's job retention policy, the job might be deleted from the queue at 16:56.

9. `$ PRINT /PARAMETERS=AAA=123`

This command passes the parameter `AAA=123` to the print symbiont. The interpretation of the parameter is dependent on the symbiont.

10. `$ PRINT /PARAMETERS=(ddd,"e,(F=(3,4),g),h"),iii)`

This command passes three parameters to the print symbiont: `DDD`, `"e,(F=(3,4),g),h"`, and `III`. The use of the quotes around the second parameter allows the use of nested parentheses, commas, and the preservation of alphabetic case. This parameter value is perfectly acceptable to the **PRINT** command, even though it is apt to subsequently be rejected by the print symbiont.

11. `$ PRINT /PARAMETERS=("N,O,P,Q,R,S,T",U,V)`

This command passes three parameters to the print symbiont: `"N,O,P,Q,R,S,T"`, `U`, and `V`. Depending on the parsing capabilities of the symbiont and the length of the parameters (each parameter is limited to 255 characters), this may be a workaround to the limitation of eight parameters.

## PRODUCT

**PRODUCT** — Invokes the POLYCENTER Software Installation utility to install one or more software products, remove one or more software products, or perform other related operations. For a complete description of the POLYCENTER Software Installation utility and the use of the **PRODUCT** command, see the relevant section in the *VSI OpenVMS System Manager's Manual, Volume 1: Essentials* [[https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#\\_6017INST\\_UPG](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#_6017INST_UPG)] and the *VSI OpenVMS System Management Utilities Reference Manual, Volume 2: M-Z* [<https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/#d0e9706>] or online help.

## Format

**PRODUCT**[*subcommand product-name* [/*qualifiers*]]

## PURGE

**PURGE** — Deletes all but the highest numbered versions of the specified files.

## Format

**PURGE** [*filespec*[,...]]

## Parameters

*filespec*[,...]

Specifies one or more files to be purged. If you specify more than one file, separate the file specifications with either commas (,) or plus signs (+). The asterisk (\*) and the percent sign (%) wildcard characters are allowed in the directory, file name, and file type fields; however, no version number can be specified. As a default, the **PURGE** command purges all files in the current directory. There are no file name or file type defaults with the **PURGE** command. If an input file specification is a symbolic link, the symbolic link itself is purged. Because only one version of a symbolic link can exist, this command has no effect on that file.

## Description

The **PURGE** command deletes earlier versions of files. The **PURGE** command never deletes all versions of any file. By default, the **PURGE** command keeps only the highest version of a file. If you do not include a file specification with the **PURGE** command, all files in the current directory are affected by the purge.

## Qualifiers

### **/BACKUP**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/BACKUP** qualifier selects files according to the dates of their most recent backups. This qualifier is incompatible with the **/CREATED**, **/EXPIRED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

### **/BEFORE[=*time*]**

Selects only those files dated prior to the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: **BOOT**, **LOGIN**, **TODAY** (default), **TOMORROW**, or **YESTERDAY**. Specify one of the following qualifiers with the **/BEFORE** qualifier to indicate the time attribute to be used as the basis for selection: **/BACKUP**, **/CREATED** (default), **/EXPIRED**, or **/MODIFIED**.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic **Date**.

### **/BY\_OWNER[=*uic*]**

Selects only those files whose owner user identification code (UIC) matches the specified owner UIC. The default UIC is that of the current process.

### **/CONFIRM**

### **/NOCONFIRM (default)**

Controls whether a request is issued before each purge operation to confirm that the operation should be performed on that file. The following responses are valid:

|      |       |               |
|------|-------|---------------|
| YES  | NO    | QUIT          |
| TRUE | FALSE | <b>Ctrl/Z</b> |
| 1    | 0     | ALL           |

**Return**

You can use any combination of uppercase and lowercase letters for word responses. Word responses can be abbreviated to one or more letters (for example, T, TR, or TRU for TRUE), but these abbreviations must be unique. Affirmative answers are YES, TRUE, and 1. Negative answers include: NO, FALSE, 0, and pressing **Return**. Entering QUIT or pressing **Ctrl/Z** indicates that you want to stop processing the command at that point. When you respond by entering ALL, the command continues to process, but no further prompts are given. If you type a response other than one of those in the list, DCL issues an error message and redisplay the prompt.

**/CREATED (default)**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/CREATED** qualifier selects files based on their dates of creation. This qualifier is incompatible with the **/BACKUP**, **/EXPIRED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

**/ERASE****/NOERASE (default)**

Erases the specified files from the disk so that the purged data no longer exists physically on the deallocated disk blocks.

When you delete a file, the area in which the file was stored is returned to the system for future use. The data that was stored in that location still exists in the system until new data is written over it. When the **/ERASE** qualifier is specified, the storage location is overwritten with a system-specified pattern so that the data no longer exists.

**/EXCLUDE=(filespec[,...])**

Excludes the specified files from the purge operation. You can include a directory but not a device in the file specification. The asterisk (\*) and the percent sign (%) wildcard characters are allowed in the file specification; however, you cannot use relative version numbers to exclude a specific version. If you specify only one file, you can omit the parentheses.

**/EXPIRED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/EXPIRED** qualifier selects files according to their expiration dates. (The expiration date is set with the **SET FILE/EXPIRATION\_DATE** command.) The **/EXPIRED** qualifier is incompatible with the **/BACKUP**, **/CREATED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

**/GRAND\_TOTAL (Alpha/Integrity servers only)**

Displays the total number of files and blocks or bytes deleted. The display is shown as blocks or bytes depending on the current default setting. You can use **SHOW PROCESS/UNITS** to display the current default. To change the default, execute the DCL command **SET PROCESS/UNITS=BYTES** or **SET PROCESS/UNITS=BLOCKS**.

**/IGNORE=INTERLOCK (Alpha/Integrity servers only)**

Allows you to mark a write-accessed file for deletion. This removes the file name entry, and the file is deleted when it is closed by the final user.

**/KEEP=*number-of-versions***

Specifies the maximum number of versions of the specified files to be retained in the directory. If you do not include the **/KEEP** qualifier, all but the highest numbered version of the specified files are deleted from the directory.

**/LOG****/NOLOG (default)**

Controls whether file specifications are displayed as the files are deleted.

**/MODIFIED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/MODIFIED** qualifier selects files according to the dates on which they were last modified. This qualifier is incompatible with the **/BACKUP**, **/CREATED**, and **/EXPIRED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time modifiers, the default is the **/CREATED** qualifier.

**/SINCE[=*time*]**

Selects only those files dated on or after the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: **BOOT**, **JOB\_LOGIN**, **LOGIN**, **TODAY** (default), **TOMORROW**, or **YESTERDAY**. Specify one of the following qualifiers with the **/SINCE** qualifier to indicate the time attribute to be used as the basis for selection: **/BACKUP**, **/CREATED** (default), **/EXPIRED**, or **/MODIFIED**.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\\_AND\\_TIME\\_SECT](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT)] or the online help topic **Date**.

**/STYLE=*keyword***

Specifies the file name format for display purposes while purging files.

The valid keywords for this qualifier are **CONDENSED** and **EXPANDED**. Descriptions are as follows:

| Keyword             | Description                                                                                                                                                                           |
|---------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CONDENSED (default) | Displays the file name representation of what is generated to fit into a 255-length character string. This file name may contain a DID or FID abbreviation in the file specification. |
| EXPANDED            | Displays the file name representation of what is stored on disk. This file name does not contain any DID or FID abbreviations.                                                        |

The keywords **CONDENSED** and **EXPANDED** are mutually exclusive. This qualifier specifies which file name format is displayed in the output message, along with the confirmation if requested.

File errors are displayed with the **CONDENSED** file specification unless the **EXPANDED** keyword is specified.

See the relevant section in the *VSI OpenVMS User's Manual* [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE\\_ACCESS](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE_ACCESS)] for more information.

## Examples

1. `$ PURGE`

The **PURGE** command in this example deletes all but the highest numbered version of all files in the default directory.

2. `$ PURGE *.COM`

The **PURGE** command in this example deletes all but the highest numbered version of each file with a file type of `.COM`.

3. `$ PURGE/KEEP=3 [WILDER.JOB308]ACCOUNT.COB`

The **PURGE** command in this example deletes all but the three highest numbered versions of the file `ACCOUNT.COB` in the subdirectory `[WILDER.JOB308]`.

4. `$ PURGE/ERASE/SINCE=YESTERDAY [.MEMOS]`

The **PURGE** command in this example purges all files in the `MEMOS` subdirectory that have been created or modified since yesterday and erases the storage locations so that the purged data no longer exists.

5. `$ PURGE [BROD.TESTFILES]/LOG`  
`%PURGE-I-FILPURG, DISK1:[BROD.TESTFILES]AVE.OBJ;1 deleted (3 blocks)`  
`%PURGE-I-FILPURG, DISK1:[BROD.TESTFILES]BACK.OBJ;2 deleted (5 blocks)`  
`%PURGE-I-TOTAL, 2 files deleted (8 blocks)`

The **PURGE** command in this example purges all files cataloged in the subdirectory named `[BROD.TESTFILES]`. The `/LOG` qualifier requests the **PURGE** command to display the specification of each file it has deleted as well as the total number of files that have been deleted.

6. `$ PURGE/GRAND_TOTAL STATUS.TXT`  
`%PURGE-I-TOTAL, 6 files deleted (600KB)`

The output display in this example shows that 6 files were deleted for a total of 600KB. The process is currently set to display file sizes in bytes. To change future displays to show blocks, use the **SET PROCESS/UNITS=BLOCKS** command.

7. `$ PURGE/KEEP=2 TAMPA::DISK1:[EXAMPLE]*.LIS`

The **PURGE** command in this example deletes all but the two highest numbered versions of each file with the file type `.LIS` in the directory `EXAMPLE` on remote node `TAMPA`.

## READ

**READ** — Reads a single record from a specified input file and assigns the record's contents to a specified symbol name.

## Format

**READ***logical-name[:]* *symbol-name*

## Parameters

### *logical-name[:]*

Specifies the logical name of the input file from which a record is to be read. Use the logical name assigned by the **OPEN** command when the file was opened. (The **OPEN** command assigns a logical name to a file and places the name in the process logical name table.)

In addition, you can specify the process-permanent files identified by the logical names SYSS\$INPUT, SYSS\$OUTPUT, SYSS\$ERROR, and SYSS\$COMMAND.

### *symbol-name*

Specifies the name of a symbol to be equated to the contents of the record. The name must be 1 to 255 alphanumeric characters and must start with an alphabetic letter, an underscore (\_), or a dollar sign (\$).

When you specify a symbol name for the **READ** command, the command interpreter places the symbol name in the local symbol table for the current command level. If the symbol has already been defined, the **READ** command redefines it to the new value being read.

## Description

The **READ** command can read data from sequential, relative, or indexed files. After each record is read from the specified file, the **READ** command positions the record pointer at the next record in the file; however, if you are reading an indexed file, you can use the **/INDEX** and **/KEY** qualifiers to read records randomly.

The maximum size of any record that can be read in a single **READ** command is 2048 bytes. The reading of a 2048-byte record from a remote file opened by DCL requires that the system default network block count be increased to a minimum value of 25 (DCL **SET RMS\_DEFAULT/NETWORK=25**).

To read a file, the file must be opened by using the **/READ** qualifier with the **OPEN** command. The process-permanent files identified by the logical names SYSS\$INPUT, SYSS\$OUTPUT, SYSS\$ERROR, and SYSS\$COMMAND do not have to be opened explicitly to be read.

If the **READ** command is executed interactively and the logical name is specified as one of the process-permanent files, SYSS\$INPUT, SYSS\$OUTPUT, SYSS\$COMMAND, or SYSS\$ERROR, the command interpreter prompts for input data. The **READ** command accepts data exactly as you enter it. The **READ** command does not convert characters to uppercase, remove extra spaces and tabs, or remove quotation marks (" "). Also, the **READ** command does not perform symbol substitution. See the [/PROMPT](#) qualifier for more information on issuing prompts with the **READ** command.

## Qualifiers

### **/DELETE**

Deletes a record from an indexed file after it has been read. An indexed file must be opened with the **/READ** and **/WRITE** qualifiers in order to use the **READ/DELETE** command.

### **/END\_OF\_FILE=label**

Transfers control to the location specified by the *label* keyword (in the current command procedure) when the end of the file is reached. When the last record in the file is read, the OpenVMS Record Management Services (RMS) returns an error condition indicating the end-of-file (EOF). If the **/END\_OF\_FILE** qualifier is specified, the command interpreter transfers control to the command line at the specified label.

If the **/END\_OF\_FILE** qualifier is not specified, control is given to the error label specified with the **/ERROR** qualifier when the end of the file is reached. If neither the **/ERROR** nor the **/END\_OF\_FILE** qualifier is specified, then the current ON condition action is taken.

**/ERROR=label**

Transfers control to the location specified by the *label* keyword (in the current command procedure) when a read error occurs. If no error routine is specified and an error occurs during the reading of the file, the current ON condition action is taken.

Overrides any ON condition action specified.

If an error occurs and the target label is successfully given control, the reserved global symbol **\$STATUS** retains the error code.

**/INDEX=n**

Specifies the index (*n*) to be used to look up keys when reading an indexed file.

If you do not specify the **/INDEX** qualifier, the most recent **/INDEX** qualifier value is used. If a previous value was not specified, the primary index is used (**/INDEX=0**).

**/KEY=string**

Reads a record with the key that matches the specified character string. Binary and integer keys are not allowed. This qualifier, when used together with the **/INDEX** qualifier, allows you random access to indexed files.

Key matches are made by comparing the characters in the **/KEY** string to characters in the record key.

To read records at random in an indexed file, you must specify the **/KEY** qualifier. Once a record is read randomly, all subsequent reads without the **/KEY** qualifier access records in the indexed file sequentially.

**/MATCH=option**

Specifies the key match algorithm to be used when searching for matching keys. Specify one of the following options:

| Option | Description                                            |
|--------|--------------------------------------------------------|
| EQ     | Selects keys equal to the match value (default).       |
| GE     | Selects keys greater than or equal to the match value. |
| GT     | Selects keys greater than the match value.             |
| LE     | Selects keys less than or equal to the match value.    |
| LT     | Selects keys less than the match value.                |

If you are reading indexed files and you do not use the **/MATCH** qualifier, the default is **/MATCH=EQ**.

**/NOLOCK**

Specifies that the record to be read not be locked and enables a record to be read that has been locked by other accessors.

By default, records are locked as they are read and unlocked on the next I/O operation on the file.

**/PROMPT=*string***

Specifies an alternate prompt string to be displayed when reading from the terminal. The default prompt string is DATA:.

**/TIME\_OUT=*n*****/NOTIME\_OUT (default)**

Specifies the number of seconds after which the **READ** command is terminated if no input is received. If you enter the **/TIME\_OUT** qualifier, you must specify a value from 0 to 255.

If you enter both the **/ERROR=*label*** and **/TIME\_OUT** qualifiers, and the time limit expires, the error branch is taken.

**/WAIT**

Sets RAB\$V\_WAT to make a process wait for a record in a file. Can be used in combination with **/TIME\_OUT** to restrict how long the process should wait before timing out upon failure to find the record.

## Examples

```
1. $ OPEN IN NAMES.DAT
   $ LOOP:
   $ READ/END_OF_FILE=ENDIT IN NAME
     .
     .
     .
   $ GOTO LOOP
   $ ENDIT:
   $ CLOSE IN
```

The **OPEN** command opens the file NAMES.DAT for input and assigns it the logical name of IN. The **READ** command reads records from the file IN and places the contents into the symbol NAME. The **READ** command specifies the label ENDIT to receive control when the last record in the file has been read. The procedure loops until all records in the file have been processed.

```
2. $ READ/ERROR=READERR/END_OF_FILE=OKAY MSGFILE CODE
     .
     .
     .
   $ READERR:
   $ CLOSE MSGFILE
     .
     .
     .
   $ OKAY:
   $ CLOSE MSGFILE
   $ EXIT
```

The **READ** command reads records from the file MSGFILE and places the contents into the symbol CODE. The **READ** command also uses the **/ERROR** and **/END\_OF\_FILE** qualifiers to specify labels to receive control at the end-of-file (EOF) and on error conditions. At the EOF, control is transferred to the label OKAY. On other read errors, control is transferred to the READERR label.

```
3. $ READ SYS$COMMAND DATA_LINE
   $ WRITE OUTPUT_FILE DATA_LINE
```

.  
.  
.

The **READ** command requests data from the current SYS\$COMMAND device. If the command procedure containing these lines is executed interactively, the command issues a prompt to the terminal, accepts a line of data, and equates the data entered to the symbol name DATA\_LINE.

Then the **WRITE** command writes the value of the symbol DATA\_LINE to the file identified by the logical name OUTPUT\_FILE.

4. \$ OPEN/READ INPUT\_FILE TRNTO::INVENTORY.DAT  
\$ OPEN/APPEND OUTPUT\_FILE RECEIVE.DAT  
\$ READ INPUT\_FILE DATA\_LINE  
\$ WRITE OUTPUT\_FILE DATA\_LINE

The **OPEN/READ** command opens the file INVENTORY.DAT at the remote node TRNTO for reading and assigns it the logical name INPUT\_FILE. The **OPEN/APPEND** command opens the file RECEIVE.DAT in the current default directory. The **READ** command requests data from the file INVENTORY.DAT at the remote node TRNTO. The **WRITE** command writes the value of the symbol DATA\_LINE to the end of the local file RECEIVE.DAT.

## RECALL

RECALL — Displays up to 254 previously entered commands on the screen for subsequent execution.

### Format

**RECALL**[ *command-specifier* ]

### Parameter

*command-specifier*

Specifies the number or the first several characters of the command you want to recall. You cannot use any of the qualifiers in conjunction with a command-specifier.

The specified characters should be unique. If they are not unique, the **RECALL** command displays the most recently entered command line that matches those characters. For example, suppose you enter a **SHOW STATUS** command and later enter a **SHOW TIME** command. If you then type **RECALL S**, the **SHOW TIME** command is recalled. You must type **RECALL SHOW S** to recall the **SHOW STATUS** command. The number of the command can be from 1 to 254 (where 1 is the last command entered).

The **RECALL** command itself is never assigned a number. If no command specifier is entered, the **RECALL** command recalls the most recently entered command. You can use the **/ALL** qualifier to have the system display all the commands in the recall buffer, along with their command numbers, to verify the number of the command you want to recall.

## Description

When you enter commands to the system, they are stored in a recall buffer for later use with the **RECALL** command. Input to the **INQUIRE** command in command procedures is also placed in the recall buffer. The **RECALL** command itself is never stored in the recall buffer. You can use continuation characters with the commands to be recalled, but only 255 characters can be read at a time.

The recall buffer can hold up to 254 commands. The size of the recall buffer is 4 KB, which will store approximately 80 commands at 48 characters each.

If the length of stored commands makes it necessary, one or more of the oldest commands will be removed from the recall buffer to make room for the most recent command.

When you use the **RECALL** command, the system displays the command but does not process it. If you want it processed as it appears, press **Return**. You can use the command line editing facility to make minor changes in the command line and then press **Return** to process the revised version of the command.

## Qualifiers

### **/ALL** [*command-specifier*]

Displays all the commands (and their numbers) available for recall. Do not use the **/ALL** qualifier with the other **RECALL** qualifiers.

To display multiple occurrences of a specific command in the recall buffer, specify the command after the **/ALL** qualifier.

---

### Note

The **RECALL** command is never stored in the recall buffer.

---

### **/ERASE**

Erases the contents of the recall buffer.

### **/INPUT=filespec**

Causes each line of the input file to be added to the recall buffer. If a file type is not specified with the file name, .LIS is the default. The file specification cannot include the asterisk (\*) and the percent sign (%) wildcard characters.

If the **/ERASE** qualifier is also specified, the contents of the recall buffer are erased before the contents of the specified file are read into the recall buffer.

The **/INPUT** qualifier is incompatible with the **/ALL** and **/PAGE** qualifiers.

### **/OUTPUT=filespec**

Specifies the name of the output file where the contents of the recall buffer are written. If you do not specify a file type, the default is .LIS. The file specification cannot include the asterisk (\*) and the percent sign (%) wildcard characters.

If the **/ERASE** qualifier is also specified, the contents of the recall buffer are erased after the contents of the recall buffer are written to the specified file.

The **/OUTPUT** qualifier is incompatible with the **/ALL** and **/PAGE** qualifiers.

### **/PAGE**

### **/NOPAGE** (default)

Displays all the commands (and their numbers) available for recall one screen at a time. The **/NOPAGE** qualifier produces the same output as the **/ALL** qualifier. You can cancel the output display by pressing **Ctrl/Z**.

The **/PAGE** qualifier is incompatible with the **/INPUT** and **/OUTPUT** qualifiers.

### **/SEARCH** *string*

Searches the recall buffer and displays all the commands (and their numbers) that contain the specified search string.

## Examples

### 1. \$ RECALL T

The **RECALL** command in this example recalls the last command entered that begins with the letter T.

```
2. $ SHOW DEFAULT
    DISK3:[SMITH]
$ DIRECTORY SEPT*
    %DIRECT-W-NOFILES, no files found
$ SET DEFAULT [SMITH.LETTERS]
$ RECALL/ALL
    1 SET DEFAULT [SMITH.LETTERS]
    2 DIRECTORY SEPT*
    3 SHOW DEFAULT
$ RECALL 2
$ DIRECTORY SEPT*
    %DIRECT-W-NOFILES, no files found
$ RECALL 2
$ SET DEFAULT [SMITH.LETTERS]
    <edit command line>
$ SET DEFAULT [SMITH.MEMOS]
$ RECALL 2
$ DIRECTORY SEPT*
```

This example starts with a **SHOW DEFAULT** and a **DIRECTORY** command. After not finding the file you want, enter the **SET DEFAULT** command to move to the LETTERS subdirectory. Next use the **RECALL/ALL** command to see the list of commands you have entered. Enter the **RECALL 2** command to repeat the **DIRECTORY** command in the LETTERS subdirectory. Because you still have not found the file you want, enter the **RECALL 2** command again to recall the **SET DEFAULT** command. (With the entry of the latest **DIRECTORY** command, **SET DEFAULT** becomes command 2 in the **RECALL** list.) Edit the command line so that the system sets the default to the MEMOS subdirectory. Finally, recall the **DIRECTORY** command to try once more to find the file.

```
3. $ TYPE COMMANDS.LIS
    DIRECTORY
    RUN AUTHORIZE
    SET PROCESS/PRIVILEGES=ALL
$ RECALL/INPUT=COMMANDS.LIS
$ RECALL/ALL
    1 SET PROCESS/PRIVILEGES=ALL
    2 RUN AUTHORIZE
    3 DIRECTORY
    4 TYPE COMMANDS.LIS
```

This example shows the contents of the **COMMANDS.LIS** file with the **TYPE** command, then uses the **RECALL/INPUT=COMMANDS.LIS** command to place the commands into the recall buffer.

Issuing the **RECALL/ALL** command subsequently shows the numbered display of commands in the recall buffer.

```
4. $ RECALL/OUTPUT=NEW_COMMANDS.LIS
$ TYPE NEW_COMMANDS.LIS
TYPE COMMANDS.LIS
DIRECTORY
RUN AUTHORIZE
SET PROCESS/PRIVILEGES=ALL
```

This example places the contents of the recall buffer (see the previous example) into the `NEW_COMMANDS.LIS` file. Note that they are not numbered and in the reverse sequence of the **RECALL/ALL** command output.

```
5. $ RECALL/ALL SHOW
    1 show system
    4 show user peleg
    5 show intrusion
    6 show error
    7 show time
```

This example displays all occurrences of the **SHOW** command in the recall buffer.

```
6. $ RECALL/SEARCH devi
    1 dir sys$sysdevice:[000000]
    4 show device dk
```

This example displays all commands in the recall buffer that contain the string "devi".

## RENAME

**RENAME** — Changes all or part of a file specification of an existing disk file or disk directory.

### Format

**RENAME***input-filespec[,...]* *output-filespec*

### Parameters

*input-filespec[,...]*

Specifies the name of one or more files whose specifications are to be changed. The asterisk (\*) and the percent sign (%) wildcard characters are allowed in the directory specification, file name, file type, or version number fields of the file specification. When wildcard characters are used, all files whose specifications satisfy the wildcard fields are renamed. If an input file specification is a symbolic link, the symbolic link itself is renamed. If the output file specification is a symbolic link, the operation fails.

*output-filespec*

Provides the new file specification to be applied to the input file. The **RENAME** command uses the device, directory, file name, and file type of the input file as defaults for fields in the output file that are either unspecified, or are indicated by the asterisk (\*) and the percent sign (%) wildcard characters. Wildcard characters in corresponding fields of the input and output file specification result in multiple rename operations.

The **RENAME** command supplies output file version numbers in the following ways:

- If the output file specification contains an explicit version number, that version number is used.
- If the output file specification contains an asterisk (\*) or a percent sign (%) wildcard character as the version number, the version number of the input file is used.
- If the input file specification contains an asterisk (\*) or a percent sign (%) wildcard character as the version number, the version number of each input file names a corresponding output file.
- If no file exists with the same file name and type as the output file, the new file is assigned a version number of 1.
- If a file already exists with the same file name and type as the output file, the next higher version number is used (unless the **/NONEWVERSION** qualifier is specified).

## Description

The **RENAME** command changes the directory name, file name, file type, or version number of a file. The node and disk designation for the input file specification must be the same as that for the output file specification. In addition, you must have delete (D) access privileges to a file to rename the file.

You cannot rename a file across a network.

## Qualifiers

### **/BACKUP**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/BACKUP** qualifier selects files according to the dates of their most recent backups. This qualifier is incompatible with the **/CREATED**, **/EXPIRED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

### **/BEFORE[=*time*]**

Selects only those files dated prior to the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: **BOOT**, **LOGIN**, **TODAY** (default), **TOMORROW**, or **YESTERDAY**. Specify one of the following qualifiers with the **/BEFORE** qualifier to indicate the time attribute to be used as the basis for selection: **/BACKUP**, **/CREATED** (default), **/EXPIRED**, or **/MODIFIED**.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic **Date**.

### **/BY\_OWNER[=*uic*]**

Selects only those files whose owner user identification code (UIC) matches the specified owner UIC. The default UIC is that of the current process.

Specify the UIC by using standard UIC format as described in the relevant section in the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC_SECTION) [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC\_SECTION].

**/CONFIRM****/NOCONFIRM (default)**

Controls whether a request is issued before each rename operation to confirm that the operation should be performed on that file. The following responses are valid:

|      |       |               |
|------|-------|---------------|
| YES  | NO    | QUIT          |
| TRUE | FALSE | <b>Ctrl/Z</b> |
| 1    | 0     | ALL           |

**Return**

You can use any combination of uppercase and lowercase letters for word responses. Word responses can be abbreviated to one or more letters (for example, T, TR, or TRU for TRUE), but these abbreviations must be unique. Affirmative answers are YES, TRUE, and 1. Negative answers include: NO, FALSE, 0, and pressing **Return**. Entering QUIT or pressing **Ctrl/Z** indicates that you want to stop processing the command at that point. When you respond by entering ALL, the command continues to process, but no further prompts are given. If you type a response other than one of those in the list, DCL issues an error message and redisplay the prompt.

**/CREATED (default)**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/CREATED** qualifier selects files based on their dates of creation. This qualifier is incompatible with the **/BACKUP**, **/EXPIRED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

**/EXCLUDE=(filespec[,...])**

Excludes the specified files from the rename operation. You can include a directory but not a device in the file specification. The asterisk (\*) and the percent sign (%) wildcard characters are allowed in the file specification; however, you cannot use relative version numbers to exclude a specific version. If you specify only one file, you can omit the parentheses.

**/EXPIRED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/EXPIRED** qualifier selects files according to their expiration dates. (The expiration date is set with the **SET FILE/EXPIRATION\_DATE** command.) This qualifier is incompatible with the **/BACKUP**, **/CREATED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

**/INHERIT\_SECURITY****/NOINHERIT\_SECURITY (default)**

Controls whether the security profile (UIC, protection code, and ACL) of the renamed file is altered. If you specify **/INHERIT\_SECURITY**, a new security profile is generated, as if a new file had been created with the new file and directory names. See the relevant section in the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#FILE_TEMPLATE) [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#FILE\_TEMPLATE] or online help (Hints topic) for a description of how a profile is assigned.

**/LOG****/NOLOG (default)**

Displays the file specification of each file as it is renamed.

**/MODIFIED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/MODIFIED** qualifier selects files according to the dates on which they were last modified. This qualifier is incompatible with the **/BACKUP**, **/CREATED**, and **/EXPIRED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time modifiers, the default is the **/CREATED** qualifier.

**/NEW\_VERSION (default)****/NONEW\_VERSION**

Assigns a new version number if an output file specification is the same as that of an existing file. The **/NONEW\_VERSION** qualifier displays an error message if an output file specification is the same as that of an existing file. The asterisk (\*) and the percent sign (%) wildcard characters appearing in the version field of an input or output file overrides these qualifiers.

**/SINCE[=time]**

Selects only those files dated on or after the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: **BOOT**, **JOB\_LOGIN**, **LOGIN**, **TODAY** (default), **TOMORROW**, or **YESTERDAY**. Specify one of the following qualifiers with the **/SINCE** qualifier to indicate the time attribute to be used as the basis for selection: **/BACKUP**, **/CREATED** (default), **/EXPIRED**, or **/MODIFIED**.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic **Date**.

**/STYLE=keyword**

Specifies the file name format for display purposes.

The valid keywords for this qualifier are **CONDENSED** and **EXPANDED**. Descriptions are as follows:

| Keyword             | Description                                                                                                                                                                           |
|---------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CONDENSED (default) | Displays the file name representation of what is generated to fit into a 255-length character string. This file name may contain a DID or FID abbreviation in the file specification. |
| EXPANDED            | Displays the file name representation of what is stored on disk. This file name does not contain any DID or FID abbreviations.                                                        |

The keywords **CONDENSED** and **EXPANDED** are mutually exclusive. This qualifier specifies which file name format is displayed in the output message, along with the confirmation if requested.

File errors are displayed with the **CONDENSED** file specification unless the **EXPANDED** keyword is specified.

See the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE_ACCESS) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE\_ACCESS] for more information.

**/SYMLINK=keyword**

The valid keywords for this qualifier are **[NO]WILDCARD** and **[NO]ELLIPSIS**. Descriptions are as follows:

| Keyword    | Description                                                                      |
|------------|----------------------------------------------------------------------------------|
| WILDCARD   | Indicates that symlinks are enabled during wildcard searches.                    |
| NOWILDCARD | Indicates that symlinks are disabled during directory wildcard searches.         |
| ELLIPSIS   | Equivalent to WILDCARD (included for command symmetry).                          |
| NOELLIPSIS | Indicates that symlinks are matched for all wildcard fields except for ellipsis. |

If the file named in the **RENAME** command is a symlink, the command operates on the symlink itself.

## Examples

1. `$ RENAME AVERAGE.OBJ OLDAVERAGE`

The **RENAME** command in this example renames the highest existing version of the file `AVERAGE.OBJ` to `OLDAVERAGE.OBJ`. If no file named `OLDAVERAGE.OBJ` currently exists, the new file is assigned a version number 1.

2. `$ RENAME/NONEW_VERSION SCANLINE.OBJ;2 BACKUP.OBJ`

The **RENAME** command in this example renames the file `SCANLINE.OBJ;2` to `BACKUP.OBJ;2`. The **/NONEW\_VERSION** qualifier ensures that, if `BACKUP.OBJ;2` already exists, the **RENAME** command does not rename the file, but instead reports the error.

3. `$ RENAME *.TXT;* *.OLD;*`

The **RENAME** command in this example renames all versions of all files with the file type `TXT` to have the file type `OLD`. The file names and version numbers are not changed.

4. `$ RENAME WATER.TXT [.MEMOS]`

The **RENAME** command in this example changes the directory name of `WATER.TXT` from your default directory to the `MEMOS` subdirectory. (The **RENAME** command moves the file to another directory.)

5. `$ RENAME [BORDERS.TESTFILES]SAVE.DAT []TEST`

The **RENAME** command in this example renames the file `SAVE.DAT` in the directory `BORDERS.TESTFILES` to `TEST.DAT`. The new file is moved to the current default directory.

6. `$ RENAME COEISABLAST.TXT COEIsABlast.txt`

The **RENAME** command in this example changes the case of `COEISABLAST.TXT` to `COEIsABlast.txt`. You must be on an ODS-5 disk and previously have used the **SET PROCESS/CASE\_LOOKUP=SENSITIVE** command for this **RENAME** command to work properly.

7. `$ RENAME/LOG`  
`$ _From: DATA.*,INFO.*`  
`$ _To: NEW`  
`%RENAME-I-RENAMED, _DISK0:[SYSTEM]DATA.AAA;1 renamed to _DISK0:`  
`[SYSTEM]NEW.AAA;1`  
`%RENAME-I-RENAMED, _DISK0:[SYSTEM]DATA.BBB;1 renamed to _DISK0:`  
`[SYSTEM]NEW.BBB;1`

```
%RENAME-I-RENAMED, _DISK0:[SYSTEM]DATA.CCC;1 renamed to _DISK0:
[SYSTEM]NEW.CCC;1
%RENAME-I-RENAMED, _DISK0:[SYSTEM]INFO.001;1 renamed to _DISK0:
[SYSTEM]NEW.001;1
%RENAME-I-RENAMED, _DISK0:[SYSTEM]INFO.002;1 renamed to _DISK0:
[SYSTEM]NEW.002;1
%RENAME-I-RENAMED, _DISK0:[SYSTEM]INFO.003;1 renamed to _DISK0:
[SYSTEM]NEW.003;1
$
```

In this example, three files exist with the file name of DATA, and three files have the file name of INFO. This **RENAME** command illustrates the asterisk (\*) wildcard character in the input file names and the use of temporary default file types and version numbers on the output files. The result is the renaming of all six files as displayed by the **/LOG** qualifier.

8. \$ RENAME NODE1::DISK2:[SMITH]ASSEMSHT.EXE NODE1::DISK3:
[JONES]ASSEMBLYSHEET.EXE

The **RENAME** command in this example renames the file ASSEMSHT.EXE in the SMITH directory on remote node NODE1 and disk DISK2 to ASSEMBLYSHEET.EXE in the JONES directory on the same remote node and disk. You can rename a file on another node and disk only if the new file resides on that same node and disk.

## REPLY

**REPLY** — Broadcasts a message to a terminal or terminals. See the qualifier descriptions for restrictions.

## Format

**REPLY** [*message-text*]

## Parameter

*message-text*

Specifies the text of the message. The text must be 1 to 511 characters. Enclose the text in quotation marks (" ") if it contains spaces, special characters, or lowercase characters.

## Description

All users with OPER (operator) privilege can use the **REPLY** command to communicate with system users. The **REPLY** command does the following:

- Displays messages at users' terminals
- Responds to user requests
- Responds to magnetic tape file system requests
- Enables and disables operator status on a terminal (if the operator communication process [OPCOM] is running)
- Closes the operator's log file and opens a new one (if OPCOM is running)

You must always use one or more qualifiers with the **REPLY** command in order for it to be meaningful. If you use the **REPLY** command without using any qualifiers, an error message is returned. When you use the **REPLY** command for any purpose other than displaying messages at users' terminals, you must also use the **/ENABLE=keyword** qualifier. See the description of the [/ENABLE](#) qualifier to determine the appropriate keyword (or keywords) for your purpose.

## Displaying Messages at Users' Terminals

To contact one or more system users, the operator enters one of the following **REPLY** commands:

- **REPLY/ALL *message-text***
- **REPLY/TERMINAL=(*terminal-name*[,...]) *message-text***
- **REPLY/USERNAME[=(*username*[,...])] *message-text***

The **/ALL** qualifier sends a message to all terminals that are on line and are connected to the OpenVMS system or OpenVMS Cluster. Generally, when an important message is to be broadcast, such as information about a system shutdown, you should use the **/ALL** qualifier.

The **/TERMINAL** qualifier sends a message to one or more specific terminals on the system or cluster.

The **/USERNAME** qualifier sends a message to terminals at which one or more system or cluster users are logged in.

Note that the **/TO** qualifier is *not* used under these three circumstances, because the operator is not replying to a specific request from either the file system or a user.

To broadcast to a terminal other than your own, you must have OPER privilege. The **REPLY** command is not complete until all terminals you are broadcasting to have received the message.

## Responding to User Requests

When a user enters the **REQUEST/REPLY** command, the process associated with the requesting user's terminal is put in a wait state until the operator responds by using one of the following **REPLY** commands:

- **REPLY/ABORT=*identification-number* *message-text***
- **REPLY/PENDING=*identification-number* *message-text***
- **REPLY/TO=*identification-number* *message-text***

The **/ABORT** qualifier indicates that the user's request has been canceled.

The **/PENDING** qualifier sends a message to the user and keeps the user's process in a wait state until the request can be fulfilled or aborted.

The **/TO** qualifier indicates that the user's request has been fulfilled.

When a user enters the **REQUEST/REPLY** command, the message is displayed at the system console terminal. For example:

```
%OPCOM, 24-DEC-2017 09:49:24.47, request 3, from user SYSTEM
_TTB6:, This is a sample request
```

The user cannot enter any further commands until the operator responds using the **/ABORT** or the **/TO** qualifier, or until the user aborts the request. If the operator does not respond and the user does not abort the request, the request is repeated at 5-minute intervals on the operator's terminal until the operator replies.

The **REPLY** command is an essential part of the procedures that operators must use in order for users to gain access to tape and disk volumes.

## Responding to File System Requests

When a multi-volume tape volume reaches the end-of-tape (EOT) mark, the magnetic tape file system suspends processing and sends a message to the operator to mount the next tape. The operator responds using one of the following **REPLY** commands:

- **REPLY/TO=identification-number label**
- **REPLY/INITIALIZE\_TAPE=identification-number label**
- **REPLY/BLANK\_TAPE=identification-number label**
- **REPLY/ABORT=identification-number**

The **/TO** qualifier indicates that the file system request has been fulfilled. When the request from the magnetic tape file system specifies a volume label, the operator mounts the specified tape and enters the **REPLY/TO** command; however, if the file system requests a new volume, the operator can reuse a scratch volume by mounting it and by entering the **REPLY/INITIALIZE\_TAPE** command. The operator also can mount a blank volume and then enter the **REPLY/BLANK\_TAPE** command. In any case, the operator may add the message "label" to the **REPLY** command to specify the volume's label. The quotation marks ( " ") are required syntax.

If the request is "**REMOUNT**" or "**MOUNT NEW**", the label is required in the message text. If the request is "**MOUNT**", no label is needed.

The **/ABORT** qualifier indicates that the file system request has been canceled.

## Enabling and Disabling Operator Status on a Terminal

Any terminal connected to the operating system can be established as an operator's terminal if **OPCOM** is running. When an operator who is logged in to an account with **OPER** (operator) privilege enters the **REPLY/ENABLE** command at the designated terminal, that terminal can be used to respond to user requests and to monitor device status. Such a terminal retains operator status until it is specifically disabled, or until the end of the current interactive session, if it was established as a temporary operator's terminal (see the description of the [/TEMPORARY](#) qualifier).

Operator messages are printed on the system console terminal unless that terminal is explicitly disabled as an operator's terminal.

When the operator enters the **REPLY/ENABLE** command, **OPCOM** confirms that the terminal has been enabled. For example:

```
$ REPLY/ENABLE
```

```
%OPCOM, 24-DEC-2001 10:22:19.75, operator status for operator OPA0
CENTRAL, PRINTER, TAPES, DISKS, DEVICES, CARDS, NETWORK, CLUSTER, LICENSE,
OPER1, OPER2, OPER3, OPER4, OPER5, OPER6, OPER7, OPER8, OPER9, OPER10,
OPER11, OPER12
```

When the operator enters the **REPLY/DISABLE** command, OPCOM uses the following message to confirm that the terminal is no longer an operator terminal:

```
%OPCOM, 24-DEC-2017 10:03:23.48, operator disabled, operator OPA0
```

To grant specific operator status on a particular terminal, the operator includes one or more keywords after the **/ENABLE** qualifier. For example, to establish a terminal as an operator terminal that can receive messages pertaining to mounting and dismounting tapes and disks, the operator enters the following:

```
$ REPLY/ENABLE=(DISKS,TAPES)
```

```
%OPCOM, 24-DEC-2001 10:04:00.18, operator enabled, operator OPA0
```

```
$
```

```
%OPCOM, 24-DEC-2001 10:04:00.47, operator status for operator OPA0  
TAPES, DISKS
```

OPCOM confirms that the terminal has operator status for tape and disk messages.

To discontinue specific operator status, the operator includes one or more keywords after the **/DISABLE** qualifier. For example, to inhibit an operator terminal from receiving messages pertaining to mounting and dismounting disks, the operator enters the following command:

```
$ REPLY/DISABLE=DISKS
```

```
%OPCOM, 24-DEC-2017 10:04:30.83, operator status for operator OPA0TAPES
```

Note that OPCOM lists the specific operator status still assigned to the terminal.

When an operator disables operator status on all terminals, including the system console terminal, OPCOM records all subsequent messages in the operator log file, except user requests and messages requiring an operator reply.

```
%OPCOM-S-OPRNOTIF, operator notified, waiting. 10:06:03.25
```

```
%OPCOM-S-OPREPLY, %OPCOM 24-DEC-2001 10:06:03:25, no operator coverage
```

To determine the operator status and to obtain a list of pending requests for a particular terminal, the operator enters the following command:

```
$ REPLY/STATUS
```

This command also shows all outstanding requests for this operator.

## Closing the Operator's Log File and Opening a New One

To close the current operator's log file and open anew one, the operator enters the **REPLY/LOG** command. If OPCOM is running, all subsequent messages are recorded in the new log file. To close the current log file without opening a new one, the operator enters the **REPLY/NOLOG** command. All subsequent messages are not recorded until the operator enters the **REPLY/LOG** command.

## Qualifiers

### **/ABORT=identification-number**

Sends a message to the user or magnetic tape file system corresponding to the unique identification number and cancels the request.

### **/ALL**

Requires OPER (operator) privilege.

Broadcasts a message to all terminals that are attached to the system or cluster. These terminals must be turned on and have broadcast-message reception enabled. The **/ALL** qualifier is incompatible with the **/USERNAME** and **/TERMINAL** qualifiers.

### **/BELL**

Rings a bell at the terminal receiving a message when entered with the **/ALL**, the **/TERMINAL**, or the **/USERNAME** qualifier; two bells when entered with the **/URGENT** qualifier; and three bells when entered with the **/SHUTDOWN** qualifier.

### **/BLANK\_TAPE=identification-number**

Requires VOLPRO (volume protection) privilege.

Sends a message to the magnetic tape file system indicated by the identification number to override the checking of volume label information. The volume label must be specified in the *message-text* parameter. The current terminal must be enabled as an operator terminal for TAPES.

### **/DISABLE[=(keyword[,...])]**

Requires OPER (operator) privilege. Requires OPER and SECURITY privileges for security messages.

If the operator communication manager (OPCOM) is running, restores to normal(that is, non operator) status the terminal at which the command is entered. The **/DISABLE** qualifier cannot be entered from a batch job. To restrict the types of messages displayed on an operator's terminal, specify one of the following keywords:

| Keyword         | Description                                                                                                       |
|-----------------|-------------------------------------------------------------------------------------------------------------------|
| CARDS           | Inhibits messages sent to the card readers.                                                                       |
| CENTRAL         | Inhibits messages sent to the central system operator.                                                            |
| CLUSTER         | Inhibits messages from the connection manager pertaining to cluster state changes.                                |
| DEVICES         | Inhibits messages pertaining to mounting disks.                                                                   |
| DISKS           | Inhibits messages pertaining to mounting and dismounting disk volumes.                                            |
| LICENSE         | Inhibits messages pertaining to software licenses.                                                                |
| NETWORK         | Inhibits messages pertaining to networks; the keyword CENTRAL must also be specified to inhibit network messages. |
| OPER1 to OPER12 | Inhibits messages sent to operators identified as OPER1 to OPER12.                                                |
| PRINTER         | Inhibits messages pertaining to print requests.                                                                   |
| SECURITY        | Inhibits messages pertaining to security events; requires SECURITY privilege.                                     |
| TAPES           | Inhibits messages pertaining to mounting and dismounting tape volumes.                                            |

When an operator logs out from a remote or a dial-in terminal, the operator terminal is automatically disabled.

### **/ENABLE[=(keyword[,...])]**

Requires OPER (operator) privilege. Requires OPER and SECURITY privileges for security messages.

Designates as an operator's terminal the terminal at which the **REPLY** command is entered, if OPCOM is running. The **/ENABLE** qualifier cannot be entered from a batch job. To enable the following types of messages displayed on an operator's terminal, specify one of the following keywords:

| Keyword         | Description                                                                                                       |
|-----------------|-------------------------------------------------------------------------------------------------------------------|
| CARDS           | Displays messages sent to the card readers.                                                                       |
| CENTRAL         | Displays messages sent to the central system operator.                                                            |
| CLUSTER         | Displays messages from the connection manager pertaining to cluster state changes.                                |
| DEVICES         | Displays messages pertaining to mounting disks.                                                                   |
| DISKS           | Displays messages pertaining to mounting and dismounting disk volumes.                                            |
| LICENSE         | Displays messages pertaining to software licenses.                                                                |
| NETWORK         | Displays messages pertaining to networks; the keyword CENTRAL must also be specified to inhibit network messages. |
| OPER1 to OPER12 | Displays messages sent to operators identified as OPER1 to OPER12.                                                |
| PRINTER         | Displays messages pertaining to print requests.                                                                   |
| SECURITY        | Allows messages pertaining to security events; requires SECURITY privilege.                                       |
| TAPES           | Allows messages pertaining to mounting and dismounting tape volumes.                                              |

#### ***/INITIALIZE\_TAPE=identification-number***

Sends a message to the magnetic tape file system indicated by the identification number to initialize a magnetic tape volume. This qualifier can be used whenever the file system requests the mounting of a new volume. The system performs normal protection and expiration checks before initializing the volume. The current terminal must be enabled as an operator terminal for TAPES.

If the tape drive cannot read the volume, the mount fails and an error message is returned. Use the **/BLANK\_TAPE** qualifier to override the checking of information on a volume label.

#### ***/LOG*** ***/NOLOG***

Requires OPER (operator) privilege.

Closes the current operator's log file and opens a new one if OPCOM is running. The **/NOLOG** qualifier closes the current log file, but does not open anew log file. The current terminal must be enabled as an operator terminal. The operator can then examine the contents of the previous log file.

#### ***/NODE[=(node-name[,...])]***

Sends a message to the local cluster node only. The optional parameter list allows you to specify which nodes will receive the message. Default sends messages to all cluster nodes.

#### ***/NOTIFY (default)*** ***/NONOTIFY***

Sends a message describing success back to the originating terminal.

***/PENDING=identification-number***

Requires OPER privilege.

Sends a message to the user specified by the identification number and prevents the user from entering other commands until the operator fulfills or aborts the request. The current terminal must be enabled as an operator terminal.

***/SHUTDOWN***

Sends a message beginning "SHUTDOWN..."; if used with the **/BELL** qualifier, rings three bells at terminals receiving the message.

***/STATUS***

Requires OPER (operator) privilege.

Reports the current operator status and all outstanding user requests for the terminal from which this command was entered. The current terminal must be enabled as an operator terminal.

***/TEMPORARY***

Designates the terminal at which the command is entered to be an operator's terminal for the current interactive session only. This qualifier is meaningful only when used with the **/ENABLE** qualifier.

***/TERMINAL=(terminal-name[,...])***

Requires OPER (operator) privilege.

Broadcasts the message to specified terminals, where the *terminal-name* parameter is the device name of the terminal. Incompatible with the **/ALL** and **/USERNAME** qualifiers.

***/TO=identification-number***

Requires OPER (operator) privilege.

Sends a message to the user or file system specified by the identification number and completes the request. The current terminal must be enabled as an operator terminal.

Note that you can also use a variation of the **REPLY/TO** command in response to a **MOUNT/ASSIST** command where you redirect the mount operation to another device. Whenever you must substitute a device, load the user's volume on the alternate device and prepare the device for connection before entering the **REPLY** command. Use the following syntax:

```
REPLY/TO=identification-number "SUBSTITUTE device-name"
```

You can abbreviate the word SUBSTITUTE to S and can use uppercase or lowercase characters. After a space, use the remainder of the *message-text* space to name the substituted device.

***/URGENT***

Sends a message beginning "URGENT..."; if used with the **/BELL** qualifier, rings two bells at terminals receiving the message.

***/USERNAME[=(username[,...])]***

Requires OPER (operator) privilege.

Broadcasts a message to all terminals at which users are logged in to the system (or OpenVMS Cluster), or only to the terminals of the specified users. Incompatible with the **/ALL** and **/TERMINAL** qualifiers.

## **/WAIT**

Sends a message synchronously and then waits. The default is to send a message to OPCOM, which does the actual I/O. On a cluster, the message is sent to the local node.

## Examples

1. `$ REPLY/ALL/BELL "SYSTEM GOING DOWN FOR BACK-UP. PLEASE LOG OFF."`

The **REPLY** command in this example broadcasts a message to all terminals on the system. When the message appears at the user's terminal, it is prefixed with the terminal name, the user name of the sender, and (when DECnet-Plus or DECnet for OpenVMS is installed) the node name. The bell sounds at the terminal as the message is displayed.

2. `$ REPLY/ENABLE=DISKS`  
`%OPCOM, 24-DEC-2001, 10:17:09.02, operator enabled, operator OPA0`  
`$`  
`%OPCOM, 24-DEC-2001 10:17:10.30, operator status for operator OPA0`  
`DISKS`

The **REPLY/ENABLE** command in this example designates the terminal OPA0 as an operator terminal that can receive messages pertaining to mounting and dismounting disks. The OPCOM message confirms that terminal OPA0 is established as an operator's terminal.

3. `%OPCOM, 24-DEC-2001 10:19:33.21, request 5, from user SYSTEM`  
`OPA0, Please mount OPGUIDE on DKA3:`  
`$ REPLY/PENDING=5 "YOU'LL HAVE TO WAIT... -`  
`_ $ THERE ARE SEVERAL REQUESTS BEFORE YOURS"`  
`.`  
`.`  
`.`  
`$ REPLY/TO=5`  
`24-DEC-2001 10:20:25.50, request 5 completed by operator OPA0`

In this example the OPCOM message indicates that a user wants the operator to place the disk volume labeled OPGUIDE on the disk drive DKA3 and prepare the device for connection. The **REPLY/PENDING** command indicates that the operator can perform the task but not immediately; the **/PENDING** qualifier prevents the user from entering other commands until the operator fulfills or aborts the request. After mounting the disk on the drive the operator sends a message indicating that the request has been fulfilled. When no message is specified, OPCOM sends a standard message indicating that the task has been performed.

4. `%%%%%%%% OPCOM, 24-DEC-2001 10:20:50.39 %%%%%%%%%`  
`request 5 from user ROBINSON`  
`Please mount volume GRAPHIC_FILES in device _DUA11:`  
`Shelf 4 - slot B`  
`$ REPLY/TO=5 "SUBSTITUTE DUA4"`

The **REPLY/TO** command with the **SUBSTITUTE** syntax in this example is used in response to a **MOUNT/ASSIST** command entered by user ROBINSON. The **MOUNT** device is switched to DUA4, and the logical name specified by the user in the **MOUNT** command is defined with an equivalence name of DUA4 rather than the drive originally specified.

5. `$ REPLY/STATUS`  
`%OPCOM, 24-DEC-2001 10:20:50.39, operator status for operator OPA0`  
`DISKS`

The **REPLY/STATUS** command in this example requests that the operator terminal status for terminal OPA0 be displayed. The response from OPCOM indicates that terminal OPA0 is enabled to receive messages from disk devices.

6. `$ REPLY/BELL/TERMINAL=TTC1: "YOUR FILE HAS COMPLETED PRINTING. BOB S."`

The **REPLY** command in this example sends a message to the user logged in at terminal TTC1. When the message displays, a bell rings at that terminal.

7. `$ REPLY/ENABLE`  
`%OPCOM, 24-DEC-2001 10:22:19.75, operator status for operator OPA0`  
`CENTRAL, PRINTER, TAPES, DISKS, DEVICES, CARDS, NETWORK, CLUSTER,`  
`LICENSE, OPER11, OPER12`

`.`  
`.`  
`.`

`$ REPLY/DISABLE=(PRINTER, TAPES)`  
`%OPCOM, 24-DEC-2001 10:22:26.07, operator disabled, operator OPA0`

The **REPLY/ENABLE** command in this example designates terminal OPA0 to receive messages from all facilities. Later, the **REPLY/DISABLE** command selectively disables OPA0 from receiving messages pertaining to print devices and tapes.

## REQUEST

**REQUEST** — Displays a message at a system operator's terminal and optionally requests a reply. All messages are logged at the operator's console and in the operator's log file, if that file is initialized. To use this command, you must start the operator communication process (OPCOM) at boot time by specifying the DCL command `@SYS$SYSTEM:STARTUP OPCOM` in the site-specific startup command file, `SYS$MANAGER:SYSTARTUP.COM`.

## Format

**REQUEST***message-text*

## Parameter

*message-text*

Specifies the text of the message to be displayed. The string can be up to 128 characters. If the string contains spaces, special characters, or lower-case characters, enclose it in quotation marks (" ").

## Description

When you use the **REQUEST** command to send a message to an operator, the message is displayed at the operator terminals specified with the **/TO** qualifier.

If you specify the **/REPLY** qualifier, the message is assigned an identification number, so the operator can respond to the message. The system displays the following message:

```
%OPCOM-S-OPRNOTIF, operator notified, waiting...hh:mm:ss
```

When the operator responds to your request, the system displays a message such as the following:

```
%OPCOM-S-OPREPLY, message text entered by operator
```

If you request a reply, you cannot enter any commands until the operator responds. If you press **Ctrl/C**, the system displays the following message:

```
REQUEST - Enter message or cancel with ^Z
REQUEST - Message?
```

At this time, you can either enter another message, or press **Ctrl/Z** to cancel the request. If you enter another message, that message is sent to the operator, and you must continue to wait for a reply.

All messages are logged at the central operator's console and in the system operator's log file, if that file is initialized.

## Qualifiers

### **/REPLY**

Requests a reply to the message and issues a unique identification number to which the operator sends the response. The system displays a message that the operator has been notified; you cannot enter any commands until the operator responds. If you press **Ctrl/C** before the operator responds, you can then enter another message to the operator, or press **Ctrl/Z** to cancel the request.

### **/TO=(operator[,...])**

Specifies one or more operators to whom you want to send the message. Possible keywords are as follows:

| Keyword         | Description                                                                        |
|-----------------|------------------------------------------------------------------------------------|
| CARDS           | Sends the message to operators designated to respond to card reader requests.      |
| CENTRAL         | Sends the message to the central system operator.                                  |
| CLUSTER         | Sends the message to operators designated to respond to cluster-related requests.  |
| DEVICES         | Sends the message to operators who mount and dismount disks.                       |
| DISKS           | Sends the message to operators who mount and dismount disk volumes.                |
| NETWORK         | Sends the message to the network operator.                                         |
| OPER1 to OPER12 | Sends the message to operators identified as OPER1 to OPER12.                      |
| PRINTER         | Sends the message to operators designated to handle print requests.                |
| SECURITY        | Sends the message to operators designated to respond to security-related requests. |
| TAPES           | Sends the message to operators designated to mount and dismount tape volumes.      |

## Examples

1. \$ PRINT/COPIES=2/QUEUE=LQ\_PRINT REPORT.OUT/FORM=LETTER  
Job REPRT (queue LQA1, entry 401) pending

```
$ REQUEST/REPLY/TO=PRINTER -
_ $"Have queued job 401 as FORM=LETTER; can you print it?"
%OPCOM-S-OPRNOTIF, operator notified, waiting...10:42:16.10
%OPCOM-S-OPREPLY, AFTER 11:00
14-DEC-2001 10:25:32.40, request 3 completed by operator OPA0
```

In this example the **PRINT** command requests that multiple copies of a file be printed using a special paper (**/FORM=LETTER**). After queueing the job to the printer, the **REQUEST** command sends a message to the system operator.

The operator sends a reply after completing the request.

2. 

```
$ REQUEST/REPLY "Are you there?"
%OPCOM-S-OPRNOTIF, operator notified, waiting...14:54:30.33
Ctrl/C
REQUEST-Enter message or cancel request with ^Z
REQUEST-Message? Ctrl/Z
%OPCOM-S-OPRNOTIF, operator notified, waiting... 14:59:01.38
%OPCOM-F-RQSTCAN, request was canceled
```

In this example the **REQUEST** command issues a message and requests a response. When no operator replies to the question, **Ctrl/C** is used to interrupt the request; then **Ctrl/Z** is used to cancel it.

## RETURN

**RETURN** — Terminates a **GOSUB** subroutine procedure and returns control to the command following the calling **GOSUB** command.

### Format

**RETURN**[ *status-code* ]

### Parameter

*status-code*

Defines a longword (integer) value or expression equivalent to an integer value that gives the exit status of the subroutine by defining a numeric value for the reserved global symbol **\$STATUS**. The value can be tested by the next outer command level. The low-order 3 bits of the longword integer value change the value of the reserved global symbol **\$SEVERITY**. If you specify a status code, DCL interprets the code as a condition code. Note that even numeric values produce warning, error, and fatal error messages, and that odd numeric values produce either no message or a success or informational message.

If you do not specify a status code, the current value of **\$STATUS** is saved. When control returns to the outer command level, **\$STATUS** contains the status of the most recently executed command or program.

## Description

The **RETURN** command terminates the **GOSUB** subroutine and returns control back to the command following the calling **GOSUB** command.

When a DCL command, user program, or command procedure completes execution, the command interpreter saves the condition code value in the global symbol **\$STATUS**. The system maintains this

value in hexadecimal. If a **RETURN** command does not explicitly set a value for **\$STATUS**, the command interpreter uses the current value of **\$STATUS** to determine the error status.

The low-order 3 bits of the status value contained in **\$STATUS** represent the severity of the condition. The reserved global symbol **\$SEVERITY** contains this portion of the condition code. Severity values range from 0 to 4, as shown in the following table:

| Value | Severity             |
|-------|----------------------|
| 0     | Warning              |
| 1     | Success              |
| 2     | Error                |
| 3     | Information          |
| 4     | Severe (fatal) error |

Note that the success and information codes have odd numeric values, and that warning and error codes have even numeric values.

## Example

```
$ SHOW TIME
    15-DEC-2001 14:25:42
$ GOSUB SYMBOL
$ EXIT
$ SYMBOL:
$     SHOW SYMBOL RED
$     RED = "SET DEFAULT [LOWE.DCL] "
$     RETURN 1
```

The **GOSUB** command transfers control to the subroutine labeled **SYMBOL**. After the subroutine is executed, the **RETURN** command transfers control back to the command following the calling **GOSUB** statement, giving **\$STATUS** and **\$SEVERITY** a value of 1. The procedure then exits.

## RUN (Image)

**RUN (Image)** — Executes an image within the context of your process. You can abbreviate the **RUN** command to a single letter, **R**.

## Format

**RUN***filespec*

## Parameter

*filespec*

Specifies an executable image to be executed. The file type defaults to **.EXE**. The asterisk (\*) and the percent sign (%) wildcard characters are not allowed.

## Description

This command executes an image within the context of your process. You can abbreviate the **RUN** command to a single letter, **R**.

When working with installed images, if you specify an image name in the command line with an explicit version number (or a semicolon), the image runs with current process privileges. If you do not specify an explicit version number (or semicolon), the image runs with any privileges with which it was installed. See the relevant section in the [VSI OpenVMS System Management Utilities Reference Manual, Volume 1: A-L](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-i-a-l/#INSTALL_CH) [https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-i-a-l/#INSTALL\_CH] for more information about the Install utility.

If you invoke an image locally, you must have read (R) or execute (E) access to the image. If you have DECnet software installed and want to execute an image over the network, you must have read (R) access to the image.

If you are invoking an image that requires one or more parameters, you must use the Automatic Foreign Command format or the Foreign Command format. For additional information, see the string assignment statement (:=) in the [VSI OpenVMS DCL Dictionary: A–M](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_2) [https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\_2] and see the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/].

## Qualifier

**/DEBUG**

**/NODEBUG**

Executes the image under control of the debugger. The default is the **/DEBUG** qualifier if the image is linked with the **/DEBUG** qualifier and the **/NODEBUG** qualifier if the image is linked without the **/DEBUG** qualifier. The **/DEBUG** qualifier is invalid if the image is linked with the **/NOTRACEBACK** qualifier. The **/NODEBUG** qualifier overrides the effect of the **LINK/DEBUG** command. If the image was linked with the **/TRACEBACK** qualifier, traceback reporting is performed when an error occurs.

If the image was not linked with the debugger, you can specify the **/DEBUG** qualifier to request the debugger at execution time; however, if the **/NOTRACEBACK** qualifier was specified when the image was linked, the **/DEBUG** qualifier is invalid.

For a complete description of the OpenVMS Debugger, see the [VSI OpenVMS Debugger Manual](https://docs.vmssoftware.com/vsi-openvms-debugger-manual/) [https://docs.vmssoftware.com/vsi-openvms-debugger-manual/].

To get help on debugger commands from the DCL level, type the following command:

```
$ HELP/LIBRARY=SYS$HELP:DBG$HELP DEBUG
```

## Examples

1. `$ RUN LIBRA.EXE`

The image `LIBRA.EXE` starts executing in the process. If the image `LIBRA` has been installed with amplified privileges, it runs with those privileges because you have not explicitly specified a version number or a semicolon. Alternatively, the image `LIBRA.EXE` still runs with its amplified privileges, if you enter the **RUN** command as follows:

```
$ RUN LIBRA.EXE
```

2. `$ MACRO/ENABLE=DEBUG ORION`  
`$ LINK/DEBUG ORION`  
`$ RUN ORION`

```
OpenVMS I64 DEBUG64 Version V8.3-014
```

```
%DEBUG-I-INITIAL, Language:IMACRO, Module:ORION
DBG>
.
.
.
$ RUN/NODEBUG ORION
```

A program is compiled, linked, and run with the debugger. Subsequently, a **RUN/NODEBUG** command requests that the debugger, which is present in the image, not issue a prompt. If an error occurs while the image executes, the debugger can perform traceback and report on the error.

3. \$ RUN AQUARIUS.EXE;1

The image AQUARIUS.EXE starts executing in the process. If the image AQUARIUS.EXE has been installed with amplified privileges, it does not run with those privileges because you have specified a version number. Instead, the image runs with current process privileges only. When you specify a version number (or even just a semicolon), the image activator does not search its list of special images that have been installed with privileges. The process AQUARIUS still runs with only normal process privileges if you enter the **RUN** command as follows:

```
$ RUN AQUARIUS.EXE;
```

In this case, however, the highest version of the image AQUARIUS runs.

## RUN (Process)

**RUN (Process)** — Creates a subprocess or a detached process to run an image and deletes the process when the image completes execution. A subprocess is created if any of the qualifiers except the **/UIC** or the **/DETACHED** qualifier is specified. A detached process is created if the **/UIC** or the **/DETACHED** qualifier is specified and you have the IMPERSONATE user privilege.

## Format

**RUN***filespec*

## Parameter

*filespec*

Specifies the file name of an executable image to be executed in a separate process. The default file type is .EXE. The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification.

## Description

The **RUN** command creates a process to execute the specified image. If you specify the **/UIC** or the **/DETACHED** qualifier, the **RUN** command creates a detached process; otherwise, the **RUN** command creates a subprocess.

When you specify any qualifiers with the **RUN** command, the **RUN** command creates a process and displays the process identification (PID) code in SYSS\$OUTPUT. The newly created process executes the image named in the file specification. When the image has finished executing, the system deletes the process that was running that image.

By default, the **RUN** command creates a subprocess with the same user identification code (UIC), current disk and directory defaults, privileges, and priority as the current process.

If the detached process terminates unexpectedly and you want to find out why, you can use the Accounting utility to display the final exit status of the process. For more information, see the relevant section in the *VSI OpenVMS System Management Utilities Reference Manual, Volume 1: A-L* [[https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-i-a-l/#ACC\\_U](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-i-a-l/#ACC_U)].

Both the **/DETACHED** and the **/UIC** qualifiers request the **RUN** command to create a detached process. You must have the user privilege IMPERSONATE or CMKRNL to create a detached process with a different UIC. When you create a detached process, the resource quotas are established as follows:

- If you do not specify a value for a particular quota, that quota is given the value of the corresponding PQL\_D\* (default) system parameter.
- If you specify a value for a particular quota, that value is compared with the quotas for the creator process (maximum) and the system parameters PQL\_M\* (minimum). If the value you specify is within the allowed range, it is used for the new process. If you specify a value greater than the creator process's quota, the creator process's quota is used. If the specified value is less than the corresponding system parameter, the system parameter value is substituted.

However, if you have the IMPERSONATE or CMKRNL privilege, you can specify any quotas for the detached process.

## Input, Output, and Error Streams

Use the following qualifiers to assign equivalence names for the logical names SYS\$INPUT, SYS\$OUTPUT, and SYS\$ERROR for the process:

```
/INPUT  
/OUTPUT  
/ERROR
```

The equivalence names you specify for these process-permanent files are interpreted within the context of the process you are creating. For example, file type defaults, and logical name use and translation are image- and language-dependent.

## Defining Process Attributes

Use the following qualifiers to override the default attributes for a process:

```
/ACCOUNTING  
/DUMP  
/PRIORITY  
/PRIVILEGES  
/PROCESS_NAME  
/SERVICE_FAILURE  
/SWAPPING
```

## Assigning Resource Quotas

When you enter a **RUN** command to create a process, you can define quotas to restrict the amount of various system resources available to the process. The following resource quota is deductible when you

create a subprocess; that is, the value you specify is subtracted from your current quota and given to the subprocess:

| Qualifier   | Quota   |
|-------------|---------|
| /TIME_LIMIT | CPUTIME |

The quota amount is returned to your current process when the subprocess is deleted.

The system defines minimum values for each specifiable quota. If you specify a quota that is below the minimum, or if you specify a deductible quota that reduces your current quota below the minimum, the **RUN** command cannot create the process. To determine your current quotas, enter the **SHOWPROCESS/QUOTAS** command.

You can also specify limits for nondeductible quotas. Nondeductible quotas are established and maintained separately for each process and subprocess. The following qualifiers specify nondeductible quotas:

| Qualifier            | Quota     |
|----------------------|-----------|
| /AST_LIMIT           | ASTLM     |
| /EXTENT              | WSEXTENT  |
| /IO_BUFFERED         | BIOLM     |
| /IO_DIRECT           | DIOLM     |
| /MAXIMUM_WORKING_SET | WSQUOTA   |
| /WORKING_SET         | WSDEFAULT |

A third type of quota treatment is pooling. Pooled quotas are established when a detached process is created. They are shared by that process and all its descendent subprocesses. Charges against pooled quota values are subtracted from the current available totals as they are used and are added back to the total when they are not being used. The following qualifiers specify pooled quotas:

| Qualifier         | Quota     |
|-------------------|-----------|
| /BUFFER_LIMIT     | BYTLM     |
| /ENQUEUE_LIMIT    | ENQLM     |
| /FILE_LIMIT       | FILLM     |
| /PAGE_FILE        | PGFLQUOTA |
| /QUEUE_LIMIT      | TQELM     |
| /SUBPROCESS_LIMIT | PRCLM     |

## Hibernation and Scheduled Wakeup Requests

Use the following qualifiers to schedule execution of the image:

**/DELAY**  
**/INTERVAL**  
**/SCHEDULE**

If you specify any of these qualifiers, the **RUN** command creates the process and places it in hibernation. The process cannot execute the image until it is awakened. Time values specified with these three qualifiers control when the process is awakened to execute the specified image.

You can schedule wakeup requests for a specified delta time (**/DELAY** qualifier) or absolute time (**/SCHEDULE** qualifier). You can also schedule wakeup requests for recurrent intervals with the **/INTERVAL** qualifier. If you specify an interval time, the created process is awakened to execute the specified image at fixed time intervals. If the image terminates normally (for example, by a **RET** instruction), the process returns to a state of hibernation, awaiting the next scheduled wakeup time and user-mode exit handlers are not called. At the next wakeup time, the image is recalled at its entry point; the image is not reactivated. If the image terminates abnormally, or by an **\$EXIT** command, or by a **\$FORCEX** command, the process does not return to hibernation, further scheduling requests are terminated, user-mode exit handlers are called, the image exits, and the created process is deleted.

Use the **/PROCESS\_NAME** qualifier to give the created process a name. You can use this process name in a subsequent **STOP** or **CANCEL** command. A **STOP** command terminates execution of the image in the process and causes the process to be deleted. The **CANCEL** command cancels wakeup requests that are scheduled but have not yet been delivered.

## Qualifiers

### **/ACCOUNTING (default)**

#### **/NOACCOUNTING**

Requires ACNT (accounting) privilege to use the **/NOACCOUNTING** qualifier.

The **/NOACCOUNTING** qualifier stops the current accounting file tracking the resources used by the created process.

The **/ACCOUNTING** qualifier (the default) has no effect.

### **/AST\_LIMIT=quota**

Specifies the maximum number of asynchronous system traps (ASTs) that the created process can have outstanding.

If you do specify an AST limit quota, the default quota established at system generation time is used. The minimum required for any process to execute is 2.

The AST limit quota is nondeductible.

### **/AUTHORIZE**

#### **/NOAUTHORIZE (default)**

Requires IMPERSONATE privilege.

When the image to be executed is the system login image (LOGINOUT.EXE), this qualifier searches the user authorization file (UAF) to validate a detached process. The **/NOAUTHORIZE** qualifier creates a detached process that runs under the control of the command interpreter.

When you specify the **/AUTHORIZE** qualifier, quotas are derived from the user authorization file (UAF) record of the process' owner. Any qualifiers to the **RUN** command that specify other quotas are ignored in favor of the UAF quotas.

When you specify the **/NOAUTHORIZE** qualifier, quotas are derived from the system parameters that set process quota default limits (parameters prefixed with **PQL\_D**).

Specify the **/AUTHORIZE** qualifier if you want the login image to check the UAF whenever a detached process is created. The process-permanent files specified by the **/INPUT** and **/OUTPUT** qualifiers are made available to the command interpreter for input and output.

**/BUFFER\_LIMIT=quota**

Specifies the maximum amount of memory, in bytes, that the process can use for buffered I/O operations or for temporary mailbox creation.

If you do not specify a buffered I/O quota, the default value established at system generation time is used. The minimum amount required for any process to execute is 1024 bytes.

The buffer limit quota is pooled.

**/DELAY=delta-time**

Places the created process in hibernation and awakens it after a specified time interval.

Specify the delta time according to the rules described for entering delta times in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DELTA_TIME) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DELTA\_TIME] or the online help topic Date.

If you specify both the **/DELAY** and **/INTERVAL** qualifiers, the first wakeup request occurs at the time specified by the **/DELAY** qualifier. All subsequent wakeup requests occur at the interval specified by the **/INTERVAL** qualifier.

**/DETACHED**

Creates a detached process with the same user identification code (UIC) as the current process. (To create a detached process with a different UIC, use the **/UIC** qualifier.) By default, the created process is not a detached process.

By default, resource quotas for the detached process are limited by the quotas of the creator process (maximum) and the system parameters PQL\_M\*(minimum). The IMPERSONATE or CMKRNL privilege allows you to specify any quotas for the detached process that exceed the normal range. Unless you have the IMPERSONATE or CMKRNL privilege, the maximum number of detached processes that you can create is limited to the quota defined by MAX\_DETACH in your UAF.

**/DUMP****/NODUMP (default)**

When an image terminates because of an unhandled error, the **/DUMP** qualifier causes the contents of the address space to be written to the file named *image-name*.DMP in the process's default device and directory. You can then use the Analyze/Process\_Dump utility to analyze the dump.

**/ENQUEUE\_LIMIT=quota**

Specifies the maximum number of locks that a process can have outstanding at any one time.

The default quota is that established at system generation time. The minimum required for any process to operate is 2.

**/ERROR=filespec**

Defines an equivalence name string of 1 to 63 alphanumeric characters for the logical device name SYS\$ERROR. The logical name and equivalence name are placed in the process logical name table for the created process. (The **/ERROR** qualifier is ignored if you are running SYS\$SYSTEM:LOGINOUT.)

***/EXTENT=quota***

Specifies the maximum size to which the image being executed in the process can increase its physical memory size.

The default quota is that established at system generation time. The minimum value required for any process to execute is 10 pages.

Specify the value of *n* as a number of 512-byte pagelets on Alpha. Note that the operating system rounds up this value to the nearest CPU-specific page so that actual amount of physical memory allowed may be larger than the specified amount on Alpha.

The extent quota is nondeductible.

***/FILE\_LIMIT=quota***

Specifies the maximum number of files that a process can have open at any onetime.

The default quota is the quota established at system generation time. The minimum amount required for any process to execute is 2.

The file limit quota is pooled.

***/INPUT=filespec***

Defines an equivalence name string of 1 to 63 characters for SYS\$INPUT. The logical name and equivalence name are placed in the process logical name table for the created process.

***/INTERVAL=delta-time***

Requests that the created process be placed in hibernation and be awakened at regularly scheduled intervals.

Specify the delta time according to the rules described in the [VSI OpenVMS User's Manual \[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DELTA\\_TIME\]](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DELTA_TIME) or the online help topic Date.

If you specify the **/DELAY** or the **/SCHEDULE** qualifier with the **/INTERVAL** qualifier, the first wakeup request occurs at the time specified by the **/DELAY** or the **/SCHEDULE** qualifier; all subsequent wakeup requests occur at intervals specified by the **/INTERVAL** qualifier. If you specify neither the **/DELAY** nor the **/SCHEDULE** qualifier with the **/INTERVAL** qualifier, the first wakeup request occurs immediately by default.

***/IO\_BUFFERED=quota***

Specifies the maximum number of system-buffered I/O operations that the created process can have outstanding at any one time.

The default quota is the quota established at system generation time. The minimum required for any process to execute is 2.

The buffered I/O quota is nondeductible.

***/IO\_DIRECT=quota***

Specifies the maximum number of direct I/O operations that the created process can have outstanding at any one time.

The default quota is the quota established at system generation time. The minimum required for any process to execute is 2.

The direct I/O quota is nondeductible.

#### ***/JOB\_TABLE\_QUOTA=quota***

Allows you to specify a quota for a detached process's jobwide logical name table.

A value of 0 has a special meaning. It means that the table, for all practical purposes, has infinite quota because its quota is pooled with that of its parent table, the system directory table.

Note that the **/JOB\_TABLE\_QUOTA** qualifier is relevant only for detached processes. If the **/JOB\_TABLE\_QUOTA** qualifier is specified in a RUN command that results in the creation of a subprocess, it is ignored.

#### ***/KERNEL\_THREAD\_LIMIT=n***

Sets the limit of the number of kernel threads that can be created in the new process. If the value specified is higher than the SYSGEN parameter MULTITHREAD, an error message is returned. Specifying the value 0 makes the process use the systemwide limit set by the MULTITHREAD parameter.

#### ***/MAILBOX=unit***

Specifies the unit number of a mailbox to receive a termination message when the created process is deleted. If no mailbox is specified, the creating process receives no notification when the subprocess or detached process has been deleted.

#### ***/MAXIMUM\_WORKING\_SET=quota***

Specifies the maximum size (up to 64K pages) to which the image being executed in the process can increase its working set size. An image can increase its working set size by calling the \$ADJWSL (Adjust Working Set Limit) system service.

The default quota is the quota established at system generation time. The minimum value required for any process to execute is 10 pages.

The maximum working set quota is nondeductible.

#### ***/ON=node\_name***

Specifies an OpenVMS Cluster node on which a detached process is to be created. Quotas are determined by comparing the values you specify with the **RUN** command with the quotas of the creator process (maximum) and the PQL\_M\* system parameters on the target node (minimum). To specify quotas outside that range, you must have IMPERSONATE or CMKRNL privilege. Omitted quota values default to the values of the PQL\_D\* system parameters on the target node.

The qualifier value *node\_name* is a 1- to 6-character string containing the SCS node name of the requested node.

For example, to create a process named BAR on node FOO that runs MY\_PROG.EXE, enter the following command:

```
$ RUN $10$DKB100:[SMITH]MY_PROG.EXE /DETACH /ON="FOO"/PROCESS_NAME="BAR"
```

Note that the disk containing the image must be mounted on the specified node. Because the disk might not be mounted on the node on which the command is entered, the **RUN** command processor does not check whether the image exists. Consequently, the command can complete without error even though the created process aborts immediately because the image file cannot be found.

***/OUTPUT=filespec***

Defines an equivalence name string of 1 to 63 characters for the logical device name SYS \$OUTPUT. Both the equivalence name and the logical name are placed in the process logical name table for the created process.

***/PAGE\_FILE=quota***

Specifies the maximum number of pagelets that can be allocated in the paging file for the process. The paging file quota is the amount of secondary storage available during execution of the image.

The default quota is the quota established at system generation time. The minimum value required for a process to execute is 256 pagelets. The paging file quota is pooled.

***/PRIORITY=n***

Requires ALTPRI (alter priority) privilege to set the priority higher than your current process.

Specifies the base priority at which the created process executes.

On Alpha, the value of parameter *n* is a decimal 0 to 63, where 63 is the highest priority and zero is the lowest. Normal priorities range from 0 to 15; real-time priorities range from 16 to 63.

The default priority is that of the current process.

***/PRIVILEGES=(privilege[,...])***

Requires SETPRV (set privilege) privilege to specify privileges that you do not have.

Defines user privileges for the created process. You can extend any privilege you possess to a process you create. By default, the created process has the same privileges as its creator. If you specify only one privilege, you can omit the parentheses.

For a list of process privileges, see the relevant section in the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#PRIVILEGE_SUBJ) [[https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#PRIVILEGE\\_SUBJ](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#PRIVILEGE_SUBJ)].

You can also use the keyword NOSAME as the *privilege* parameter. If you specify ***/PRIVILEGES=NOSAME***, the created process has no privileges.

***/PROCESS\_NAME=process-name***

Specifies a name of 1 to 15 characters for the created process. The process name is implicitly qualified by the group number of the process's user identification code (UIC). By default, the name is null.

***/QUEUE\_LIMIT=quota***

Specifies the maximum number of timer queue entries that the created process can have outstanding at any one time. This number includes timer requests and scheduled wakeup requests.

The default quota is the quota established at system generation time. A process does not require any timer queue quota in order to execute.

The timer queue entry quota is pooled.

**/RESOURCE\_WAIT (default)****/NORESOURCE\_WAIT**

Places the created process in a wait state when a resource required for a particular function is not available.

If you specify the **/NORESOURCE\_WAIT** qualifier, the process receives an error status code when a resource is unavailable.

**/SCHEDULE=*absolute-time***

Places the created process in hibernation and awakens it at the specified time.

Specify the absolute time value according to the rules given for entering absolute time values in the *VSI OpenVMS User's Manual* [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#ABSOLUTE\\_TIME](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#ABSOLUTE_TIME)] or the online help topic Date.

**/SERVICE\_FAILURE****/NOSERVICE\_FAILURE (default)**

Enables or disables an exception condition notification if an error occurs during a system service request. By default, an error status code is returned to the process.

If you specify the **/SERVICE\_FAILURE** qualifier and an error occurs during a system service request, the process encounters an exception condition.

**/SSLOG\_ENABLE[=COUNT=*n*] [,FLAGS=[NO]ARG]**

Valid on Alpha and Integrity server systems only.

Requires CMEXEC, CMKRNL, or SETPRV privilege to log argument values. The SYSGEN parameter SYSSER\_LOGGING must be enabled or the command will fail.).

Creates a process with system service logging enabled.

Keywords are as follows:

| Keyword         | Description                                                                                                                                                                                  |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| COUNT= <i>n</i> | Specifies how many P2-space buffers to log. (Default: 2)                                                                                                                                     |
| FLAGS=[NO]ARG   | Specifies whether or not service argument values are to be logged. The default is ARG, which requires privileges. If the value is ARG but you lack privilege, no argument values are logged. |

When enabling SSLOG for a process, you can specify the number of buffers to be used for logging. Buffers are allocated in P2 space and are charged against the process's paging file quota. Each buffer is 65,024<sub>10</sub> bytes or FE00<sub>16</sub> bytes. The buffer space remains allocated and the quota charged until the process is deleted.

Before you delete the process, stop the logging and close the log file by executing the **SET PROCESS /SSLOG=STATE=UNLOAD** command. The log file does not close automatically.

To analyze the log file, use the DCL command **ANALYZE/SSLOG**, which is described in online help and in the relevant section in the *VSI OpenVMS System Analysis Tools Manual* [<https://docs.vmssoftware.com/vsi-openvms-system-analysis-tools-manual/#d0e28672>].

#### **/SUBPROCESS\_LIMIT=quota**

Specifies the maximum number of subprocesses that the created process is allowed to create.

The default quota is the quota established at system generation time. A process does not require any subprocess quota in order to execute.

The subprocess limit quota is pooled.

#### **/SWAPPING (default)**

#### **/NOSWAPPING**

Requires PSWAPM (process swap mode) privilege to inhibit process swapping.

Permits the process to be swapped. The default allows a process to be swapped from the balance set in physical memory to allow other processes to execute.

With **/NOSWAPPING** in effect, the process is not swapped out of the balance set when it is in a wait state. By default, a process may be swapped out of the balance set whenever it is in a wait state.

#### **/TIME\_LIMIT=limit**

Specifies the maximum amount of CPU time (in delta time) a created process can use. CPU time is allocated to the created process in units of 10 milliseconds. When it has exhausted its CPU time limit quota, the created process is deleted.

If this quota is not specified and the created process is a detached process, the detached process receives a default value of zero, that is, unlimited CPU time.

If this quota is not specified and the created process is a subprocess, the subprocess receives half the CPU time limit quota of the creating process.

If this quota is specified as zero, the created process has unlimited CPU time providing that the creating process also has unlimited CPU time. If, however, the creating process does not have unlimited CPU time, the created process receives half the CPU time limit quota of the creating process.

The CPU time limit quota is a consumable quota; that is, the amount of CPU time used by the created process is not returned to the creating process when the created process is deleted.

If you restrict CPU time for a process, specify the time limit according to the rules for specifying delta time values, as described in the relevant section in the *VSI OpenVMS User's Manual* [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DELTA\\_TIME](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DELTA_TIME)] or the online help topic Date.

#### **/TRUSTED**

Specifies that the created process is part of the Trusted Computing Base (TCB) and performs its own auditing. The **/DETACH** qualifier is required as well as the IMPERSONATE privilege.

#### **/UIC=uic**

Specifies that the created process be a detached process and assigns it a user identification code (UIC). Specify the UIC by using standard UIC format as described in the relevant section in the *VSI*

*OpenVMS Guide to System Security* [[https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC\\_SECTION](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC_SECTION)].

### **/WORKING\_SET=default**

Specifies the number of pages in the working set of the created process.

The default working set size is the size established at system generation time. The minimum number of pages required for a process to execute is 10 pages. The value specified cannot be greater than the quota specified with **/MAXIMUM\_WORKING\_SET**.

The maximum working set quota is nondeductible.

## **Examples**

1. \$ RUN/PROCESS\_NAME=SUBA SCANLINE  
%RUN-S-PROC\_ID, identification of created process is 00010044.

In this example, the **RUN** command creates a subprocess named SUBA to run the image SCANLINE . EXE. The system gives the subprocess an identification number of 00010044.

2. \$ RUN/DELAY=3:30/OUTPUT=BALANCE.OUT BALANCE

In this example, the **RUN** command creates a subprocess to run the image BALANCE . EXE 3 hours and 30 minutes from now; output is written to the file BALANCE . OUT.

3. \$ RUN/INTERVAL=1:40/PROCESS\_NAME=STAT STATCHK  
%RUN-S-PROC\_ID, identification of created process is 00050023  
.  
.  
.  
\$ CANCEL STAT

In this example, the **RUN** command creates a subprocess named STAT to execute the image STATCHK . EXE. The process is scheduled to execute the image at intervals of 1 hour and 40 minutes. The process hibernates; however, because neither the **/DELAY** nor the **/SCHEDULE** qualifier is specified, the first wakeup request occurs immediately.

The **CANCEL** command subsequently cancels the wakeup requests posted by the **/INTERVAL** qualifier. If the process is currently executing the image, it completes the execution and hibernates.

4. \$ RUN/PROCESS\_NAME=LYRA LYRA -  
\_\$/OUTPUT=\_TTB3: -  
\_\$/ERROR=\_TTB3:  
%RUN-S-PROC\_ID, identification of created process is 000A002F

In this example, the **RUN** command creates a subprocess named LYRA to execute the image LYRA . EXE. The **/OUTPUT** and **/ERROR** qualifiers assign equivalences to the logical names SYS\$OUTPUT and SYS\$ERROR for the subprocess. Any messages the subprocess writes to its default output devices are displayed on the terminal TTB3.

5. \$ RUN/UIC=[100,4]/PRIVILEGES=(SAME,NOPSWAPM) -  
\_\$/NORESOURCE\_WAIT OVERSEER  
%RUN-S-PROC\_ID, identification of created process is 0001002C

In this example, the **RUN** command creates a detached process to execute under the UIC [100,4]. The image OVERSEER . EXE is executed. The **RUN** command gives the process all the privileges of

the current process, except the ability to alter its swap mode. The **/NORESOURCE\_WAIT** qualifier disables resource wait mode for the process.

## RUNOFF

**RUNOFF** — Invokes the DIGITAL Standard Runoff (DSR) text formatter to format one or more ASCII files. Creates formatted files from source DSR (.RNO) files, unformatted table of contents (.RNT) files, and unformatted index (.RNX) files. Optionally creates intermediate (.BRN) files for input to **RUNOFF/CONTENTS** and **RUNOFF/INDEX** commands. For more information about the **RUNOFF**, **RUNOFF/CONTENTS**, and **RUNOFF/INDEX** commands and for a description of the DSR formatter, see the [VSI OpenVMS DIGITAL Standard Runoff Reference Manual \[https://docs.vmssoftware.com/digital-standard-runoff-reference-manual/\]](https://docs.vmssoftware.com/digital-standard-runoff-reference-manual/) or online help.

### Format

**RUNOFF***filespec*[,...]

## SEARCH

**SEARCH** — Searches one or more files for the specified strings and displays the lines containing those strings.

### Format

**SEARCH** *filespec*[,...] *search-string*[,...]

### Parameters

*filespec*[,...]

Specifies one or more files to be searched. You must specify at least one file name. If you specify more than one file name, separate the file specifications with commas (.).

You can use the asterisk (\*) and the percent sign (%) wildcard characters in the file specification.

*search-string*[,...]

Specifies the character string to be located in the specified files. Enclose strings containing lowercase letters, blanks, or other non-alphanumeric characters (including spaces) in quotation marks (" ").

You can use the **/MATCH** and **/EXACT** qualifiers to alter the way that **SEARCH** matches search strings.

### Description

The **SEARCH** command searches through files for specific character strings; all lines containing occurrences of the strings are displayed. Use the **SEARCH** qualifiers to tailor the search operation to your specific needs.

The **SEARCH** command opens the file with shared read (R) and write (W) access. Therefore, any file that has its attributes set to shared write is searched even if it is currently opened by other users.

## Qualifiers

### **/BACKUP**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/BACKUP** qualifier selects files according to the dates of their most recent backups. This qualifier is incompatible with the **/CREATED**, **/EXPIRED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

### **/BEFORE[=*time*]**

Selects only those files dated prior to the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: **BOOT**, **LOGIN**, **TODAY** (default), **TOMORROW**, or **YESTERDAY**. Specify one of the following qualifiers with the **/BEFORE** qualifier to indicate the time attribute to be used as the basis for selection: **/BACKUP**, **/CREATED** (default), **/EXPIRED**, or **/MODIFIED**.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic **Date**.

### **/BY\_OWNER[=*uic*]**

Selects only those files whose owner user identification code (UIC) matches the specified owner UIC. The default UIC is that of the current process.

Specify the UIC by using standard UIC format as described in the relevant section in the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC_SECTION) [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC\_SECTION].

### **/CONFIRM**

#### **/NOCONFIRM (default)**

Controls whether a request is issued before each search operation to confirm that the operation should be performed on that file. The following responses are valid:

|      |       |               |
|------|-------|---------------|
| YES  | NO    | QUIT          |
| TRUE | FALSE | <b>Ctrl/Z</b> |
| 1    | 0     | ALL           |

#### **Return**

You can use any combination of uppercase and lowercase letters for word responses. Word responses can be abbreviated to one or more letters (for example, **T**, **TR**, or **TRU** for **TRUE**), but these abbreviations must be unique. Affirmative answers are **YES**, **TRUE**, and **1**. Negative answers include: **NO**, **FALSE**, **0**, and pressing **Return**. Entering **QUIT** or pressing **Ctrl/Z** indicates that you want to stop processing the command at that point. When you respond by entering **ALL**, the command continues to process, but no further prompts are given. If you type a response other than one of those in the list, DCL issues an error message and redisplay the prompt.

### **/CREATED (default)**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/CREATED** qualifier selects files based on their dates of creation. This qualifier is incompatible with the

**/BACKUP**, **/EXPIRED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

### **/EXACT**

#### **/NOEXACT (default)**

Controls whether the **SEARCH** command matches the search string exactly or treats uppercase and lowercase letters as equivalents. By default, **SEARCH** ignores case differences in letters.

Specifying the **/EXACT** qualifier causes the system to use less CPU time; therefore, if you are sure of the case of the letters in the string, it is more efficient to use the **/EXACT** qualifier.

### **/EXCLUDE=(filespec[,...])**

Excludes the specified files from the search operation. You can include a directory but not a device in the file specification. The asterisk (\*) and the percent sign (%) wildcard characters are allowed in the file specification; however, you cannot use relative version numbers to exclude a specific version. If you specify only one file, you can omit the parentheses.

### **/EXPIRED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/EXPIRED** qualifier selects files according to their expiration dates. (The expiration date is set with the **SET FILE/EXPIRATION\_DATE** command.) The **/EXPIRED** qualifier is incompatible with the **/BACKUP**, **/CREATED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

### **/FORMAT=option**

Formats output in one of the following five ways:

| Option  | Description                                                                                                                                                                                                                                                                                                                                                                                                        |
|---------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DUMP    | Displays all control characters (including <HT>, <CR>, and <LF>) and non-printable characters as ANSI mnemonics.                                                                                                                                                                                                                                                                                                   |
| NOFF    | Replaces control characters in text with ANSI mnemonics (for example, <b>Ctrl/C</b> is replaced with <ETX>). The terminal formatting characters <HT>, <CR>, <LF>, <VT> are passed without change. Form feed characters are replaced with <FF>.                                                                                                                                                                     |
| NONULLS | Same as DUMP, but removes all null characters from the input file before reformatting. (In dump mode, the null character is displayed as <NUL>.) NONULLS is convenient when you are searching binary format files, such as EXE or OBJ files, that generally contain many zero bytes.                                                                                                                               |
| PASSALL | Moves control and non-printable characters to the output device without translating them. The terminal driver cannot send 8-bit characters to the terminal unless <b>SET TERMINAL/EIGHT_BIT</b> is already in effect.<br><br>You can use <b>/FORMAT=PASSALL</b> whenever you do not want the <b>SEARCH</b> command to substitute the ANSI mnemonic for control characters (for example, <BEL> for <b>Ctrl/G</b> ). |

| Option | Description                                                                                                                                                                                                                             |
|--------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| TEXT   | Replaces control characters in text with ANSI mnemonics (for example, <b>Ctrl/C</b> is replaced with <ETX>). The terminal formatting characters <HT>, <CR>, <LF>, <VT>, and <FF> are passed without change. TEXT is the default format. |

**/HEADING (default)****/NOHEADING**

Includes file names in the output file and displays a line of 30 asterisks (\*) as a window separator between groups of lines that belong to different files. With the default heading format, file names are printed only when more than one file is specified or when the asterisk (\*) and the percent sign (%) wildcard characters are used.

The **/WINDOW** qualifier displays a line of 15 asterisks to separate each window within a file.

**/HIGHLIGHT[=keyword] (default)****/NOHIGHLIGHT**

You can use one of the following keywords: BOLD, BLINK, REVERSE, and UNDERLINE. BOLD is the default highlighting on ANSI video terminals with advanced video; REVERSE is the default highlighting on ANSI video terminals without advanced video.

For hardcopy printing, you can use the **HARDCOPY=OVERSTRIKE** and **HARDCOPY=UNDERLINE** keywords. This specifies that the strings should be highlighted in a manner suitable for most hardcopy printers. With overstrike highlighting, matched strings are double-printed, so that they appear darker. The matched strings are underlined with the underscore character.

Hardcopy printing is accomplished by adding a carriage return and spacing back over the line to overprint the string or underlines. Note that this can as much as double the length of the line, and perhaps lead to truncation if the device buffer size is too small.

VSI recommends that you use the **/HIGHLIGHT=UNDERLINE** qualifier with the LN01 printer rather than using the **/HIGHLIGHT=HARDCOPY=UNDERLINE** qualifier. The LN01 printer ignores OVERSTRIKE highlighting.

VSI recommends that you use either the **/HIGHLIGHT=BOLD** or the **/HIGHLIGHT=UNDERLINE** qualifier with the LN03 printer rather than using the **/HIGHLIGHT=HARDCOPY=UNDERLINE** qualifier. The LN03 printer ignores OVERSTRIKE highlighting.

---

**Note**

You cannot specify **/WILDCARD\_MATCHING** with **/HIGHLIGHT**. An error will occur.

---

**/KEY=(POSITION=*n*,SIZE=*n*)**

Searches the records of a file (beginning at the specified position)for the length of the specified size.

You can specify the POSITION keyword value as 1 to 32,767. The first byte in a record is considered position 1.

---

## Note

The **/KEY** qualifier must appear before the file name, or after the specified search string. If the qualifier is placed between these parameters, it is ignored.

---

### **/LIMIT=*n* (Alpha/Integrity servers Only)**

Limits the number of matches displayed to the number specified by *n*.

### **/LOG**

#### **/NOLOG (default)**

Outputs a message to the current SYS\$OUTPUT device for each file searched. The message includes the file name, the number of records, and the number of matches for each file searched.

### **/MATCH=*option***

Interprets and matches multiple search strings in one of the following ways:

| Option | Description                                                                                                     |
|--------|-----------------------------------------------------------------------------------------------------------------|
| AND    | A match occurs only if the record contains all the strings.                                                     |
| EQV    | A match occurs if none or all of the search strings are in the record.                                          |
| NOR    | A match occurs only if the record contains none of the strings.                                                 |
| NAND   | A match occurs only if the record does not contain all of the strings.                                          |
| OR     | A match occurs if the record contains any of the strings.                                                       |
| XOR    | A match occurs if any of the search strings are in the record but not if all or none of them are in the record. |

When only one search string is specified, the OR and AND options produce identical results. Similarly, NOR and NAND produce identical results for a single search string. If you specify none of these options, the default is **/MATCH=OR**.

### **/MODIFIED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/MODIFIED** qualifier selects files according to the dates on which they were last modified. This qualifier is incompatible with the **/BACKUP**, **/CREATED**, and **/EXPIRED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time modifiers, the default is the **/CREATED** qualifier.

### **/NUMBERS**

#### **/NONUMBERS (default)**

Controls whether the source line number is displayed at the left margin of each line in the output.

### **/OUTPUT[=*filespec*]**

#### **/NOOUTPUT**

Controls whether the results of the search are output to a specified file. The output is sent to the current default output device (SYS\$OUTPUT) if you omit the **/OUTPUT** qualifier or omit the file specification with the qualifier. The **/NOOUTPUT** qualifier means that no matching records are output as a result of the **SEARCH** command.

**/PAGE[=keyword]**  
**/NOPAGE (default)**

Controls the display of information on the screen.

You can use the following keywords with the **/PAGE** qualifier:

| Keyword           | Description                                                                               |
|-------------------|-------------------------------------------------------------------------------------------|
| CLEAR_SCREEN      | Displays information one page at a time.                                                  |
| SCROLL            | Displays information on a continuous stream.                                              |
| SAVE[= <i>n</i> ] | Enables screen navigation of information, where <i>n</i> is the number of pages to store. |

The **/PAGE=SAVE** qualifier allows you to navigate through screens of information. The **/PAGE=SAVE** qualifier stores up to 5 screens of up to 255 columns of information. When you use the **/PAGE=SAVE** qualifier, you can use the following keys to navigate through the information:

| Key Sequence                                                           | Description                                      |
|------------------------------------------------------------------------|--------------------------------------------------|
| Up arrow key, <b>Ctrl/B</b>                                            | Scroll up one line.                              |
| Down arrow key                                                         | Scroll down one line.                            |
| Left arrow key                                                         | Scroll left one column.                          |
| Right arrow key                                                        | Scroll right one column.                         |
| Insert Here ( <b>E2</b> )                                              | Scroll right one half screen.                    |
| Remove ( <b>E3</b> )                                                   | Scroll left one half screen.                     |
| Select ( <b>E4</b> )                                                   | Toggle 80/132 column mode.                       |
| Prev Screen ( <b>E5</b> )                                              | Get the previous page of information.            |
| Next Screen ( <b>E6</b> ), <b>Return</b> , <b>Enter</b> , <b>Space</b> | Get the next page of information.                |
| <b>F10</b> , <b>Ctrl/Z</b>                                             | Exit. (Some utilities define these differently.) |
| Help ( <b>F15</b> )                                                    | Display utility help text.                       |
| Do ( <b>F16</b> )                                                      | Toggle the display to oldest/newest page.        |
| <b>Ctrl/W</b>                                                          | Refresh the display.                             |

The **/PAGE** qualifier is not compatible with the **/OUTPUT** qualifier.

**/REMAINING**  
**/NOREMAINING (default)**

Includes in the output all records from the first matched record to the end of the file. This qualifier overrides the value *n2* in the **/WINDOW** qualifier, but allows the qualifier **/WINDOW=*n1***.

**/SINCE[=time]**

Selects only those files dated on or after the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: **BOOT**, **JOB\_LOGIN**, **LOGIN**, **TODAY** (default), **TOMORROW**, or **YESTERDAY**. Specify one of the following qualifiers with the **/SINCE** qualifier to indicate the time attribute to be used as the basis for selection: **/BACKUP**, **/CREATED** (default), **/EXPIRED**, or **/MODIFIED**.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic Date.

### **/SKIP=*n* (Alpha/Integrity servers Only)**

Skips the first *n* matches found before outputting match information.

### **/STATISTICS[=(*keyword*,...)]**

### **/NOSTATISTICS[=(*keyword*,...)] (default)**

Controls whether the following statistics about the search are displayed:

- Number of files searched
- Number of records searched
- Number of characters searched
- Number of records matched
- Number of lines printed
- Buffered I/O count
- Direct I/O count
- Number of page faults
- Elapsed CPU time
- Elapsed time

You can use the following keywords with the **/STATISTICS** qualifier:

| Keyword | Description                                                                                             |                                                                                                                                       |
|---------|---------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------|
| OUTPUT  | Writes the statistics output lines into the output file in addition to the standard SYS\$OUTPUT device. |                                                                                                                                       |
| SYMBOLS | Define symbols to hold statistic values. The symbol names are as follows:                               |                                                                                                                                       |
|         | SEARCH\$CHARACTERS_SEARCHED                                                                             | Displays the number of characters searched.                                                                                           |
|         | SEARCH\$CPU_TIME                                                                                        | Displays the total amount of CPU time that was charged to the process for the command during the time it took to complete the search. |
|         | SEARCH\$ELAPSED_TIME                                                                                    | Displays the total amount of wall clock time that it took to complete the search.                                                     |
|         | SEARCH\$FILES_SEARCHED                                                                                  | Displays the number of files searched.                                                                                                |
|         | SEARCH\$LINES_PRINTED                                                                                   | Displays the number of lines printed.                                                                                                 |
|         | SEARCH\$RECORDS_MATCHED                                                                                 | Displays the number of records matched.                                                                                               |
|         | SEARCH\$RECORDS_                                                                                        | Displays the number of records searched.                                                                                              |

| Keyword | Description |
|---------|-------------|
|         | SEARCHED    |

Using the **/STATISTICS** qualifier with no keywords is the equivalent of **/STATISTICS=(OUTPUT,SYMBOLS)**.

#### ***/STYLE=keyword***

Specifies the file name format for display purposes.

The valid keywords for this qualifier are **CONDENSED** and **EXPANDED**. Descriptions are as follows:

| Keyword             | Description                                                                                                                                                                           |
|---------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CONDENSED (default) | Displays the file name representation of what is generated to fit into a 255-length character string. This file name may contain a DID or FID abbreviation in the file specification. |
| EXPANDED            | Displays the file name representation of what is stored on disk. This file name does not contain any DID or FID abbreviations.                                                        |

The keywords **CONDENSED** and **EXPANDED** are mutually exclusive. This qualifier specifies which file name format is displayed in the output message, along with the confirmation if requested.

File errors are displayed with the **CONDENSED** file specification unless the **EXPANDED** keyword is specified.

See the relevant section in the *VSI OpenVMS User's Manual* [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE\\_ACCESS](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE_ACCESS)] for more information.

#### ***/SYMLINK=keyword***

The valid keywords for this qualifier are **[NO]WILDCARD** and **[NO]ELLIPSIS**. Descriptions are as follows:

| Keyword    | Description                                                                      |
|------------|----------------------------------------------------------------------------------|
| WILDCARD   | Indicates that symlinks are enabled during wildcard searches.                    |
| NOWILDCARD | Indicates that symlinks are disabled during directory wildcard searches.         |
| ELLIPSIS   | Equivalent to <b>WILDCARD</b> (included for command symmetry).                   |
| NOELLIPSIS | Indicates that symlinks are matched for all wildcard fields except for ellipsis. |

If the file named in the **SEARCH** command is a symlink, the command operates on the symlink target.

#### ***/WARNINGS (default)*** ***/NOWARNINGS***

Allows or disallows the following messages to be displayed when search operations are performed:

NOMATCHES  
TRUNCATE  
NULLFILE

**/WILDCARD\_MATCHING[= keyword] (Alpha/Integrity servers Only)**

Specifies that the following characters in the search string are to be interpreted as wildcard characters:

asterisk (\*) – Accept any number of unspecified characters in this position when searching for a match.

percent sign (%) – Accept any single character in this position when searching for a match.

The optional keyword can be either of the following:

RELAXED (default) – Automatically appends asterisks to the beginning and end of the string to be searched.

STRICT – Performs a narrow search based on the exact search string with no appended asterisks. An entire record must match the criteria specified for the wildcarded search.

---

**Note**

You cannot specify **/WILDCARD\_MATCHING** with **/HIGHLIGHT**. An error will occur.

---

**/WINDOW[=(n1,n2)]****/NOWINDOW (default)**

Specifies the number of lines to be displayed with the search string.

If you specify *n1* and *n2*, the **/WINDOW** qualifier displays *n1* lines above the search string, the search string, and *n2* lines below the search string. Either of these numbers can be zero.

If you specify the **/WINDOW** qualifier without the values *n1* and *n2*, two lines above the search string, the search string, and the two lines below the search string are included in the output.

If you specify the **/WINDOW** qualifier with a single number (*n1*), *n1* specifies the number of lines to display including the search string. Half the lines precede the matched search string and half follow it. (If *n1* is even, one line is added to the lines following the matched search string.)

For example, if you specify **/WINDOW=10**, nine additional lines are listed along with the line containing the search string. Four lines are listed above the line containing the search string and five lines are listed below it, for a total of 10 lines.

If you specify **/WINDOW=0**, the file name of each file containing a match (but no records) is included in the output. This specification creates a file (using the **/OUTPUT** qualifier) that can be inserted into a command file to manipulate the files containing matches.

If you omit the **/WINDOW** qualifier, only the line containing a match is displayed.

The **/WINDOW** qualifier displays a line of 30 asterisks to separate each window within a file.

**/WRAP****/NOWRAP (default)**

Use with the **/PAGE=SAVE** qualifier to limit the number of columns to the width of the screen and to wrap lines that extend beyond the width of the screen to the next line.

The **/NOWRAP** qualifier extends lines beyond the width of the screen and can be seen when you use the scrolling (left and right) features provided by the **/PAGE=SAVE** qualifier.

## Examples

1. `$ SEARCH CABLE.MEM,JOYNER.MEM "MANUAL TITLE"`

This command searches the files `CABLE.MEM` and `JOYNER.MEM` for occurrences of the character string `MANUAL TITLE`. Each line containing the string is displayed at the terminal. It is necessary to enclose the string in quotation marks because it contains a space character.

2. `$ SEARCH/OUTPUT=RESULTS.DAT/WINDOW=9 DISLIST.MEM NAME`

The **SEARCH** command searches the file `DISLIST.MEM` for occurrences of the character string `NAME` and sends the output to the file `RESULTS.DAT`. The four lines preceding and following each occurrence of `NAME` are included in the output.

3. `$ SEARCH/OUTPUT=ALLSUB.COM/WINDOW=5000 *.COM SUBMIT`

The **SEARCH** command searches all command files in the current directory for the string `SUBMIT`. If a match is found, **SEARCH** effectively copies the entire command file to the output file, because the window is so large.

4. `$ SEARCH/OUTPUT=COLUMBUS.OH/WINDOW=(3,0)/NOHEAD/MATCH=AND -  
_ $ *.DAT COLUMBUS,OH`

The **SEARCH** command searches all files of type `DAT` for lines containing both `COLUMBUS` and `OH`. When a match is found, the three previous lines (containing blank line, name, and street address) are copied to the new file. The new file `COLUMBUS.OH` is ready to use, because it does not contain headings and window separators.

5. `$ SEARCH/OUTPUT=SWAP.LIS/FORMAT=PASSALL/NUMBERS/EXACT -  
_ $ /WINDOW=10000 SWAP.PAS SWAP`

This **SEARCH** command produces a listing file with the line numbers at the left margin. The **/FORMAT=PASSALL** qualifier is specified so that form-feed characters in the source are passed through. The **/EXACT** qualifier is specified for efficiency (because it is known that the name `SWAP` in the program statement is always in uppercase). The **/WINDOW** qualifier is entered so that the entire file is copied to the output file `SWAP.LIS`.

6. `$ SEARCH/REMAINING CABLE.LOG FORTRAN`

The **SEARCH** command displays all the lines in the `CABLE.LOG` file that follow the first occurrence of the string `FORTRAN`.

7. `$ SEARCH OMAHA::DISK1:[EXP]SUB.DAT,DATA.LIS VAX`

The **SEARCH** command searches through the files `SUB.DAT` and `DATA.LIS` at remote node `OMAHA` for all occurrences of the string `VAX`. The list of all records containing the string `VAX` is displayed at the local terminal.

## SET

**SET** — Defines or changes the session, batch job, or system values or characteristics. See the Description section of each command for details.

## Format

**SET** *option*

## Description

The **SET** command options are described individually in this manual. *Table 2, "SET Command Options"* lists all the **SET** command options, including those generally reserved for use by system operators and managers.

**Table 2. SET Command Options**

| Option                             | Description                                                                                                                                                              |
|------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| ACCOUNTING                         | Controls the current accounting file.                                                                                                                                    |
| AUDIT                              | Provides the management interface to the security auditing system.                                                                                                       |
| BOOTBLOCK (Integrity servers only) | Initializes the boot block on the target device.                                                                                                                         |
| BROADCAST                          | Determines which messages will be broadcast to SYS\$OUTPUT.                                                                                                              |
| CACHE/RESET                        | Resets systemwide I/O caching statistics for the extended file cache (XFC).                                                                                              |
| CARD_READER                        | Defines the default ASCII translation mode for a card reader.                                                                                                            |
| CLUSTER/EXPECTED_VOTES             | Sets the total expected votes in the OpenVMS Cluster to a value that you specify or, if no value is specified, sets the total votes to a value determined by the system. |
| COMMAND                            | Adds commands that are defined in a command description file to your process command set or a command tables file.                                                       |
| CONTROL                            | Enables or disables interrupts caused by <b>Ctrl/T</b> or <b>Ctrl/Y</b> .                                                                                                |
| CPU                                | Changes the user capabilities associated with the specified CPUs.                                                                                                        |
| DAY                                | Overrides the default day type specified in the user authorization file (UAF).                                                                                           |
| DEFAULT                            | Establishes a device and directory as the current default for file specifications.                                                                                       |
| DEVICE                             | Defines device characteristics.                                                                                                                                          |
| DEVICE/SERVED                      | Lets you make a disk on a local node available to all the nodes on an OpenVMS Cluster.                                                                                   |
| DIRECTORY                          | Modifies the characteristics of one or more directories.                                                                                                                 |
| DISPLAY                            | Redirects the output of a DECwindows application.                                                                                                                        |
| ENTRY                              | Changes the current status or attributes of a job not currently executing in a queue.                                                                                    |
| FILE                               | Modifies the characteristics of one or more files.                                                                                                                       |
| HOST                               | Connects your terminal (through the current host processor) to another processor, called the remote processor.                                                           |
| HOST/DTE                           | Connects your system to a remote system by way of an outgoing terminal line.                                                                                             |
| HOST/DUP                           | Connects your terminal to a storage controller through the appropriate bus for that controller.                                                                          |

| Option             | Description                                                                                                                                                                     |
|--------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| HOST/HSC           | Connects your terminal to a remote HSC50 disk and tape controller through the computer interconnect (CI) bus.                                                                   |
| HOST/LAT           | Connects your terminal to a specified service available in the local area network (LAN), establishing one session for communication between your terminal and that service.     |
| HOST/RLOGIN        | Allows you to log in to a remote host over a TCP/IP connection and start an interactive terminal session by accessing the RLOGIN application.                                   |
| HOST/TELNET        | Connects you to a remote host over a TCP/IP connection by invoking the TELNET application.                                                                                      |
| HOST/TN3270        | Connects you to a remote IBM host over a TCP/IP connection, causing the local keyboard to emulate an IBM 3279-class terminal keyboard by invoking the TN3270 terminal emulator. |
| IMAGE              | Modifies or restores the image attributes of an OpenVMS ELF format image file.                                                                                                  |
| KEY                | Changes the current keypad state setting.                                                                                                                                       |
| LOGINS             | Allows or disallows users to log in to the system.                                                                                                                              |
| MAGTAPE            | Defines characteristics of a magnetic tape device.                                                                                                                              |
| MESSAGE            | Overrides or supplements system messages.                                                                                                                                       |
| NETWORK            | Registers the attributes of a network service.                                                                                                                                  |
| ON                 | Controls whether the command interpreter checks for an error condition following the execution of commands in a command procedure.                                              |
| OUTPUT_RATE        | Sets the rate at which output is written to a batch job log file.                                                                                                               |
| PASSWORD           | Lets users change their own passwords; lets system managers change the system password.                                                                                         |
| PREFERRED_PATH     | Specifies a particular host or preferred path to access a specific MSCP class disk or TMSCP class tape device.                                                                  |
| PREFIX             | Allows you to set a prefix control string for verified command lines.                                                                                                           |
| PRINTER            | Defines printer characteristics.                                                                                                                                                |
| PROCESS            | Defines execution characteristics of the current process.                                                                                                                       |
| PROMPT             | Defines the DCL prompt.                                                                                                                                                         |
| PROTECTION/DEFAULT | Establishes the default protection to be applied to all files subsequently created.                                                                                             |
| QUEUE              | Changes the current status or attributes of the specified queue.                                                                                                                |
| RESTART_VALUE      | Establishes a test value for restarting portions of batch jobs.                                                                                                                 |
| RIGHTS_LIST        | Lets users modify the process rights list; lets privileged users modify the system rights list.                                                                                 |
| RMS_DEFAULT        | Provides default multiblock and multibuffer count values to be used by RMS for file operations.                                                                                 |

| Option                                         | Description                                                                                                                                               |
|------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------|
| SECURITY                                       | Modifies the security profile of an object.                                                                                                               |
| SERVER ACME (Alpha/Integrity servers only)     | Controls starting, stopping, and restarting of the ACME server, which controls authentication policies for \$ACM system service clients.                  |
| SERVER REGISTRY (Alpha/Integrity servers only) | Controls starting, stopping, and restarting of the Registry server, which provides access to the Registry database for \$REGISTRY system service clients. |
| SERVER SECURITY                                | Controls starting, stopping, and restarting of the security server, which maintains information stored in the system intrusion and proxy databases.       |
| SHADOW (Alpha/Integrity servers only)          | Changes the characteristics of shadow sets created using Volume Shadowing for OpenVMS.                                                                    |
| SYMBOL                                         | Controls access to local and global symbols in command procedures.                                                                                        |
| TERMINAL                                       | Defines terminal characteristics.                                                                                                                         |
| TIME                                           | Resets the system clock to the specified value.                                                                                                           |
| VERIFY                                         | Controls whether the command interpreter displays lines in command procedures as it executes them.                                                        |
| VOLUME                                         | Modifies the characteristics of one or more Files-11 volumes.                                                                                             |
| WORKING_SET                                    | Changes the current working set limit or quota.                                                                                                           |

## SET ACCOUNTING

SET ACCOUNTING — Controls the current accounting file. **Requires OPER (operator) privilege.**

### Format

**SET ACCOUNTING**

### Parameters

None.

### Description

Each node on your system has its own current accounting file. You can control what resources this file tracks, and start up a new version of this file using the **SET ACCOUNTING** command.

There are two occasions when the resources used by a process are not tracked, despite the **SET ACCOUNTING** command:

- When you use the **RUN** (Process) command with the **/NOACCOUNTING** qualifier.
- When you use the \$CREPRC system service with the PRC\$M\_NOACNT status flag.

Similarly, there is one occasion when the resources used by an image are always tracked, despite the **SET ACCOUNTING** command:

- When you install an image using the **/ACCOUNTING** qualifier of the Install utility.

For more information on how to use the **SET ACCOUNTING** command, see the relevant section in the *VSI OpenVMS System Manager's Manual, Volume 2: Tuning, Monitoring, and Complex Systems* [[https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-2-tuning-monitoring-and-complex-systems/#\\_6017ACCOUNTING](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-2-tuning-monitoring-and-complex-systems/#_6017ACCOUNTING)].

## Qualifiers

**/DISABLE[=(keyword[,...])]**

Prevents the tracking of the resources specified by the keywords.

Table 3, "*SET ACCOUNTING Keywords for Resource Types*" lists the keywords you can use to specify the type of resource.

**Table 3. SET ACCOUNTING Keywords for Resource Types**

| Keyword       | Type of Resource                                                                           |
|---------------|--------------------------------------------------------------------------------------------|
| IMAGE         | Resources used by an image                                                                 |
| LOGIN_FAILURE | Resources used by an unsuccessful attempt to log in                                        |
| MESSAGE       | Unformatted record written to the accounting file by a call to the \$SNDJBC system service |
| PRINT         | Resources used by a print job                                                              |
| PROCESS       | Resources used by a process                                                                |

You do not need to stop the tracking of all processes and images. You can prevent resources being tracked for specific types of process and for images running in these types of process.

Table 4, "*SET ACCOUNTING Keywords for Process Types*" lists the keywords you can use to specify the type of process.

**Table 4. SET ACCOUNTING Keywords for Process Types**

| Keyword     | Type of Process                                                                           |
|-------------|-------------------------------------------------------------------------------------------|
| BATCH       | Batch process                                                                             |
| DETACHED    | Detached process                                                                          |
| INTERACTIVE | Interactive process                                                                       |
| NETWORK     | Network process                                                                           |
| SUBPROCESS  | Subprocess (the parent process can be a batch, detached, network, or interactive process) |

If the system is no longer tracking any resources, **/DISABLE** closes the current accounting file.

If you use the **/DISABLE** qualifier and omit the keywords, the current accounting file does not track any resources, and the system closes the file.

**/ENABLE[=(keyword[,...])]**

Enables the tracking of the specified resources, and opens the current accounting file if it is not already open. The **/ENABLE** qualifier uses the same keywords as the **/DISABLE** qualifier.

Use the keywords shown in Table 3, "*SET ACCOUNTING Keywords for Resource Types*" to specify the types of resource that you want the local node to track in its current accounting file.

If the resources used by processes or images are being tracked, you can use the keywords shown in *Table 4, "SET ACCOUNTING Keywords for Process Types"* to enable the tracking of these resources for specified types of process and for images running in those types of process.

If you use the **/ENABLE** qualifier and omit the keywords, the current accounting file tracks all resources.

## **/LOG**

Writes information to the current SYSS\$OUTPUT device as the command executes.

## **/NEW\_FILE**

Closes the current accounting file, and starts up a new version of it.

The name of the new file depends on whether the logical name ACCOUNTNG is defined in your system logical name table.

If this logical name is not defined, the **SET ACCOUNTING** command opens the file SYSS\$MANAGER:ACCOUNTNG.DAT.

If this logical name is defined, the command opens the file that this logical name points to. If you omit the directory, SYSS\$MANAGER is the default, and if you omit the file type, .DAT is the default.

The **/NEW\_FILE** qualifier writes a record to the end of the old file that contains a forward pointer to the new file, and a record to the beginning of the new file that contains a backward pointer to the old file. These records contain the names of the new and old files respectively.

## **Examples**

1. \$ SET ACCOUNTING /DISABLE /ENABLE=(PROCESS,BATCH,INTERACTIVE)  
\$ SET ACCOUNTING /ENABLE=IMAGE

This example tells the system to track the resources used only by batch and interactive processes, and by images running in batch and interactive processes. It illustrates the cumulative effect of **/ENABLE** and **/DISABLE** qualifiers, and of **SET ACCOUNTING** commands.

The **/DISABLE** qualifier prevents the tracking of all resources. The **/ENABLE** qualifier then tells the system to track the resources used by batch and interactive processes. The second **SET ACCOUNTING** command tells the system to track the resources used by images.

2. \$ SET ACCOUNTING /NEW\_FILE  
\$ RENAME SYSS\$MANAGER:ACCOUNTNG.DAT;-1 WEEK\_24\_RESOURCES.DAT

This example closes the current accounting file, opens a new version of it, and changes the name of the old file to WEEK\_24\_RESOURCES.DAT.

## **SET AUDIT**

**SET AUDIT** — Provides the management interface to the security auditing system. Requires the SECURITY privilege.

## **Format**

**SET AUDIT/qualifier**

## Parameters

None.

## Description

The **SET AUDIT** command and the **SHOW AUDIT** command provide the management interface to the security auditing system.

The **SET AUDIT** command enables or disables security auditing. In addition, you use the command to do the following:

- Select categories of events to audit
- Change the operational characteristics of the audit server
- Establish the location of the audit journal and the security archive file
- Control the monitoring of disk resources

Values set by the command are saved so it is unnecessary to set them each time the system starts up. Commands for event definition, resource monitoring, and starting a new log apply clusterwide, while other commands apply only to the local node.

Security auditing features require a certain amount of system overhead; therefore, you should be careful to select the features that will provide the most benefit in your work environment. Enable only the auditing of information that you know you will examine and analyze regularly. Any other collection of data is likely to be wasteful. For further information about auditing, see the relevant section in the *VSI OpenVMS Guide to System Security* [[https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#AUDITING\\_CHAPTER](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#AUDITING_CHAPTER)].

There are five categories of qualifiers, grouped by task, for the **SET AUDIT** command:

| Task                                                                                   | Qualifiers                                        | Requirements                                                                                                                                                                                                        |
|----------------------------------------------------------------------------------------|---------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Define auditing events                                                                 | /AUDIT<br>/ALARM<br>/CLASS<br>/ENABLE<br>/DISABLE | Specify whether you are defining alarms ( <b>/ALARM</b> ), audits ( <b>/AUDIT</b> ), or both. Also specify whether you are enabling ( <b>/ENABLE</b> ) or disabling ( <b>/DISABLE</b> ) the reporting of the event. |
| Define auditing log file                                                               | /DESTINATION<br>/JOURNAL<br>/VERIFY               | Requires both the <b>/DESTINATION</b> and <b>/JOURNAL</b> qualifiers.                                                                                                                                               |
| Define operational characteristics of the audit server and a listener mailbox (if any) | /INTERVAL<br>/LISTENER<br>/SERVER<br>/VERIFY      | None.                                                                                                                                                                                                               |
| Define secondary log file                                                              | /ARCHIVE<br>/DESTINATION<br>/VERIFY               | None.                                                                                                                                                                                                               |
| Define resource monitoring defaults                                                    | /BACKLOG<br>/EXCLUDE<br>/JOURNAL                  | With the <b>/RESOURCE</b> or <b>/THRESHOLD</b> qualifier, include the <b>/JOURNAL</b> qualifier.                                                                                                                    |

| Task | Qualifiers                         | Requirements |
|------|------------------------------------|--------------|
|      | /RESOURCE<br>/THRESHOLD<br>/VERIFY |              |

## Qualifiers

### /ALARM

Makes the command apply to alarms, which are messages displayed on an operator terminal. See the description of the DCL command [REPLY / ENABLE](#) for details on how to enable terminals to display security messages.

### /ARCHIVE=[keyword,...]

Specifies which classes of audit event messages are written to the security archive file. Specify one or more of the following keywords:

| Keyword           | Description                                                                                      |
|-------------------|--------------------------------------------------------------------------------------------------|
| NONE              | Disables archiving on the system.                                                                |
| [NO]ALL (default) | Enables or disables archiving of all system security events. By default, no events are archived. |
| SYSTEM_ALARM      | Enables archiving of all security alarm events.                                                  |
| SYSTEM_AUDIT      | Enables archiving of all security audit events.                                                  |

Archiving should be run on only one node in an OpenVMS Cluster with its own audit server database because multiple nodes will try to open the audit file exclusively.

### /AUDIT

Makes the command apply to audits, which are messages recorded in the system security audit log file.

### /BACKLOG=[keyword[,...]]

Specifies the thresholds for suspending a process that has exceeded the process message limit. The thresholds include the total number of messages in memory and the number belonging to the particular process. To prevent a process from being suspended, use the **/EXCLUDE** qualifier. Specify the following keywords:

| Keyword          | Description                                                                           |
|------------------|---------------------------------------------------------------------------------------|
| TOTAL=(n1,n2,n3) | Thresholds at which flow control is initiated and accelerated; see description below. |
| PROCESS=(p1,p2)  | Thresholds at which process submissions are controlled.                               |

| Total Messages | Default | Process Messages | Default | Action Taken                                                                                                                                               |
|----------------|---------|------------------|---------|------------------------------------------------------------------------------------------------------------------------------------------------------------|
| N1             | 100     | P1               | 5       | When there are 100 messages in memory, the audit server suspends any process that has submitted 5 or more messages until all messages are written to disk. |

| Total Messages | Default | Process Messages | Default | Action Taken                                                                                                                                               |
|----------------|---------|------------------|---------|------------------------------------------------------------------------------------------------------------------------------------------------------------|
| N2             | 200     | P2               | 2       | When there are 200 messages in memory, the audit server suspends any process that has submitted 2 or more messages until all messages are written to disk. |
| N3             | 300     |                  |         | Any process with messages in memory is suspended until all messages are written to disk.                                                                   |

**/CLASS=class**

Specifies the class of the object whose auditing attributes are to be modified. If **/CLASS** is not specified, the command assumes the class is **FILE**. Specify one of the following keywords with the **/CLASS** qualifier:

CAPABILITY  
COMMON\_EVENT\_CLUSTER  
DEVICE  
FILE  
GROUP\_GLOBAL\_SECTION  
LOGICAL\_NAME\_TABLE  
QUEUE  
RESOURCE\_DOMAIN  
SECURITY\_CLASS  
SYSTEM\_GLOBAL\_SECTION  
VOLUME

**/DESTINATION=filespec**

When changing the destination of event messages, specifies the new location of the system security audit log file. The device, if part of the file specification, must be a disk. The **/DESTINATION** qualifier requires the **/JOURNAL** qualifier in this case.

Once you have relocated the log file, execute the command **SET AUDIT /SERVER=NEW\_LOG** to let all the nodes in the cluster know of the new location. The previous audit log file is closed and all subsequent audit event messages generated throughout the cluster are sent to the new audit log file.

When used with **/ARCHIVE**, specifies the name of the archive log file. Events can be archived to a local or remote file on any file-structured disk device. For example, you can use an archive file to redirect event messages from a satellite to a larger node in the cluster.

**/DISABLE=(keyword[,...])**

Disables alarms or audits for the specified events. To disable all system events and file access events, specify the keyword **ALL**. You must specify at least one of the keywords. For a list of the keywords to use with the **/DISABLE** qualifier, see the [/ENABLE](#) qualifier description. You must also specify either the **/ALARM** or **/AUDIT** qualifier, or both, when you use the **/DISABLE** qualifier.

**Note**

In processing the **SET AUDIT** command, the system processes the **/DISABLE** qualifier last. If you specify both the **/ENABLE** and **/DISABLE** qualifiers for items in the same class on the same

command line, the **/DISABLE** qualifier disables any enabled items. VSI recommends that you use separate lines for commands containing the **/ENABLE** and **/DISABLE** qualifiers.

### **/ENABLE=(keyword[,...])**

Enables alarms or audits for the specified events. To enable all system events and file access events, specify the keyword **ALL**. You must specify at least one keyword. You must also specify either the **/ALARM** or **/AUDIT** qualifier, or both, when you use the **/ENABLE** qualifier.

The keywords that you can specify with either the **/ENABLE** or the **/DISABLE** qualifier are as follows:

| Keyword                                     | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |                   |             |     |                   |        |                                                                 |         |                            |        |                                                                         |         |                                                                  |         |                          |        |                                                                          |                |             |     |                     |           |                  |         |                                                              |
|---------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------|-------------|-----|-------------------|--------|-----------------------------------------------------------------|---------|----------------------------|--------|-------------------------------------------------------------------------|---------|------------------------------------------------------------------|---------|--------------------------|--------|--------------------------------------------------------------------------|----------------|-------------|-----|---------------------|-----------|------------------|---------|--------------------------------------------------------------|
| ACCESS=(condition[:access[,...]]<br>[,...]) | <p>Specifies access events for all objects in a class. (To audit a single object, use an auditing ACE and enable the access control list (ACL) category.)</p> <p>VSI recommends that when you enable auditing conditionally, you enable it for all possible forms of access because the system can check access rights at several points during an operation. (For example, a FAILURE might occur on a read or write access check.)</p> <p>See the relevant section in the <a href="https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#SYS_ACC_PWD">VSI OpenVMS Guide to System Security</a> [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#SYS_ACC_PWD] for information about the various types of access permitted on each class. (For example, the Access keyword, CREATE, is not defined for FILE objects.)</p> <table> <tr> <th>Condition Keyword</th><th>Description</th></tr> <tr> <td>ALL</td><td>All object access</td></tr> <tr> <td>BYPASS</td><td>Successful object access due to the use of the BYPASS privilege</td></tr> <tr> <td>FAILURE</td><td>Unsuccessful object access</td></tr> <tr> <td>GRPPRV</td><td>Successful object access due to the use of the group privilege (GRPPRV)</td></tr> <tr> <td>READALL</td><td>Successful object access due to the use of the READALL privilege</td></tr> <tr> <td>SUCCESS</td><td>Successful object access</td></tr> <tr> <td>SYSPRV</td><td>Successful object access due to the use of the system privilege (SYSPRV)</td></tr> <tr> <th>Access Keyword</th><th>Description</th></tr> <tr> <td>ALL</td><td>All types of access</td></tr> <tr> <td>ASSOCIATE</td><td>Associate access</td></tr> <tr> <td>CONTROL</td><td>Control access to examine or change security characteristics</td></tr> </table> | Condition Keyword | Description | ALL | All object access | BYPASS | Successful object access due to the use of the BYPASS privilege | FAILURE | Unsuccessful object access | GRPPRV | Successful object access due to the use of the group privilege (GRPPRV) | READALL | Successful object access due to the use of the READALL privilege | SUCCESS | Successful object access | SYSPRV | Successful object access due to the use of the system privilege (SYSPRV) | Access Keyword | Description | ALL | All types of access | ASSOCIATE | Associate access | CONTROL | Control access to examine or change security characteristics |
| Condition Keyword                           | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |                   |             |     |                   |        |                                                                 |         |                            |        |                                                                         |         |                                                                  |         |                          |        |                                                                          |                |             |     |                     |           |                  |         |                                                              |
| ALL                                         | All object access                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |                   |             |     |                   |        |                                                                 |         |                            |        |                                                                         |         |                                                                  |         |                          |        |                                                                          |                |             |     |                     |           |                  |         |                                                              |
| BYPASS                                      | Successful object access due to the use of the BYPASS privilege                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |                   |             |     |                   |        |                                                                 |         |                            |        |                                                                         |         |                                                                  |         |                          |        |                                                                          |                |             |     |                     |           |                  |         |                                                              |
| FAILURE                                     | Unsuccessful object access                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |                   |             |     |                   |        |                                                                 |         |                            |        |                                                                         |         |                                                                  |         |                          |        |                                                                          |                |             |     |                     |           |                  |         |                                                              |
| GRPPRV                                      | Successful object access due to the use of the group privilege (GRPPRV)                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |                   |             |     |                   |        |                                                                 |         |                            |        |                                                                         |         |                                                                  |         |                          |        |                                                                          |                |             |     |                     |           |                  |         |                                                              |
| READALL                                     | Successful object access due to the use of the READALL privilege                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |                   |             |     |                   |        |                                                                 |         |                            |        |                                                                         |         |                                                                  |         |                          |        |                                                                          |                |             |     |                     |           |                  |         |                                                              |
| SUCCESS                                     | Successful object access                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |                   |             |     |                   |        |                                                                 |         |                            |        |                                                                         |         |                                                                  |         |                          |        |                                                                          |                |             |     |                     |           |                  |         |                                                              |
| SYSPRV                                      | Successful object access due to the use of the system privilege (SYSPRV)                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |                   |             |     |                   |        |                                                                 |         |                            |        |                                                                         |         |                                                                  |         |                          |        |                                                                          |                |             |     |                     |           |                  |         |                                                              |
| Access Keyword                              | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |                   |             |     |                   |        |                                                                 |         |                            |        |                                                                         |         |                                                                  |         |                          |        |                                                                          |                |             |     |                     |           |                  |         |                                                              |
| ALL                                         | All types of access                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |                   |             |     |                   |        |                                                                 |         |                            |        |                                                                         |         |                                                                  |         |                          |        |                                                                          |                |             |     |                     |           |                  |         |                                                              |
| ASSOCIATE                                   | Associate access                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |                   |             |     |                   |        |                                                                 |         |                            |        |                                                                         |         |                                                                  |         |                          |        |                                                                          |                |             |     |                     |           |                  |         |                                                              |
| CONTROL                                     | Control access to examine or change security characteristics                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |                   |             |     |                   |        |                                                                 |         |                            |        |                                                                         |         |                                                                  |         |                          |        |                                                                          |                |             |     |                     |           |                  |         |                                                              |

| Keyword                         | Description                                                                                                                                                                                                                                                                                       |                                                                                                                                                                                                                                                                                                                                    |
|---------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                 | CREATE                                                                                                                                                                                                                                                                                            | Create access. To audit create events for files, use the CREATE keyword.                                                                                                                                                                                                                                                           |
|                                 | DELETE                                                                                                                                                                                                                                                                                            | Delete access                                                                                                                                                                                                                                                                                                                      |
|                                 | EXECUTE                                                                                                                                                                                                                                                                                           | Execute access                                                                                                                                                                                                                                                                                                                     |
|                                 | LOCK                                                                                                                                                                                                                                                                                              | Lock access                                                                                                                                                                                                                                                                                                                        |
|                                 | LOGICAL                                                                                                                                                                                                                                                                                           | Logical I/O access                                                                                                                                                                                                                                                                                                                 |
|                                 | MANAGE                                                                                                                                                                                                                                                                                            | Manage access                                                                                                                                                                                                                                                                                                                      |
|                                 | PHYSICAL                                                                                                                                                                                                                                                                                          | Physical I/O access                                                                                                                                                                                                                                                                                                                |
|                                 | READ                                                                                                                                                                                                                                                                                              | Read access                                                                                                                                                                                                                                                                                                                        |
|                                 | SUBMIT                                                                                                                                                                                                                                                                                            | Submit access                                                                                                                                                                                                                                                                                                                      |
|                                 | WRITE                                                                                                                                                                                                                                                                                             | Write access                                                                                                                                                                                                                                                                                                                       |
| ACL                             | Specifies an event requested by an audit or alarm ACE in the access control list (ACL) of an object. To audit all objects of a class, use the ACCESS keyword.                                                                                                                                     |                                                                                                                                                                                                                                                                                                                                    |
| ALL                             | Specifies all system events and file access events. It does not enable access events for object classes other than FILE.                                                                                                                                                                          |                                                                                                                                                                                                                                                                                                                                    |
| AUDIT= <i>keyword</i>           | Specifies events within the auditing subsystem. Only one keyword is currently defined.                                                                                                                                                                                                            |                                                                                                                                                                                                                                                                                                                                    |
|                                 | Keyword                                                                                                                                                                                                                                                                                           | Description                                                                                                                                                                                                                                                                                                                        |
|                                 | ILLFORMED                                                                                                                                                                                                                                                                                         | Specifies ill-formed events from internal calls (identified by NSA\$M_INTERNAL) to \$AUDIT_EVENT, \$CHECK_PRIVILEGE, \$CHKPRO, or \$CHECK_ACCESS system services. An ill-formed event is caused by an incomplete or syntactically incorrect argument being supplied to one of these system services by a piece of privileged code. |
| AUTHORIZATION                   | Specifies the modification of any portion of the system user authorization file (SYSUAF), network proxy authorization file (NETPROXY), or the rights list (RIGHTLIST) (including password changes made through the AUTHORIZE, SET PASSWORD, or LOGINOUT commands or the \$SETUAI system service). |                                                                                                                                                                                                                                                                                                                                    |
| BREAKIN=( <i>keyword</i> [...]) | Specifies the occurrence of one or more classes of break-in attempts, as specified by one or more of the following keywords:<br><br>ALL<br>DETACHED<br>DIALUP                                                                                                                                     |                                                                                                                                                                                                                                                                                                                                    |

| Keyword                                          | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
|--------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------|--------------------------------------|-------|-----------------------------|----------|--------------------------------|--------|----------------------------------|-------|---------------------------------|---------|-----------------------------------|--------|-------------------------------------------------------------------------------------------|--------|------------------------------------|------------|--------------------------|
|                                                  | LOCAL<br>NETWORK<br>REMOTE                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| CONNECTION                                       | Specifies a logical link connection or termination through DECnet-Plus, DECnet Phase IV, DECwindows, \$IPC, or SYSMAN.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| CREATE                                           | Specifies the creation of an object. Requires the <b>/CLASS</b> qualifier if it is not a file.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| DEACCESS                                         | Specifies deaccess from an object. Requires the <b>/CLASS</b> qualifier if it is not a file.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| DELETE                                           | Specifies the deletion of an object. Requires the <b>/CLASS=DEVICE</b> qualifier.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| IDENTIFIER                                       | Specifies that the use of identifiers as privileges should be audited. For further information, see the <a href="https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/">VSI OpenVMS Guide to System Security</a> [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/].                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| INSTALL                                          | Specifies modifications made to the known file list through the INSTALL utility.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| LOGFAILURE= ( <i>keyword</i> [,...])             | Specifies the occurrence of one or more classes of login failures, as specified by the following keywords: <table> <tr> <td>ALL</td><td>All possible types of login failures</td></tr> <tr> <td>BATCH</td><td>Batch process login failure</td></tr> <tr> <td>DETACHED</td><td>Detached process login failure</td></tr> <tr> <td>DIALUP</td><td>Dialup interactive login failure</td></tr> <tr> <td>LOCAL</td><td>Local interactive login failure</td></tr> <tr> <td>NETWORK</td><td>Network server task login failure</td></tr> <tr> <td>REMOTE</td><td>Interactive login failure from another network node, for example, with a SET HOST command</td></tr> <tr> <td>SERVER</td><td>Server or TCB-based login failure.</td></tr> <tr> <td>SUBPROCESS</td><td>Subprocess login failure</td></tr> </table> | ALL                                              | All possible types of login failures | BATCH | Batch process login failure | DETACHED | Detached process login failure | DIALUP | Dialup interactive login failure | LOCAL | Local interactive login failure | NETWORK | Network server task login failure | REMOTE | Interactive login failure from another network node, for example, with a SET HOST command | SERVER | Server or TCB-based login failure. | SUBPROCESS | Subprocess login failure |
| ALL                                              | All possible types of login failures                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| BATCH                                            | Batch process login failure                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| DETACHED                                         | Detached process login failure                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| DIALUP                                           | Dialup interactive login failure                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| LOCAL                                            | Local interactive login failure                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| NETWORK                                          | Network server task login failure                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| REMOTE                                           | Interactive login failure from another network node, for example, with a SET HOST command                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| SERVER                                           | Server or TCB-based login failure.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| SUBPROCESS                                       | Subprocess login failure                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| LOGIN= ( <i>keyword</i> [,...])                  | Specifies the occurrence of one or more classes of login attempts, as specified by the following keywords. See the <a href="#">LOGFAILURE</a> keyword for further description. <table> <tr> <td>ALL<br/>DETACHED<br/>LOCAL<br/>REMOTE<br/>SUBPROCESS</td><td>BATCH<br/>DIALUP<br/>NETWORK<br/>SERVER</td></tr> </table>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  | ALL<br>DETACHED<br>LOCAL<br>REMOTE<br>SUBPROCESS | BATCH<br>DIALUP<br>NETWORK<br>SERVER |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| ALL<br>DETACHED<br>LOCAL<br>REMOTE<br>SUBPROCESS | BATCH<br>DIALUP<br>NETWORK<br>SERVER                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |
| LOGOUT= ( <i>keyword</i> [,...])                 | Specifies the occurrence of one or more classes of logouts, as specified by the following keywords. See the <a href="#">LOGFAILURE</a> keyword for further description.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |                                                  |                                      |       |                             |          |                                |        |                                  |       |                                 |         |                                   |        |                                                                                           |        |                                    |            |                          |

| Keyword                             | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
|-------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------|-----|---------------------------------------------------|--------|---------------------|--------|---------------------|--------|------------------------------|--------|----------------------------|------|--------------------------|--------|------------------------------|--------|----------------------------|---------|-----------------------------|---------|-----------------------------|--------|----------------------------|--------|----------------------------|--------|----------------------------|
|                                     | ALL<br>DETACHED<br>LOCAL<br>REMOTE<br>SUBPROCESS                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        | BATCH<br>DIALUP<br>NETWORK<br>SERVER |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| MOUNT                               | Specifies a mount or dismount operation.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| NCP                                 | Specifies access to the network configuration database, using the network control program (NCP).                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| PRIVILEGE= ( <i>keyword</i> [,...]) | <p>Specifies successful or unsuccessful use of privilege, as specified by the following keywords:</p> <p>FAILURE [<i>:privilege</i>(,...)] --- Unsuccessful use of privilege<br/>SUCCESS [<i>:privilege</i>(,...)] --- Successful use of privilege</p> <p>For a listing of privileges, see the online help for the DCL command <b>SET PROCESS/PRIVILEGES</b>.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| PROCESS= ( <i>keyword</i> [,...])   | <p>Specifies the use of one or more of the process control system services, as specified by the following keywords:</p> <table><tr><td>ALL</td><td>Use of any of the process control system services</td></tr><tr><td>CREPRC</td><td>All use of \$CREPRC</td></tr><tr><td>DELPRC</td><td>All use of \$DELPRC</td></tr><tr><td>SCHDWK</td><td>Privileged use of \$\$SCHDWK</td></tr><tr><td>CANWAK</td><td>Privileged use of \$CANWAK</td></tr><tr><td>WAKE</td><td>Privileged use of \$WAKE</td></tr><tr><td>SUSPND</td><td>Privileged use of \$\$SUSPND</td></tr><tr><td>RESUME</td><td>Privileged use of \$RESUME</td></tr><tr><td>GRANTID</td><td>Privileged use of \$GRANTID</td></tr><tr><td>REVOKID</td><td>Privileged use of \$REVOKID</td></tr><tr><td>GETJPI</td><td>Privileged use of \$GETJPI</td></tr><tr><td>FORCEX</td><td>Privileged use of \$FORCEX</td></tr><tr><td>SETPRI</td><td>Privileged use of \$SETPRI</td></tr></table> <p>Privileged use of a process control system service means the caller used GROUP or WORLD privilege to affect the target process.</p> |                                      | ALL | Use of any of the process control system services | CREPRC | All use of \$CREPRC | DELPRC | All use of \$DELPRC | SCHDWK | Privileged use of \$\$SCHDWK | CANWAK | Privileged use of \$CANWAK | WAKE | Privileged use of \$WAKE | SUSPND | Privileged use of \$\$SUSPND | RESUME | Privileged use of \$RESUME | GRANTID | Privileged use of \$GRANTID | REVOKID | Privileged use of \$REVOKID | GETJPI | Privileged use of \$GETJPI | FORCEX | Privileged use of \$FORCEX | SETPRI | Privileged use of \$SETPRI |
| ALL                                 | Use of any of the process control system services                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| CREPRC                              | All use of \$CREPRC                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| DELPRC                              | All use of \$DELPRC                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| SCHDWK                              | Privileged use of \$\$SCHDWK                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| CANWAK                              | Privileged use of \$CANWAK                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| WAKE                                | Privileged use of \$WAKE                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| SUSPND                              | Privileged use of \$\$SUSPND                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| RESUME                              | Privileged use of \$RESUME                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| GRANTID                             | Privileged use of \$GRANTID                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| REVOKID                             | Privileged use of \$REVOKID                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| GETJPI                              | Privileged use of \$GETJPI                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| FORCEX                              | Privileged use of \$FORCEX                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| SETPRI                              | Privileged use of \$SETPRI                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| SYSGEN                              | Specifies the modification of a system parameter with the OpenVMS System Generation utility.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |
| TIME                                | Specifies the modification of system time.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |                                      |     |                                                   |        |                     |        |                     |        |                              |        |                            |      |                          |        |                              |        |                            |         |                             |         |                             |        |                            |        |                            |        |                            |

**/EXCLUDE=***process-id*

**/NOEXCLUDE=***process-id*

Adds a process identification (PID) to the audit server's process exclusion list. The process exclusion list contains those processes that will not be suspended by the audit server if a resource exhaustion

reaches the action threshold. By default, real-time processes and all of the following processes are included in the process exclusion list and are never suspended:

CACHE\_SERVER  
 CLUSTER\_SERVER  
 CONFIGURE  
 DFS\$COM\_ACP  
 DNS\$ADVER  
 IPCACP  
 JOB\_CONTROL  
 NETACP  
 NET\$ACP  
 OPCOM  
 REMACP  
 SHADOW\_SERVER  
 SMISERVER  
 SWAPPER  
 TP\_SERVER  
 VWS\$DISPLAYMGR  
 VWS\$EMULATORS

Use the **SET AUDIT/NOEXCLUDE** command to remove a process from the process exclusion list; however, processes listed above cannot be removed from the exclusion list. Also note that PIDs are not automatically removed from the process exclusion list when processes log out of the system.

#### **/INTERVAL=(keyword[,...])**

Specifies the delta times to be used for regular audit server operations. For information about specifying delta times, see the relevant section in the *VSI OpenVMS User's Manual* [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\\_AND\\_TIME\\_SECT](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT)].

The following table describes keywords for the **/INTERVAL** qualifier:

| Keyword                       | Description                                                                                                                                                                                                                                                                                     |
|-------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| ARCHIVE_FLUSH= <i>time</i>    | Specifies the interval at which data collected by the audit server is written to the archive file. The default is 1 minute.                                                                                                                                                                     |
| JOURNAL_FLUSH= <i>time</i>    | Specifies the interval at which data collected by the audit server is written to the audit log file. The default is 5 minutes.                                                                                                                                                                  |
| RESOURCE_MONITOR= <i>time</i> | Specifies the interval at which the audit server retries log file allocation or access. This interval applies whenever free space in the log file is below either the warning or action thresholds, or when the volume holding the log file is inaccessible. The default interval is 5 minutes. |
| RESUME_SCAN= <i>time</i>      | Specifies the interval at which the audit server reviews an existing resource exhaustion condition. The default is 15 minutes.                                                                                                                                                                  |

#### **/JOURNAL[=*journal-name*]**

Specifies the name of the audit journal; the name defaults to SECURITY. (Currently, there is only one journal.)

The **/JOURNAL** qualifier is required when redefining the audit log file or when specifying resource monitoring characteristics with the **/RESOURCE** or the **/THRESHOLD** qualifier.

**/LISTENER=*device***  
**/NOLISTENER**

Specifies the name of a mailbox device to which the audit server sends a binary copy of all security audit event messages. Users can create such a mailbox to process system security events as they occur. For a description of the message formats written to the listener mailbox, see the Audit Analysis Utility documentation in the [VSI OpenVMS System Management Utilities Reference Manual, Volume 1: A-L](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-i-a-l/#AUDITING_PART) [https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-i-a-l/#AUDITING\_PART].

Use the **SET AUDIT/NOLISTENER** command to disable a listener device.

**/RESOURCE=*keyword*[,...]**

Enables or disables the monitoring of disk volumes to ensure adequate space for audit journal entries; it also specifies the monitoring method to use. The **/JOURNAL** qualifier is required. For more information about resource monitoring, see the relevant section in the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#d0e17705) [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#d0e17705].

| Keyword | Description                                                                  |
|---------|------------------------------------------------------------------------------|
| DISABLE | Disables monitoring on the disk volume containing the audit journal.         |
| ENABLE  | Enables resource monitoring on the disk volume containing the audit journal. |

**/SERVER=*keyword*[,...]**

Modifies audit server characteristics. The following table describes keywords for the **/SERVER** qualifier:

| Keyword                     | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
|-----------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EXIT                        | Initiates an audit server shutdown. This is the only method for removing the audit server process from the system; the audit server cannot be deleted or suspended.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| FINAL_ACTION= <i>action</i> | Specifies the action the audit server should take when it runs out of memory and cannot buffer messages. (For more information, see the discussion of message flow control in the <a href="https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#d0e17455">VSI OpenVMS Guide to System Security</a> [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#d0e17455].) Specify one of the following actions:<br><br>CRASH – Crash the system if the audit server runs out of memory.<br>IGNORE_NEW – Ignore new event messages until memory is available. New event messages are lost but event messages in memory are saved.<br>PURGE_OLD (default) – Remove old event messages until memory is available for the most current messages. |
| FLUSH                       | Copies all buffered audit and archive records to the security audit log file and security archive file, respectively.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| INITIATE                    | Enables auditing during system startup. Ordinarily, auditing is started from VMS\$LPBEGIN in STARTUP.COM but, if a site redefines the logical name                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |

| Keyword | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|---------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|         | SYSSAUDIT_SERVER_INHIBIT, the OpenVMS system waits for a <b>SET AUDIT/SERVER=INITIATE</b> command before enabling auditing.                                                                                                                                                                                                                                                                                                                                                                                           |
| NEW_LOG | <p>Creates a new clusterwide audit log file. Typically, this is used daily to generate a new version of the audit log file.</p> <p>The following sequence of commands can be used to reset the space monitoring thresholds and then to recreate the auditing log, thereby creating a smaller log file:</p> <pre>\$ SET AUDIT /JOURNAL=SECURITY /THRESHOLD=   WARN=200 \$ SET AUDIT /SERVER=NEW_LOG</pre> <p>By default, the size of the new auditing log file is based on the size of the previous auditing logs.</p> |
| RESUME  | Requests the audit server process to resume normal activity on the system, if adequate disk space is available. Normally, once the resource monitoring action threshold has been reached, the audit server process suspends most system activity and waits 15 minutes before attempting to resume normal system activity.                                                                                                                                                                                             |
| START   | <p>Starts the audit server process on the system. In order to fully enable the auditing subsystem, the <b>SET AUDIT/SERVER=INITIATE</b> command must be used after the <b>SET AUDIT/SERVER=START</b> command has completed.</p> <p>Use the following command procedure to start the audit server:</p> <pre>SYSS\$SYSTEM:STARTUP AUDIT_SERVER</pre>                                                                                                                                                                    |

### **/THRESHOLD=type=value**

Specifies threshold values used in monitoring available space in the audit log file. The auditing system issues advisory messages to central and security operators whenever free space in the audit log file falls below the WARNING threshold. The auditing system suspends processes that generate audit events when free disk space is below the action threshold. (See the [/RESOURCE](#) qualifier). The **/JOURNAL** qualifier is required.

The following table lists the types of thresholds:

| Keyword       | Description                                                                                                                                                                                                                                                                                                                                                 |
|---------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| WARNING=value | Specifies the threshold at which the audit server notifies all security operator terminals that resources are getting low.                                                                                                                                                                                                                                  |
| ACTION=value  | Specifies the threshold at which the audit server starts suspending processes that are generating audit records. (Certain processes are immune to this: see the <a href="https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/">VSI OpenVMS Guide to System Security</a> [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/]. |

The following table lists the default warning and action values for each monitoring mode:

| Mode       | Warning   | Action    |
|------------|-----------|-----------|
| Blocks     | 100       | 25        |
| Delta time | 2 0:00:00 | 0 0:30:00 |

**/VERIFY**

Do not return the dollar sign (\$) prompt until the audit server completes the command. Associated qualifiers determine which of the following actions occur:

- Redefinition of auditing events
- Redefinition of the audit log file or the archive file
- Modification of the audit server's operational characteristics
- Modification of resource monitoring attributes

If you do not want to wait for the command to complete, specify **/NOVERIFY**.

**Examples**

```
1. $ SET AUDIT/AUDIT/ENABLE= -
_$ (CREATE,ACCESS=(SYSPRV,BYPASS),DEACCESS)/CLASS=FILE
$ SHOW AUDIT/AUDIT
System security audits currently enabled for:
.
.
.

FILE access:
  Failure:      read,write,execute,delete,control
  SYSPRV:       read,write,execute,delete,control
  BYPASS:       read,write,execute,delete,control
  Other:        create,deaccess
```

The **SET AUDIT** command in this example enables auditing of file creation and file deaccess; it also enables auditing for any file access done by using either SYSPRV or BYPASS privilege.

```
2. $ SET AUDIT/JOURNAL=SECURITY/DESTINATION=AUDIT$: [AUDIT] TURIN
$ SET AUDIT/SERVER=NEW
$ SHOW AUDIT/JOURNAL
List of audit journals:
  Journal name:      SECURITY
  Journal owner:     (system audit journal)
  Destination:      AUDIT$: [AUDIT] TURIN.AUDIT$JOURNAL
```

The **SET AUDIT** command in this example demonstrates how to switch to a new journal.

```
3. $ SET AUDIT/SERVER=FINAL=CRASH
$ SHOW AUDIT/SERVER
Security auditing server characteristics:
  Database version:   4.4
  Backlog (total):    100, 200, 300
  Backlog (process):  5, 2
  Server processing intervals:
```

```
Archive flush:          0 00:01:00.00
Journal flush:          0 00:05:00.00
Resource scan:          0 00:05:00.00
Final resource action:  crash system
```

The **SET AUDIT** command in this example changes the audit server's final action setting so the system crashes when the audit server runs out of memory.

4. 

```
$ SET AUDIT/ARCHIVE/DESTINATION=SYS$SPECIFIC:[SYSMGR]TURIN-ARCHIVE
$ SHOW AUDIT/ARCHIVE
Security archiving information:
  Archiving events:      system audits
  Archive destination:  SYS$SPECIFIC:[SYSMGR]TURIN-ARCHIVE.AUDIT$JOURNAL
```

The **SET AUDIT** command in this example enables a node-specific archive file.

5. 

```
$ SET AUDIT/JOURNAL/RESOURCE=ENABLE
$ SHOW AUDIT/JOURNAL
List of audit journals:
  Journal name:          SECURITY
  Journal owner:          (system audit journal)
  Destination:           SYS$COMMON:[SYSMGR]SECURITY.AUDIT$JOURNAL
  Monitoring:            enabled
    Warning thresholds,  Block count:    100    Duration:  2 00:00:00.0
    Action thresholds,   Block count:     25    Duration:  0 00:30:00.0
```

The **SET AUDIT** command in this example enables disk monitoring and switches the mode so the disk space is monitored in terms of time rather than free blocks.

## SET BOOTBLOCK (Integrity servers Only)

**SET BOOTBLOCK** — Initializes the boot block on the target device.

### Format

**SET BOOTBLOCK**[*boot-file*]

### Parameters

*boot-file*

Specifies the file name of the boot file for the target disk.

Architecture-specific defaults are applied for the boot file. For Integrity servers, the default is `SYS$SYSROOT:[SYS$LDR]SYS$EFL.SYS (SYS$EFI)`.

The boot file must be contiguous. If the target boot file is not contiguous, use the DCL command **COPY/CONTIGUOUS** or another functionally similar mechanism to recreate a contiguous version of the boot file.

The boot file must also be marked **NOMOVE** (using the DCL command **SET FILE/NOMOVE**) to avoid a bootstrap failure that could result from the normal and expected operations of disk defragmentation tools.

## Description

The **SET BOOTBLOCK** command writes a boot block onto the specified disk.

As an alternative to using the **SET BOOTBLOCK** command, you can use **RUN** to invoke the SETBOOT utility, which then prompts you for all required input.

## Qualifier

**/BLOCK\_SIZE=512 (default)**

**/BLOCK\_SIZE=2048**

Specifies the target block size for the bootstrap device, in bytes.

The 512-byte block size applies for most disk devices. The 2048-byte block size typically is used only when writing the boot block to specific OpenVMS Integrity servers CD and DVD devices.

**/Integrity servers**

Specifies OpenVMS Integrity servers as the target architecture for the boot block. The default boot file for OpenVMS Integrity servers is SYS\$SYSROOT:[SYS\$LDR]SYS\$EFL.SYS.

**/PRESERVE=keyword**

**/PRESERVE=SIGNATURE**

**/PRESERVE=SIGNATURE** maintains the existing GUID disk signature value. The default is to generate a new signature for the target volume.

SIGNATURE is the only *keyword* currently supported.

## SET BROADCAST

SET BROADCAST — Enables you to selectively screen out various kinds of messages from being broadcast to your terminal.

## Format

**=(class-name[,...])**

## Parameter

**class-name[,...]**

Specifies the class of message that you want to enable or disable for broadcast to your terminal. If you specify only one class, you can omit the parentheses. The class names are as follows:

| Class Name  | Description                                                           |
|-------------|-----------------------------------------------------------------------|
| ALL         | Enables all message classes.                                          |
| [NO]DCL     | Specifies <b>Ctrl/T</b> and <b>SPAWN/NOTIFY</b> messages.             |
| [NO]GENERAL | Specifies all normal <b>REPLY</b> messages or messages from \$BRDCST. |
| [NO]MAIL    | Specifies notification of mail.                                       |
| NONE        | Disables all message classes.                                         |

| Class Name              | Description                                                                                                                                                                                                                                                                                                                                                                                                                             |
|-------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| [NO]OPCOM               | Specifies messages issued by the operator communication process (OPCOM).                                                                                                                                                                                                                                                                                                                                                                |
| [NO]PHONE               | Specifies messages from the Phone utility.                                                                                                                                                                                                                                                                                                                                                                                              |
| [NO]QUEUE               | Specifies messages referring to print or batch jobs issued by the queue manager.                                                                                                                                                                                                                                                                                                                                                        |
| [NO]SHUTDOWN            | Specifies messages issued from the <b>REPLY/SHUTDOWN</b> command.                                                                                                                                                                                                                                                                                                                                                                       |
| [NO]URGENT              | Specifies messages issued from the <b>REPLY/URGENT</b> command.                                                                                                                                                                                                                                                                                                                                                                         |
| [NO]USER1 to [NO]USER16 | Specifies messages from specific user groups. (For information on setting up user-written broadcast messages, see the description of the \$BRKTHRU system service in the <a href="https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-a-getuai/#JUN_72">VSI OpenVMS System Services Reference Manual: A-GETUAI</a> [https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-a-getuai/#JUN_72].) |

## Description

The **SET BROADCAST** command enables you to receive certain kinds of messages at your terminal, but not others. By default, you receive all messages at your terminal (**SET BROADCAST=ALL**). **SET BROADCAST=NONE** screens out all messages.

After you have used the **SET BROADCAST** command to screen out some classes of messages (for example, **SET BROADCAST=NOPHONE**), you can use the command to restore that class (**SET BROADCAST=PHONE**).

Use the **SHOW BROADCAST** command to see which message classes are currently being screened out.

## Note

SYS\$COMMAND must be a terminal.

## Examples

1. \$ SET BROADCAST=(NOMAIL, NOPHONE)

·  
·  
·

\$ SET BROADCAST=MAIL

In this example, the first **SET BROADCAST** command screens out all mail and phone messages. Later the second **SET BROADCAST** command restores mail messages. Phone messages are still screened.

2. \$ SET BROADCAST=NONE

·  
·  
·

\$ SET BROADCAST=(SHUTDOWN, URGENT, DCL, OPCOM)

In this example, the first **SET BROADCAST** command screens out all messages. Later the second **SET BROADCAST** command restores SHUTDOWN, URGENT, DCL, and OPCOM messages. General, phone, mail, queue, and user messages are still screened.

# SET CACHE/RESET

**SET CACHE/RESET** — Resets systemwide I/O caching statistics for the extended file cache (XFC). **OPER** privilege is required to execute this command.

## Format

**SET CACHE/RESET**

## Parameters

None.

## Description

The **SET CACHE/RESET** command resets several of the systemwide I/O caching statistics that are displayed by the **SHOW MEMORY/CACHE** and **SDA SHOW MEMORY** commands. Statistics that are reset include: I/O counts, hit rates, hit counts, reads bypassing cache, and the read/write ratio.

A timestamp displays the time the cache was last reset, thus subsequent **SHOW MEMORY/CACHE** commands display statistics from this time.

## Example

```
$ SHOW MEMORY/CACHE
      System Memory Resources on 22-AUG-2017 11:22:22.50

Extended File Cache (Time of last reset: 16-AUG-2017 11:16:24.96)
  Allocated (Mbytes)      151.39   Maximum size (Mbytes)    1024.00
  Free (Mbytes)           0.21    Minimum size (Mbytes)    0.23
  In use (Mbytes)         151.18   Write hit rate           0%
  Read hit rate           97%     Write I/O count          5321
  Read I/O count          208052   Write hit count          0
  Read hit count          203761   Writes bypassing cache   0
  Reads bypassing cache   1787    Vols in Full XFC mode    0
  Files cached open       316     Vols in VIOC Compatible mode 1
  Files cached closed     300     Vols in No Caching mode  0
  Read/Write ratio        97%     Vols in Perm. No Caching mode 0
```

This example shows the cache statistics prior to issuing the **SET CACHE/RESET** command.

```
$ SET CACHE/RESET
```

This command resets the cache statistics and updates the timestamp.

```
$ SHOW MEMORY/CACHE
      System Memory Resources on 22-AUG-2017 11:27:41.11

Extended File Cache (Time of last reset: 22-AUG-2017 11:27:37.76)
  Allocated (Mbytes)      151.39   Maximum size (Mbytes)    1024.00
  Free (Mbytes)           0.21    Minimum size (Mbytes)    0.23
  In use (Mbytes)         151.18   Write hit rate           0%
  Read hit rate           100%    Write I/O count          0
  Read I/O count          9       Write hit count          0
  Read hit count          9       Writes bypassing cache   0
  Reads bypassing cache   0       Vols in Full XFC mode    0
```

|                     |      |                               |   |
|---------------------|------|-------------------------------|---|
| Files cached open   | 316  | Vols in VIOC Compatible mode  | 1 |
| Files cached closed | 300  | Vols in No Caching mode       | 0 |
| Read/Write ratio    | 100% | Vols in Perm. No Caching mode | 0 |

This example shows the reset cache statistics and the modified timestamp.

## SET CARD\_READER

**SET CARD\_READER** — Defines the default translation mode for cards read from a card reader. All subsequent input read from the specified card reader is converted using the specified mode.

### Format

**SET CARD\_READER***device-name*[:]

### Parameter

*device-name*[:]

Specifies the name of the card reader for which the translation mode is to be set. The device must not be currently allocated to any other user.

### Description

When the system is bootstrapped, the translation mode for cards read into all card readers is set at 029. If you do not specify either of the command qualifiers, the **SET CARD\_READER** command has no effect; that is, the current translation mode for the device remains the same.

### Qualifiers

**/026**

Sets the card reader for cards punched on an 026 punch.

**/029**

Sets the card reader for cards punched on an 029 punch.

**/LOG**

**/NOLOG (default)**

Controls whether log information is displayed at the terminal to confirm that the card reader is set.

### Example

```
$ ALLOCATE CR:
  _CRA0: ALLOCATED
$ SET CARD_READER CRA0:/029
$ COPY  CRA0: [PEARLMAN.DATAFILES]CARDS.DAT
```

The **ALLOCATE** command requests the allocation of a card reader by specifying the generic device name. When the **ALLOCATE** command displays the name of the device, the **SET CARD\_READER** command sets the translation mode at 029. Then the **COPY** command copies all the cards read by the card reader CRA0 into the file CARDS.DAT in the directory [PEARLMAN.DATAFILES].

# SET CLUSTER/EXPECTED\_VOTES

**SET CLUSTER/EXPECTED\_VOTES** — Sets the total expected votes in the OpenVMS Cluster to a value that you specify or, if no value is specified, sets the total votes to a value determined by the system.  
**Requires OPER (operator) privilege.**

## Format

[=*value*]

## Parameter

*value*

Specifies the total number of expected votes in the cluster.

## Description

The **SET CLUSTER/EXPECTED\_VOTES** command enables you to adjust the total number of expected votes in the cluster. Set this value equal to the number of votes contributed by each node plus the number of votes contributed by the cluster quorum disk. The system will automatically calculate the value of the cluster quorum from the total number of expected votes in the cluster.

You can specify the expected total votes value as part of the **SET CLUSTER/EXPECTED\_VOTES** command string. If you enter the command without specifying a value for expected votes, the system calculates the value for you, using the following formula:

$$\text{EXPECTED\_VOTES} = (\text{NODE1\_VOTES} + \text{NODE2\_VOTES} + \dots) + \text{QUORUM\_DISK\_VOTES}$$

**NODE *n*\_VOTES** is the value of the system parameter **VOTES** for each node in the cluster and **QUORUM\_DISK\_VOTES** is the value of the system parameter **QDSKVOTES**.

When you enter the **SET CLUSTER/EXPECTED\_VOTES** command without specifying a value, the system assumes that all nodes that are expected to be in the cluster are currently members.

In general, you use the **SET CLUSTER/EXPECTED\_VOTES** command only when a node is leaving the cluster for an extended period of time. Under normal circumstances, quorum is not reduced when a node leaves the cluster, because it is assumed that the node may be rebooted and rejoin the cluster. If a node is removed and is unable to rejoin the cluster within a reasonable period of time (for example, if a node crashes due to a hardware problem and cannot rejoin the cluster for several days), the quorum for the cluster can safely be reduced by lowering the total expected votes until that node rejoins.

The purpose of a cluster quorum is to eliminate any possibility of the cluster partitioning into separate clusters and simultaneously accessing the same resources (such as disks). If the sum of the votes for all members of the cluster is smaller than the cluster quorum, all nodes will block activity until new nodes join to increase the vote total. Lowering the quorum value (by reducing the value of the total expected votes) when one or more nodes leave the cluster for long periods of time reduces this possibility.

Note that no matter what value you specify for the **SET CLUSTER/EXPECTED\_VOTES** command, you cannot increase quorum to a value that is greater than the number of the votes present, nor can you reduce quorum to a value that is half or fewer of the votes present.

When you enter the **SET CLUSTER/EXPECTED\_VOTES** command, either with or without an expected votes value specified, the system responds with a message indicating the new value that was actually set. Note that you need to enter this command only on one node in the cluster, because the new

value for total expected votes is propagated through the cluster. This new expected votes value should then be stored in the system parameter `EXPECTED_VOTES` on each node, so that it remains in effect after the nodes reboot.

When a node that was previously a member of the cluster is ready to rejoin, you should increase the system parameter `EXPECTED_VOTES` to its original value before bringing the node back to the cluster. Note that you do not need to use the `SET CLUSTER/EXPECTED_VOTES` command to increase the number of expected votes, because the expected votes value will be increased automatically when the node rejoins the cluster.

## Examples

1. `$ SET CLUSTER/EXPECTED_VOTES`

The `SET CLUSTER` command in this example instructs the system to calculate the total expected votes value for you, because no value is specified as part of the command string. The system uses the `NODEN_VOTES + QUORUM_DISK_VOTES` formula.

2. `$ SET CLUSTER/EXPECTED_VOTES=9`

The `SET CLUSTER` command in this example sets the total expected votes to 9, which is the value specified in the command string.

## SET COMMAND

**SET COMMAND** — Invokes the Command Definition Utility, which adds commands to your process command table or to a specified command table file. For a complete description of the Command Definition Utility, see the relevant section in the *VSI OpenVMS Command Definition, Librarian, and Message Utilities Manual* [[https://docs.vmssoftware.com/vsi-openvms-command-definition-librarian-and-message-utilities/#CD\\_CHAP](https://docs.vmssoftware.com/vsi-openvms-command-definition-librarian-and-message-utilities/#CD_CHAP)].

## Format

`SET COMMAND[filespec[,...]]`

## Parameter

`[filespec[,...]]`

Specifies the name of one or more command definition files. If you specify more than one name, separate them with commas. The default file type is `.CLD`. See the relevant section in the *VSI OpenVMS Command Definition, Librarian, and Message Utilities Manual* [[https://docs.vmssoftware.com/vsi-openvms-command-definition-librarian-and-message-utilities/#CDU\\_WRITING\\_DEFINITION\\_FILE](https://docs.vmssoftware.com/vsi-openvms-command-definition-librarian-and-message-utilities/#CDU_WRITING_DEFINITION_FILE)] for more information about writing a command definition file.

The asterisk (\*) and the percent sign (%) wildcard characters are allowed in the file specification.

## Qualifiers

`/DELETE=(verb[,...])`

Specifies **/DELETE** mode to delete verbs from the command table you are modifying.

You can use the **/DELETE** qualifier to delete a verb in either your process command table or in a command table file specified with the **/TABLE** qualifier. If you do not use the **/TABLE** qualifier

to specify an alternate command table, the default is to delete verbs from your process command table. If you do not use the **/OUTPUT** qualifier to specify an output file, the default is to return the modified command table to your process.

The verb specifies a verb to be deleted. If you specify two or more verbs, separate them with commas and enclose the list in parentheses. If you specify only one verb, you can omit the parentheses.

You cannot use the **/LISTING**, **/OBJECT**, or **/REPLACE** qualifiers in **/DELETE** mode.

#### **/LISTING[=*filespec*] /NOLISTING**

Controls whether an output listing is created and optionally provides an output file specification for the listing file. A listing file contains a listing of the command definitions along with any error messages. The listing file is similar to a compiler listing.

If you specify the **/LISTING** qualifier and omit the file specification, output is written to the default device and directory; the listing file will have the same name as the first command definition file and a file type of .LIS.

You can use the **/LISTING** qualifier only in **/OBJECT** or **/REPLACE** mode; you cannot create a listing in **/DELETE** mode. In **/OBJECT** and **/REPLACE** modes, the default is **/NOLISTING**.

#### **/OBJECT[=*filespec*]**

Specifies **/OBJECT** mode to create an object module from a command definition file and optionally provides an object file specification. You cannot use the **/OBJECT** qualifier to create an object module from a command definition that contains the **IMAGE** keyword.

You can specify only one command definition file when you use **SET COMMAND/OBJECT**.

If you specify the **/OBJECT** qualifier and omit the file specification, output is written to the default device and directory; the object file will have the same name as the input file and a file type .OBJ.

You cannot use the **/DELETE**, **/OUTPUT**, **/REPLACE**, or **/TABLE** qualifiers in **/OBJECT** mode.

---

### **Note**

When compiling very large command definition (CLD) files, you may encounter the following error:

```
%CDU-F-INTNODESPACE, Internal error: node space exhausted
```

The default value of virtual memory allocated by the **SET COMMAND/OBJECT** command is 384KB. This value may not be sufficient to process large CLD files. To increase this size, use the **CDU\$TABLE\_SPACE** logical name to specify a larger value.

For example:

```
$ DEFINE CDU$TABLE_SPACE 2048
```

---

#### **/OUTPUT[=*filespec*] /NOOUTPUT**

Controls where the modified command table should be placed. If you provide an output file specification, the modified command table is written to the specified file. If you do not provide an

output file specification, the edited command table replaces your process table. The **/NOOUTPUT** qualifier indicates that no output is to be generated.

You can specify an output file specification with the **/OUTPUT** qualifier only when you also use the **/TABLE=filespec** qualifier to provide the input tables. The default file type is .EXE.

You can use the **/OUTPUT** qualifier only in **/DELETE** or **/REPLACE** mode; you cannot use the **/OUTPUT** qualifier in **/OBJECT** mode.

In **/DELETE** and **/REPLACE** mode, the default is **/OUTPUT** with no file specification.

## **/REPLACE**

Specifies **/REPLACE** mode to add or replace verbs in the command table you are modifying.

You can use the **/REPLACE** qualifier to modify either the process command table or a command table file specified with the **/TABLE** qualifier. If you do not use the **/TABLE** qualifier to specify an alternate command table, the default is to modify your process command table. If you do not use the **/OUTPUT** qualifier to specify an output file, the default is to return the modified command table to your process.

You cannot use the **/OBJECT** or **/DELETE** qualifiers in **/REPLACE** mode.

If you do not explicitly specify **/DELETE**, **/OBJECT**, or **/REPLACE** mode, the default is **/REPLACE**.

## **/TABLE=[filespec]**

Specifies the command table that is to be modified. If you specify the **/TABLE** qualifier and omit the file specification, the current process command table is modified. If you include a file specification, the specified command table is modified. The default file type is .EXE.

If you use the **/TABLE** qualifier to provide an input command table file, you should also use the **/OUTPUT** qualifier to provide an output table file; otherwise, the modified command table will be written to your process and will replace your process command table.

You can only use the **/TABLE** qualifier in **/DELETE** or **/REPLACE** mode; you cannot use the **/TABLE** qualifier in **/OBJECT** mode.

In **/REPLACE** and **/DELETE** mode, the default is **/TABLE** with no input file specification.

## **Examples**

1. `$ SET COMMAND SNAG`

This command adds the commands in SNAG .CLD to the command table in the current process.

2. `$ SET COMMAND/OBJECT SNAG`

This command creates an object file using the commands in SNAG .CLD. This object file can then be linked with other object files to process application defined commands.

3. `$ SET COMMAND/TABLE=MYTAB/OUTPUT=MYCLI SNAG`

This command adds the commands in SNAG .CLD to the command table MYTAB .EXE and writes the updated table to MYCLI .EXE.

When you use the **/TABLE** qualifier to specify an input command table, you should use the **/OUTPUT** qualifier to specify an output file; otherwise, your process command table will be overwritten.

#### 4. \$ SET COMMAND/DELETE=HOLD

This command deletes the definition for the verb **HOLD** from your process command table. The modified command table is returned to your process.

## SET CONTROL

**SET CONTROL** — Enables or disables the **Ctrl/Y** or the **Ctrl/T** function. Pressing **Ctrl/Y** interrupts a command and returns you to the DCL command level. Pressing **Ctrl/T** momentarily interrupts a command to print a line of statistics. **SET CONTROL=T** requires that **SET TERMINAL/BROADCAST** be set for the information to be displayed at your terminal.

### Format

**SET CONTROL[=(T,Y)] SET NOCONTROL[=(T,Y)]**

### Parameter

**(T,Y)**

Specifies that **T** (**Ctrl/T**) or **Y** (**Ctrl/Y**) be enabled or disabled. If you specify only one character, you can omit the parentheses. If you do not specify either **T** or **Y**, **Y** is the default.

### Description

The **Ctrl/Y** function provides a general-purpose escape from the current operation. The **Ctrl/Y** function can generally be used during an interactive terminal session to interrupt the current command, command procedure, or program image.

The **SET NOCONTROL=Y** command can be used for special application programs. When the **SET NOCONTROL=Y** command is executed in a system-specified command procedure for a particular user at login, that user can communicate only with the application program that controls the terminal.

When you press **Ctrl/Y** and **SET NOCONTROL=Y** is in effect, the **INTERRUPT** message is displayed, but no interruption takes place.

---

### Note

Note that DCL maintains a pending **Ctrl/Y** asynchronous system trap (AST) to the terminal driver. This affects captive command procedures when using the **SET HOST** command. For more information, see the description of the [SET HOST](#) command.

**SET NOCONTROL=Y** also disables the **Ctrl/C** cancel function for all commands and programs that do not have special action routines responding to the **Ctrl/C** function.

The **Ctrl/T** function displays a single line of statistical information about the current process. When you press **Ctrl/T** during an interactive terminal session, it momentarily interrupts the current command, command procedure, or image to display statistics. The statistical information includes the node and user

names, the current time, the current process, CPU usage, number of page faults, level of I/O activity, and memory usage. For example:

```
BOSTON::SMITH 16:21:04 EDT CPU=00:00:03.33 PF=778 IO=296 MEM=277
```

When **SET NOCONTROL=T** (the default) is in effect, pressing **Ctrl/T** does not cause any statistics to be displayed.

## Customizing the Output of Ctrl/T

By defining the new symbol **DCL\$CTRLT**, users can augment the traditional **Ctrl/T** output with the text defined for **DCL\$CTRLT**. This technique can be used to indicate progress in user applications or for debugging purposes.

## Examples

1. \$ SET NOCONTROL=Y

The **SET CONTROL** command in this example disables the **Ctrl/Y** function as well as most **Ctrl/C** functions.

2. \$ SET CONTROL=T

The **SET CONTROL** command in this example enables the **Ctrl/T** function.

3. \$ SET NOCONTROL=(T,Y)

The **SET CONTROL** command in this example disables both the **Ctrl/T** and **Ctrl/Y** functions.

4. \$ Ctrl/T  
NODE22::SMITH 16:21:04 (DCL) CPU=00:03:29.39 PF=14802 IO=18652 MEM=68  
\$ SET NOCONTROL=T  
\$ Ctrl/T

As shown in this example, when you press **Ctrl/T**, the system displays the appropriate information. The **SET NOCONTROL=T** command disables the **Ctrl/T** function. Now when you press **Ctrl/T**, no information is displayed.

5. \$ TYPE CTRLT\_LOOP.COM  
\$ inner=0  
\$ outer=0  
\$ loop:  
\$ loop1:  
\$ if inner .gt. 20000 then goto end\_loop1  
\$ inner=inner+1  
\$ dcl\$ctrlt=F\$FAO("Inner loop count is !SL Outer loop count is !  
SL" ,inner,outer)  
\$ goto loop1  
\$ end\_loop1:  
\$ inner=0  
\$ outer=outer+1  
\$ goto loop  
\$ @CTRLT\_LOOP  
  
<<Press Ctrl/T>>  
NODE1::JSMITH 10:46:37 (DCL) CPU=00:03:42.68 PF=13453 IO=6743 MEM=187  
Inner loop count is 12306  
Outer loop count is 0

```
NODE1::JSMITH 10:46:43 (DCL) CPU=00:03:49.19 PF=13455 IO=6744 MEM=187
Inner loop count is 19200
Outer loop count is 2
.
.
.
<<Press Ctrl/C>> <<--- To exit the loop.
$ SET NOCONTROL=T
$ @CTRLT_LOOP
<<Press Ctrl/T>>
<<Nothing is displayed as CTRL/T is disabled.>>
<<Press Ctrl/C>> <<--- To exit the loop.
```

This example demonstrates the use of DCL\$CTRLT within a command procedure. The command procedure is running in a loop that updates the symbol DCL\$CTRLT to indicate the number of loop iterations executed so far.

## SET CPU

SET CPU — Changes the user capabilities associated with the specified CPUs. **Requires ALTPRI and WORLD privileges.**

### Format

```
SET CPU [cpu-id[, ...]]
```

### Parameter

*cpu-id*

Specifies a decimal value representing the identity of a processor in an OpenVMS multiprocessing system. On an Alpha 7000 system, the CPU is the backplane slot number of the processor.

### Qualifiers

**/ALL**

Applies the specified operation to all CPUs in the active set.

**/ASSIGN [=option] (Alpha/Integrity servers only)**

Assigns the CPU to the current instance if no option is specified.

If an option is specified, the CPU is assigned to that resource.

| Option             | Description                                         |
|--------------------|-----------------------------------------------------|
| \$\$PARTITION      | The current soft partition of the OpenVMS instance. |
| \$\$HARD_PARTITION | The hard partition of the OpenVMS instance.         |

Supported only on AlphaServer systems that support partitioning.

**/AUTO\_START (Alpha/Integrity servers only)**

**/NOAUTO\_START**

Sets or clears the instance-specific autostart flag for the specified CPUs.

When autostart is enabled, that CPU will join the OpenVMS active set when it is assigned or migrated into the partition. The CPU will also autostart if a power-up transition is completed while the CPU is owned by the issuing instance.

Supported only on AlphaServer systems that support partitioning.

**/CAPABILITY**  
**/NOCAPABILITY**

Allows bits in the process user capability mask to be set or cleared individually, in groups, or all at once.

**Note**

The **SET CPU/[NO]CAPABILITY** command will fail if there is an active process that requires a capability that is not available on any remaining active CPU.

Specifying the **/CAPABILITY** qualifier has no direct effect, but merely indicates the target of the operations specified by the following secondary qualifiers:

| Qualifier                    | Description                                                                                                     |
|------------------------------|-----------------------------------------------------------------------------------------------------------------|
| <b>/SET=(n[ , . . . ])</b>   | Sets all user capabilities defined by the position values <i>n</i> , where <i>n</i> has the range of 1 to 16.   |
| <b>/CLEAR=(n[ , . . . ])</b> | Clears all user capabilities defined by the position values <i>n</i> , where <i>n</i> has the range of 1 to 16. |

The secondary qualifiers can all be used at once as long as the user capability bits defined in the **/SET** and **/CLEAR** parameters do not overlap.

The **/NOCAPABILITY** qualifier clears all user capability bits.

**/CLEAR=(n[,...])**

Clears all user capabilities defined by the position values *n* specified by the **/CAPABILITY** qualifier.

**/FAILOVER=option (Alpha/Integrity servers only)**  
**/NOFAILOVER**

Establishes instance-specific failover relationships for each CPU in the instance's potential set.

When the instance crashes, CPUs with a failover target other than the current instance will be assigned or migrated to that target.

Specifying the **/FAILOVER** qualifier has no direct effect; however, it indicates the target of the operations specified by the following options:

| Option               | Description                                                                                                                                                                          |
|----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>instance_name</i> | The name of any valid running instance in the current hard partition.                                                                                                                |
| <i>partitionID</i>   | The numeric ID of any partition(reflected in the configuration tree) in the current hard partition. An operating system instance is not required to be running with this identifier. |
| <b>\$\$PARTITION</b> | Assigns a resource to the current partition of the current instance.                                                                                                                 |

| Option                    | Description                                                                                                                                 |
|---------------------------|---------------------------------------------------------------------------------------------------------------------------------------------|
| <b>\$\$HARD_PARTITION</b> | Assigns a resource to the hard partition node of the configuration tree. This makes the CPU available to multiple soft partitions below it. |

The **/FAILOVER** qualifier generates a resource assignment only when the current instance crashes.

Supported only on AlphaServer systems that support partitioning.

## **/GLOBAL**

Modifies the global cell SCH\$GL\_DEFAULT\_CPU\_CAP. This global cell is used to initialize the user capability mask of CPUs that are brought into the active set for the first time.

## **/MIGRATE=option (Alpha/Integrity servers only)**

Transfers ownership of the CPU from the current instance to another soft partition.

| Option               | Description                                                                                                                                                                          |
|----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>instance_name</i> | The name of any valid running instance in the current hard partition.                                                                                                                |
| <i>partitionID</i>   | The numeric ID of any partition(reflected in the configuration tree) in the current hard partition. An operating system instance is not required to be running with this identifier. |

Supported only on AlphaServer systems that support partitioning.

## **/POWER=option (Alpha/Integrity servers only)**

Turns the power on or off in one or more CPU slots. Valid options are ON and OFF.

Supported only on AlphaServer GS series systems.

## **/OVERRIDE\_CHECKS (Alpha/Integrity servers only)**

Directs the **SET/CPU** command to bypass a series of checks that determine whether the specified processor is eligible for removal from the active set.

## **/REFRESH (Alpha/Integrity servers only)**

Examines and updates the OpenVMS context for the specified CPU or CPUs, using the hardware configuration tree.

## **/SET=(*n*[,...])**

Sets all user capabilities defined by the position values *n* specified by the **/CAPABILITY** qualifier.

## **/START (Alpha/Integrity servers only)**

Initiates a request for the specified CPU to join the OpenVMS active set if it is not already there.

# Examples

1. \$ SET CPU/CAPABILITY/GLOBAL/SET=(2,4)

This command sets user capabilities 2 and 4 in the global cell SCH\$GL\_DEFAULT\_CPU\_CAP.

2. \$ SET CPU/CAPABILITY/GLOBAL/SET=(2,4) 0

This command sets user capabilities 2 and 4 in the global cell SCH\$GL\_DEFAULT\_CPU\_CAP, as well in the active CPU 0.

3. \$ SET CPU/CAPABILITY/SET=(1,2) 0

\$ SHOW CPU/FULL

SYSTEM: EUROS, HPE RX2600 (900MHZ/1.5MB)

SMP EXECLET = 3 : ENABLED : STREAMLINED.

CONFIG TREE = VERSION 6

PRIMARY CPU = 0

HWRPB CPUS = 2

PAGE SIZE = 8192

REVISION CODE =

SERIAL NUMBER = US30464615

DEFAULT CPU CAPABILITIES:

SYSTEM: QUORUM RUN

DEFAULT PROCESS CAPABILITIES:

SYSTEM: QUORUM RUN

CPU 0 STATE: RUN CPUDB: 8901C000 HANDLE: 00005D70  
OWNER: 000004C8 CURRENT: 000004C8 PARTITION 0

(EUROS)

CHGCNT: 1 STATE: PRESENT, PRIMARY,

REASSIGNABLE

PROCESS: TEST11 PID: 20201185

CAPABILITIES:

SYSTEM: PRIMARY QUORUM RUN RAD0

USER: USR1 USR2

SLOT CONTEXT: 901EB000

CPU - STATE.....: RC, PA, PP, CV, PV, PMV, PL  
TYPE.....: ITANIUM MAJOR = 31, MINOR = 0  
SPEED.....: 900 MHZ  
LID.....: 00000000  
VARIATION.....: IEEE FP, PRIMARY ELIGIBLE  
SERIAL NUMBER...: 0001A968930A1A25  
REVISION.....:  
HALT REQUEST...: 0  
SOFTWARE COMP...: 7.0  
PALCODE - REVISION CODE...: 1.1  
COMPATIBILITY...: 0  
MAX SHARED CPUS: 0

BINDINGS: \* NONE \*

FASTPATH:

FGB0

PKA0

PEA0

EIA0

FEATURES:

AUTOSTART - ENABLED.

FASTPATH - SELECTION ENABLED AS PREFERRED CPU.

CPU 1 STATE: RUN CPUDB: 89163480 HANDLE: 00005E80  
OWNER: 000004C8 CURRENT: 000004C8 PARTITION 0

(EUROS)

CHGCNT: 1 STATE: PRESENT, REASSIGNABLE

PROCESS: \* NONE \*

CAPABILITIES:

```

        SYSTEM: QUORUM RUN RAD0
SLOT CONTEXT: 901EC000
  CPU      -  STATE.....: RC, PA, PP, CV, PV, PMV, PL
               TYPE.....: ITANIUM MAJOR = 31,  MINOR = 0
               SPEED.....: 900 MHZ
               LID.....: 01000000
               VARIATION.....: IEEE FP
               SERIAL NUMBER...: 000363B4B0C5C862
               REVISION.....:
               HALT REQUEST...: 0
               SOFTWARE COMP...: 7.0
  PALCODE -  REVISION CODE...: 1.1
               COMPATIBILITY...: 0
               MAX SHARED CPUS: 0
BINDINGS:    * NONE *
FASTPATH:
  FGA0
  EWA0
  PKB0
  BG0
FEATURES:
  AUTOSTART - ENABLED.
  FASTPATH  - SELECTION ENABLED AS PREFERRED CPU.

$ SET CPU/CAPABILITY/CLEAR=1 0

$ SHOW CPU/FULL
SYSTEM: EUROS, HPE RX2600  (900MHZ/1.5MB)

SMP EXECLET  = 3 : ENABLED : STREAMLINED.
CONFIG TREE  = VERSION 6
PRIMARY CPU  = 0
HWRPB CPUS  = 2
PAGE SIZE   = 8192
REVISION CODE =
SERIAL NUMBER = US30464615
DEFAULT CPU CAPABILITIES:
  SYSTEM: QUORUM RUN
DEFAULT PROCESS CAPABILITIES:
  SYSTEM: QUORUM RUN
CPU 0      STATE: RUN                CPUIDB: 8901C000      HANDLE: 00005D70
          OWNER: 000004C8            CURRENT: 000004C8      PARTITION 0
(EUROS)
          CHGCNT:          1          STATE: PRESENT, PRIMARY,
REASSIGNABLE
          PROCESS: TEST11            PID: 20201185
CAPABILITIES:
  SYSTEM: PRIMARY QUORUM RUN RAD0
  USER: USR2
SLOT CONTEXT: 901EB000
  CPU      -  STATE.....: RC, PA, PP, CV, PV, PMV, PL
               TYPE.....: ITANIUM MAJOR = 31,  MINOR = 0
               SPEED.....: 900 MHZ
               LID.....: 00000000
               VARIATION.....: IEEE FP, PRIMARY ELIGIBLE
               SERIAL NUMBER...: 0001A968930A1A25
               REVISION.....:
               HALT REQUEST...: 0

```

```

        SOFTWARE COMP...: 7.0
PALCODE - REVISION CODE...: 1.1
          COMPATIBILITY...: 0
          MAX SHARED CPUS: 0
BINDINGS: * NONE *
FASTPATH:
        FGB0
        PKA0
        PEA0
        EIA0
FEATURES:
        AUTOSTART - ENABLED.
        FASTPATH - SELECTION ENABLED AS PREFERRED CPU.

CPU 1      STATE: RUN                CPUIDB: 89163480      HANDLE: 00005E80
          OWNER: 000004C8            CURRENT: 000004C8      PARTITION 0
(EUROS)
        CHGCNT:          1                STATE: PRESENT, REASSIGNABLE
        PROCESS: * NONE *
CAPABILITIES:
        SYSTEM: QUORUM RUN RAD0
SLOT CONTEXT: 901EC000
CPU        - STATE.....: RC, PA, PP, CV, PV, PMV, PL
          TYPE.....: ITANIUM MAJOR = 31, MINOR = 0
          SPEED.....: 900 MHZ
          LID.....: 01000000
          VARIATION.....: IEEE FP
          SERIAL NUMBER...: 000363B4B0C5C862
          REVISION.....:
          HALT REQUEST...: 0
          SOFTWARE COMP...: 7.0
PALCODE - REVISION CODE...: 1.1
          COMPATIBILITY...: 0
          MAX SHARED CPUS: 0
BINDINGS: * NONE *
FASTPATH:
        FGA0
        EWA0
        PKB0
        BG0
FEATURES:
        AUTOSTART - ENABLED.
        FASTPATH - SELECTION ENABLED AS PREFERRED CPU.
$
```

In this example, the first **SET CPU** command sets user capabilities 1 and 2 for CPU 0. The second **SET CPU** command clears capability 1.

4. \$ SET CPU/REFRESH/ALL

This command updates the OpenVMS context in this instance for all CPUs physically residing in the current hard partition.

5. \$ SET CPU/FAILOVER=WFGLXA 12

This command sets CPU 12 to failover to another instance (WFGLXA), if the current instance crashes.

6. `$ SET CPU/FAILOVER=$$HARD 13`

This command assigns CPU 13 to hard partition ownership if the current instance crashes. Assignment to the hard partition makes the CPU visible and available to other instances for assignment.

7. `$ SET CPU/ASSIGN=$$HARD 14`

This command assigns CPU 14, currently owned by the instance, to hard partition ownership. Assignment to the hard partition makes the CPU visible and available to other instances for assignment.

8. `$ SET CPU/ASSIGN 15`

This command assigns CPU 15, currently owned by the hard partition, to this instance. If the CPU is powered, in the potential set, and autostart enabled, then it will automatically join the active set.

## SET DAY

**SET DAY** — Sets the default day type specified in the user authorization file (UAF) for the current day. Requires **OPER (operator) privilege**.

### Format

**SET DAY**

### Parameters

None.

### Description

The **SET DAY** command overrides the default primary and secondary day types that are used to control daily logins. These default day types are defined by the system manager in the user authorization file (UAF).

The **SET DAY** command is useful when you need to override the day type because of a change in the work days of a particular week. For example, Monday, which is normally a work day, is occasionally a holiday. You can use the **SET DAY** command to override the normal day type for Monday and set it to a different day type.

### Qualifiers

#### **/DEFAULT**

Overrides any previous **SET DAY** specification and specifies that the normal UAF defaults are to be used to determine today's day type.

#### **/LOG**

#### **/NOLOG (default)**

Controls whether log information is displayed at the terminal to confirm that the new **SET DAY** information has been set.

**/PRIMARY**

Sets today until midnight to a primary day.

**/SECONDARY**

Sets today until midnight to a secondary day.

## Examples

1. `$ SET DAY/PRIMARY`

The **SET DAY** command in this example overrides the current default day type and sets today until midnight to a primary day.

2. `$ SET DAY/DEFAULT`

The **SET DAY** command in this example overrides the previous **SET DAY** command and sets today's day type to the UAF-defined default.

## SET DEFAULT

**SET DEFAULT** — Sets your default device and directory specifications. The new default is applied to all subsequent file specifications that do not explicitly include a device or directory name. When you change the default device assignment, the system equates the specified device with the logical name `SYSDISK`.

### Format

**SET DEFAULT**[*device-name*[:]][*directory-spec*]

### Parameter

*device-name*[:]

Specifies the name of the device you want to go to.

---

### Note

The **SET DEFAULT** command will accept a node name with the device name(that is, node-name::device-name). However, the results of operations using a default with a node name are unpredictable. Some utilities and applications do not allow a node name to be specified in a file specification and will fail if the default file specification contains a node name.

---

*directory-spec*

Specifies the name of the directory you want to go to. A directory name must be enclosed in brackets ([ ]). Use the minus sign (-) to specify the next higher directory from the current default.

On Alpha systems, if the length of the resulting default directory specification exceeds 255 characters, the **SET DEFAULT** attempts to replace the default directory string with a generated directory specification. If this happens, then in addition to the normal syntax check, the entire path to that specification, including the device, is verified and must exist for the call to succeed.

On Alpha systems, if the process parse style is set to extended, then the directory specification may include a directory ID (DID).

You must specify either the *device-name* parameter or the *directory-spec* parameter. If you specify only the device name, the current directory is the default for the *directory-spec* parameter. If you specify only the directory name, the current device is the default for the *device-name* parameter.

You can use a logical name but it must constitute at least the device part of the specification. When you use a search list logical name as the parameter, the logical name is not translated by the **SET DEFAULT** command. Instead, the **SET DEFAULT** command retains the logical name so that OpenVMS Record Management Services (RMS) is able to access the entire search list. If you enter the **SHOW DEFAULT** command, the search list logical name is displayed as the default device, along with its equivalence strings.

## Examples

1. `$ SET DEFAULT [TANNER]`

The **SET DEFAULT** command in this example changes the default directory to [TANNER]. The default disk device does not change.

2. `$ SET DEFAULT $FLOPPY1:[MOREAU.MEMOS]`

The **SET DEFAULT** command in this example sets your default to the MOREAU.MEMOS subdirectory on \$FLOPPY1.

3. `$ SET DEFAULT $FLOPPY1:`

The **SET DEFAULT** command in this example sets the default device to \$FLOPPY1. The directory name does not change.

4. `$ SET DEFAULT [-]`

The **SET DEFAULT** command in this example changes the default directory to the parent directory of the one you are currently in. For example, if the current directory is \$FLOPPY1:[NIELSEN.MEMOS], this command sets your default to \$FLOPPY1:[NIELSEN]. If you are in \$FLOPPY1:[NIELSEN], this command sets your default to the master directory on the disk---\$FLOPPY1:[000000].

5. 

```
$ SAVEDEF = F$ENVIRONMENT("DEFAULT")
$ SET DEFAULT [122001.ZAMORA.APP10]      .      .      .
$ SET DEFAULT 'SAVEDEF'
```

The command procedure in this example uses the F\$ENVIRONMENT lexical function to save the current default directory in the symbol named SAVEDEF. The **SET DEFAULT** command changes the default directory 122001.ZAMORA.APP10. Later, the symbol SAVEDEF is used to restore the original default directory.

6. 

```
$ SHOW DEFAULT
WORK:[TOP]
$ DEFINE X WORK:[TOP.SUB1],WORK:[TOP.SUB2]
$ SET DEFAULT X
$ SHOW DEFAULT
X:[TOP]
=    WORK:[TOP.SUB1]
=    WORK:[TOP.SUB2]
```

```
$ DIRECTORY
Directory WORK:[TOP.SUB1]
KUDOS.TMP;1
Total of 1 file.
Directory WORK:[TOP.SUB2]
KUDOS.TMP;1
Total of 1 file.
Grand total of 2 directories, 2 files.
$ DIRECTORY []
Directory WORK:[TOP]
KUDOS.TMP;1          NETSERVER.LOG;2
Total of 2 files.
```

In this example, the default directory is `WORK:[TOP]`. `X` is then defined to be a search list consisting of two subdirectories. When the **SETDEFAULT X** command is entered, the search list (`X`) is equated with the logical name `SYSDISK` and is entered into the disk field. The subsequent **SHOW DEFAULT** command shows both the search list and the current default directory, followed by the expanded search list.

If a **DIRECTORY** command is entered, the directories searched are those contained in the logical name `X`; however, if the current default directory specification (`[]`) is explicitly entered, the current default directory, rather than `SYSDISK`, is searched.

7. 

```
$SET PROCESS/PARSE_STYLE=EXTENDED
$SET DEFAULT WORK:[11,1,0]
$SHOW DEFAULT
WORK:[11,1,0]
$DIRECTORY
Directory WORK:[11,1,0]
X.X;1
Total of 1 file.
```

On Alpha systems, the **SET DEFAULT** command in this example uses a directory ID (DID) in the directory specification.

8. 

```
$SET PROCESS/PARSE_STYLE=EXTENDED
$SET DEFAULT -
WORK:
[.LONG_DIRECTORY_NAME_AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA]
$SET DEFAULT -
WORK:
[.LONG_SUBDIRECTORY_NAME_BBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBB]
$SET DEFAULT -
WORK:
[.LONG_SUBDIRECTORY_NAME_CCCCCCCCCCCCCCCCCCCCCCCCCCCCCCCCCC]
$SET DEFAULT -
WORK:
[.LONG_SUBDIRECTORY_NAME_DDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDD]
$SET DEFAULT -
WORK:
[.LONG_SUBDIRECTORY_NAME_EEEEEEEEEEEEEEEEEEEEEEEEEEEEEEEEEEE]
$SHOW DEFAULT
MDA0:[15,1,0]
$SET DEFAULT [-]
%RMS-F-DIR, error in directory name
$SET DEFAULT [.TEST]
$SHOW DEFAULT
```

```
MDA0:[15,1,0.TEST]
```

On Alpha systems, because the total length of the default directory string would exceed 255 characters in this example, a Directory ID is used in the directory specification. When the default directory string is replaced with a Directory ID, it is not possible to use the minus sign to specify the next higher directory.

## SET DEVICE

**SET DEVICE** — Establishes a print device or terminal as a spooled device or establishes the operational status for a device.

### Format

```
SET DEVICE [device-name[:]]
```

### Parameter

*device-name*[:]

Specifies the name of the device whose spooling or operational status is to change. The device must be a print device or a terminal if you want to change the spooling status; the device must be a disk or magnetic tape if you want to change the operational status.

When you specify qualifiers that act on shadow sets, the device might be a shadow set member (*ddcu:*) or the whole shadow set (*DSAnnnn:*), as noted in the qualifier format. Depending on the qualifier, if no device name is supplied, the qualifier applies to *all* shadow sets mounted on the node from which the command is executed.

### Description

**Requires OPER (operator) privilege.**

**PHY\_IO (physical I/O) privilege** is required when specifying the Alpha-only qualifiers that change the characteristics of shadow sets. These qualifiers also can be specified using the **SET SHADOW** command, which provides additional options for controlling shadow sets. Qualifier settings for shadow sets remain in effect until they are changed using either **SET DEVICE** or **SET SHADOW** or until the shadow set or shadow set member is dismounted. If the shadow set is remounted or a shadow set member is returned to the shadow set from which it was dismounted, the settings must be specified again. For more information about volume shadowing, see the [VSI OpenVMS Volume Shadowing Guide \[https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/\]](https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/).

When you specify any of the following qualifiers, the operational status of the drive is changed:  
**/ABORT\_VIRTUAL\_UNIT**, **/AVAILABLE**, **/COPY\_SOURCE**, **/DUAL\_PORT**, **/ENABLE**,  
**/ERROR\_LOGGING**, **/FORCE\_REMOVAL**, **/MEMBER\_TIMEOUT**, **/MVTIMEOUT**, **/POLL**,  
**/READ\_COST**, **/SITE**, or **/SWITCH**.

When you specify the **/SPOOLED** qualifier, program output that uses OpenVMS Record Management Services (RMS) or file control system (FCS) and that specifies the print device name is written onto an intermediate disk rather than written directly to the print device or terminal.

## Qualifiers

### **/ABORT\_VIRTUAL\_UNIT DSA<sub>nnnn</sub>: (Alpha/Integrity servers only)**

Aborts mount verification on a shadow set.

Use this qualifier when you know that the unit cannot be recovered. When you use this qualifier, the shadow set must be in mount verification. The shadow set aborts mount verification immediately on the node from which the command is issued. If the shadow set is not in mount verification, this command returns the error

%SYSTEM-E-UNSUPPORTED, unsupported operation or function.

After this command completes, the shadow set still must be dismounted. Use the following command to dismount the shadow set:

```
$ DISMOUNT/ABORT DSAnnnn:
```

### **/AVAILABLE**

### **/NOAVAILABLE**

Controls whether the specified disk or magnetic tape is to be considered available.

You must dismount the specified disk or magnetic tape before entering the

**SET DEVICE/[NO]AVAILABLE** command. If you specify the **/NOAVAILABLE** qualifier, any attempt to allocate or mount the specified disk or magnetic tape is prevented. Devices are automatically set **/AVAILABLE** when brought online even if the device had been previously set **/NOAVAILABLE**.

### **/COPY\_SOURCE {ddcu: | DSA<sub>nnnn</sub>:} (Alpha/Integrity servers only )**

Specifies which source member of a shadow set will be used as the source for read data during full copy operations when a third member is added to the shadow set. This qualifier affects only copy operations that do not use disk copy data (DCD) commands.

Some storage controllers, such as the HSG80, have a read-ahead cache, which significantly improves single-disk read performance. Copy operations normally alternate reads between the two source members, which effectively nullifies the benefits of the read-ahead cache. This qualifier lets you force all reads from a single, specified source member for a copy operation.

If only a shadow set (DSA<sub>nnnn</sub>:) is specified, all reads for full copy operations will be performed from the disk that is the current "master" member, regardless of physical location of the disk.

If a shadow set member (ddcu:) is specified, that member will be used as the source of all copy operations. This allows you to choose a local source member, rather than a remote master member.

### **/DUAL\_PORT**

### **/NODUAL\_PORT**

Controls whether the port seize logic in the device driver of the specified disk is to be enabled. This qualifier should be used only on disks that contain a dual port kit and have been dismounted.

### **/ENABLE**

### **/NOENABLE**

Enables or disables a path to a multipath device; the affected path is the one named in the **/PATH** qualifier. All paths are initially enabled; the current path cannot be disabled.

**/ERROR\_LOGGING**  
**/NOERROR\_LOGGING**

Controls whether device errors are logged in the error log file. When you specify the **/ERROR\_LOGGING** qualifier, all error messages reported by the device on which error logging is enabled are recorded in the error log file. Use the **SHOW DEVICE/FULL** command to find out the current status.

**/FORCE\_REMOVAL ddcu: (Alpha/Integrity servers only )**

Expels the specified shadow set member from the shadow set.

If connectivity to a device has been lost and the shadow set is in mount verification, this qualifier causes the member to be expelled from the shadow set immediately.

If the shadow set is not currently in mount verification, no immediate action is taken. If connectivity to a device has been lost but the shadow set is not in mount verification, this qualifier lets you flag the member to be expelled from the shadow set, as soon as it does enter mount verification.

The specified device must be a member of a shadow set that is mounted on the node where the command is issued.

**/LOG**  
**/NOLOG (default)**

Controls whether log information is displayed at the terminal.

**/MEMBER\_TIMEOUT=n ddcu: (Alpha/Integrity servers only)**

Specifies the timeout value to be used for a shadow set member.

The value supplied by this qualifier overrides the system parameter **SHADOW\_MBR\_TMO** for this specific device. Each member of a shadow set can be assigned a different **MEMBER\_TIMEOUT** value.

The valid range for *n* is 1 to 16777215 seconds.

The specified device must be a member of a shadow set that is mounted on the node where the command is issued.

**/MV\_INTVL=n**

Overrides the systemwide setting of the **MVSUPMSG\_INTVL** system parameter with the value specified by *n* (seconds) for the specified device only. If **/MV\_INTVL=0**, the value for **MVSUPMSG\_INTVL** is used instead. If **MVSUPMSG\_INTVL=0** or **MVSUPMSG\_NUM=0**, all mount verifications are announced. For more information about **MVSUPMSG\_INTVL**, see the relevant section in the [VSI OpenVMS System Management Utilities Reference Manual, Volume 2: M-Z](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/#SYS_PARAMS_SEC) [[https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/#SYS\\_PARAMS\\_SEC](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/#SYS_PARAMS_SEC)].

**/MV\_NUM=n**

Overrides the systemwide setting of the **MVSUPMSG\_NUM** system parameter with the value specified by *n* (seconds) for the specified device only. If **/MV\_NUM=0**, the value for

MVSUPMSG\_NUM is used instead. If MVSUPMSG\_NUM=0 or MVSUPMSG\_INTVL=0, all mount verifications are announced. For more information about MVSUPMSG\_NUM, see the relevant section in the [VSI OpenVMS System Management Utilities Reference Manual, Volume 2: M-Z](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/#SYS_PARAMS_SEC) [[https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/#SYS\\_PARAMS\\_SEC](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/#SYS_PARAMS_SEC)].

**/MVTIMEOUT=*n* DSAnnnn: (Alpha/Integrity servers only)**

Specifies the mount verification timeout value to be used for the shadow set specified by its virtual unit name (DSAnnnn:).

The value supplied by this qualifier overrides the value specified by the system parameter MVTIMEOUT for this specific shadow set.

---

**Note**

You cannot change the value of MVTIMEOUT for a system disk. Any attempt to do so results in an error.

---

The valid range for *n* is 1 to 16777215 seconds.

The specified shadow set must be mounted on the node where the command is issued.

**/PATH=*path-description-string***

(For multipath devices only) Specifies a particular route to the device. The path description string identifies a path from the host to the device (for example, PGA0.2343-A855-BC99-876F or PKC0.5). Wildcard characters have no special meaning. The path description can be abbreviated to the minimum unique string.

Note that this qualifier does not imply that any action be taken. To take action, you must also specify one of the following qualifiers: / **(NO) ENABLE**, / **(NO) POLL**, or / **SWITCH**.

**/POLL**

**/NOPOLL**

Specifies that the path specified by the **/PATH** qualifier is to be polled for continued availability as a path switch destination. This does not affect any attempt to switch to this path. Its purpose is only to inform an operator that a path may or may not be viable as a path switch destination. By default, all device paths are enabled for polling when they are discovered. Note that this qualifier applies only to multipath devices.

**/PREFERRED\_CPUS=*cpu-a[,cpu-b,cpu-c,...]***

**/NOPREFERRED\_CPUS**

Allows you to specify a CPU or a set of candidate CPUs from which the operating system chooses the CPU to assign to the Fast Path port. The chosen CPU is called the preferred CPU for this Fast Path port. The Fast Path port's interrupt I/O completion processing and I/O initiation processing are performed on this preferred CPU.

In addition to selecting the preferred CPU, the User Preferred CPU is set for this port. Setting the User Preferred CPU prevents the port from being reassigned to another CPU unless the User preferred CPU is being stopped. The qualifier can be negated. When the **/NOPREFERRED\_CPUS**

qualifier is specified, the User Preferred CPU is cleared for the port, but it remains a Fast Path port, and the current preferred CPU is not changed.

If both **/PREFERRED\_CPUS** and **/NOPREFERRED\_CPUS** are specified on the same command line, **/NOPREFERRED\_CPUS** is ignored.

If Fast Path is enabled, you can use the DCL command, **SHOW DEVICE/FULL**, to display the current preferred CPU and the User Preferred CPU.

For more information about using Fast Path features to improve I/O performance, see the relevant section in the *VSI OpenVMS I/O User's Reference Manual* [<https://docs.vmssoftware.com/vsi-openvms-io-user-s-reference-manual/#d0e29396>].

### **/READ\_COST=*n* {*ddcu*: | *DSAnnnn*:} (Alpha/Integrity servers only)**

Enables you to modify the default cost assigned to each shadow set member (*ddcu*:). By modifying the assignments, you can bias the reads in favor of one member of a two-member shadow set, or, in the case of three-member shadow sets, in favor of one or two members of the set over the remaining members. The device specified must be a shadow set or member of a shadow set that is mounted on the node where the command is issued.

The valid range for the specified cost is 1 to 65,535 units.

The shadowing driver assigns default **READ\_COST** values to shadow set members when each member is initially mounted. The default value depends on the device type and its configuration relative to the system mounting it. The following list of device types is ordered by the default **READ\_COST** assignments, from the lowest cost to the highest cost:

- DECram device
- Directly connected device in the same physical location
- Directly connected device in a remote location
- DECram served device
- Default value for other served devices

The value supplied by the **/READ\_COST** qualifier overrides the default assignment. The shadowing driver adds the value of the current queue depth of the shadow set member to the **READ\_COST** value and then reads from the member with the lowest value.

Different systems in the cluster can assign different costs to each shadow set member.

When this qualifier specifies a shadow set (*DSAnnnn*;) instead of a shadow set member, the **/READ\_COST** qualifier switches the read cost setting for *all* shadow set members back to the default read cost settings established automatically by the shadowing software. The specified shadow set must be mounted on the node where the command is issued. In this case, the value specified for the cost can be any number because it will be ignored.

If the **/SITE** command qualifier has been specified, the shadowing driver takes site values into account when it assigns default **READ\_COST** values. In order for the shadowing software to determine whether a device is in the category of "directly connected device in a remote location", the **/SITE** command qualifier must have been applied to *both* the shadow set and the shadow set member.

Reads requested for a shadow set from a system at site 1 are performed from a shadow set member that is also at site 1. Reads requested for the same shadow set from site 2 can read from the member located at site 2.

**/RESET=(*keyword*[,*keyword*])**

Requires CMKRNL and DIAGNOSE privileges.

Resets either or both the error count and the operation count for a device. You must specify one or both of the following keywords:

| Keyword         | Description                 |
|-----------------|-----------------------------|
| ERROR_COUNT     | Resets the error count.     |
| OPERATION_COUNT | Resets the operation count. |

When either count is reset, a message is sent to the error log. The message indicates that the count was reset and includes the value of the counter before the reset.

**/SITE=*n* {*DSAnnnn*: | *ddcu*:} (Alpha/Integrity servers only )**

Indicates to the shadowing driver the site location of the specified shadow set (*DSAnnnn*:) or shadow set member (*ddcu*:). If the member is removed from the shadow set and later is returned, this qualifier must be specified again.

The SHADOW\_SITE\_ID system parameter defines the default site location of the shadow set. You can override the default location of the shadow set with the **/SITE** qualifier.

The valid range for the site location, represented by *n*, is 1 through 255.

After you apply this qualifier, the setting remains in effect until you change it either with this command or with the **SET SHADOW/SITE** command.

This qualifier can improve read performance because the member that is physically local to the system will be the preferred disk from which to read, provided that you specify the **/SITE** qualifier for each shadow set member and for the shadow set. (In a Fibre Channel configuration, shadow set members at different sites are directly attached to the system. For the Volume Shadowing and cluster software, there is no distinction between local and remote in multiple-site Fibre Channel configurations.)

**/SPOOLED[(*queue-name*[:],*intermediate-disk-name*[:])]  
/NOSPOOLED**

Controls whether files are spooled to an intermediate disk.

The queue name indicates the printer queue to which a file is queued. If a queue name is not supplied, the default is the name of either the printer or terminal.

The intermediate disk name identifies the disk to which the spooled files are written. If the intermediate disk name is not supplied, the default is SYS\$DISK (the current default disk). The intermediate disk must be mounted before files can be written to it.

Once the device has been set spooled to a disk, that disk cannot be dismounted until the spooled device is set to **/NOSPOOLED**. All channels must be deassigned from a print device before its

spooling characteristics can be changed. Also, the queue that is assigned to the device must be stopped.

## /SWITCH

Attempts to switch from the current path of a multipath device to the path named in the **/PATH** qualifier. The path switch is attempted only if the path has not been disabled by **SET DEVICE/NOENABLE**. The path switch is initiated but not completed before returning control to the user; use **SHOW DEVICE/MULTIPATH** to verify that the path switching has completed successfully.

This command requires the OPER privilege. Additionally, if the device is currently allocated by another process, as tape devices often are, the SHARE privilege is needed.

## Examples

1. `$ SET DEVICE/SPOOLED=(LPA0) LPA0:`

In this example, the **/SPOOLED** qualifier requests that the printer queue LPA0 be spooled to an intermediate disk before files directed to the disk are printed. Because no intermediate disk was specified, the intermediate disk defaults to SYS\$DISK.

2. `$ SET DEVICE/ERROR_LOGGING DKB2:`

The **SET DEVICE** command in this example requests that all device errors reported on device DKB2 be logged in the error log file.

3. `$ SET DEVICE/NOAVAILABLE DRA0:`

The **SET DEVICE** command in this example prevents any attempt to mount a disk on device DRA0.

4. `$ SET DEVICE/DUAL_PORT DRA0:`

The **SET DEVICE** command in this example enables the dual port seize logic in device DRA0.

5. `$ SET DEVICE/PREFERRED_CPU=1 PNA0`

The Fast Path port PNA0 is assigned to CPU 1, and the User Preferred CPU is set to 1.

6. `$ SET DEVICE/NOPREFERRED_CPU PNA0`

The port PNA0 will have the User Preferred CPU cleared, but will remain a Fast Path port, with CPU 1 as its current preferred CPU.

7. `$ SET DEVICE/PREFERRED_CPU=(0,1,2) PNA0`

The operating system selects CPU 0, 1, or 2 as the preferred CPU for Fast Path port PNA0, and sets its User Preferred CPU to the selected CPU.

8. `$ SET DEVICE $1$DGA1001:/PATH=PGB0.0123-4567-89AB-CDEF/ENABLE`

In this example, a request is made to enable path PGB0.0123-4567-89AB-CDEF as a switch path destination. No error is indicated if the path was in the enabled state prior to the request. Had the **/NOENABLE** option been used, the path would have been removed from switch path consideration.

9. `$ SET DEVICE $1$DGA1001:/PATH=PGB0.0123-4567-89AB-CDEF/POLL`

In this example, a request is made to enable path `PGB0.0123-4567-89AB-CDEF` for polling of its continued availability as a path switch destination. Had the **/NOPOLL** option been used, the path would have been removed from path availability polling consideration.

10. `$ SET DEVICE $1$DGA1001:/PATH=PGB0.0123-4567-89AB-CDEF/SWITCH`

In this example, a request is made to switch from the current path to path `PGB0.0123-4567-89AB-CDEF`. Should the path fail, the switch algorithm of the unspecified path is used.

11. `$ ! Command sequence used on system 1 at site 1:`  
`$ MOUNT/SYSTEM DSA0:/SHADOW=($1$DGA0:,$1$DGA1:) TEST`  
`$ SET DEVICE/SITE=1 DSA0:`  
`$ !`  
`$ ! Command sequence used on system 2 at site 2:`  
`$ MOUNT/SYSTEM DSA0:/SHADOW=($1$DGA0:,$1$DGA1:) TEST`  
`$ SET DEVICE/SITE=2 DSA0:`  
`$ !`  
`$ ! Commands used on both system 1 and system 2:`  
`$ SET DEVICE/SITE=1 $1$DGA0:`  
`$ SET DEVICE/SITE=2 $1$DGA1:`

In this example, the system at `site 1` will perform all reads from `$1$DGA0`, which is the physically local disk, while the system at `site 2` will perform all reads from its physically local disk, `$1$DGA1`.

## SET DEVICE/SERVED

**SET DEVICE/SERVED** — Makes a disk on a local node available to all the nodes in an OpenVMS Cluster. **Applies only to OpenVMS Cluster environments.**

### Format

**SET DEVICE/SERVED** *node-name\$ddcu:*

### Parameter

*node-name\$ddcu:*

Specifies the device name of the device that you want to make available to the cluster.

### Description

The **SET DEVICE/SERVED** command is used in conjunction with the mass storage control protocol (MSCP) server to make a disk on a local node available to all nodes on the cluster. The local node must be a member of an OpenVMS Cluster, and the local MSCP server must have been invoked by the System Generation utility (SYSGEN).

You cannot use the **SET DEVICE/SERVED** command under the following conditions:

- In service of a Phase II shadow set virtual unit
- On devices that are already mounted

- On system disks
- On quorum disks

The **SET DEVICE/SERVED** command string can be included as part of the local startup command file and entered before the Mount utility mounts the disk to be served (made available to the entire cluster).

## Example

```
$ SET DEVICE/SERVED DRA4:
```

The **SET DEVICE/SERVED** command in this example instructs the MSCP server to make the disk device DRA4 on your local node available to all other processors on your cluster.

## SET DIRECTORY

SET DIRECTORY — Modifies the characteristics of one or more directories. **See the qualifier descriptions for restrictions.**

### Format

```
SET DIRECTORY [device-name[:]]directory-spec[,...]
```

### Parameters

*device-name*[:]

Specifies the device on which the directory that you want to modify is located. The device name parameter is optional.

*directory-spec*[,...]

Specifies one or more directories to be modified. If you specify more than one directory, separate the directory specifications with commas. The asterisk (\*) and the percent sign (%) wildcard characters are allowed.

### Qualifiers

#### /BACKUP

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/BACKUP** qualifier selects directories according to the dates of their most recent backups. This qualifier is incompatible with the **/CREATED**, **/EXPIRED**, and **/MODIFIED** qualifiers, which also allow you to select directories according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

#### /BEFORE[=*time*]

Selects only those directories dated prior to the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: **BOOT**, **LOGIN**, **TODAY** (default), **TOMORROW**, or **YESTERDAY**. Specify one of the following qualifiers with the **/BEFORE** qualifier to indicate the time attribute to be used as the basis for selection: **/BACKUP**, **/CREATED** (default), **/EXPIRED**, or **/MODIFIED**.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic Date.

### **/BY\_OWNER[=*uic*]**

Selects only those directories whose owner user identification code (UIC) matches the specified owner UIC. The default UIC is that of the current process.

Specify the UIC by using standard UIC format as described in the relevant section in the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC_SECTION) [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC\_SECTION].

The **/OWNER\_UIC** qualifier requires control access, a system UIC, or privilege.

### **/CONFIRM**

#### **/NOCONFIRM (default)**

Controls whether a request is issued before each **SET DIRECTORY** operation to confirm that the operation should be performed on that file. The following responses are valid:

|      |       |               |
|------|-------|---------------|
| YES  | NO    | QUIT          |
| TRUE | FALSE | <b>Ctrl/Z</b> |
| 1    | 0     | ALL           |

#### **Return**

You can use any combination of uppercase and lowercase letters for word responses. Word responses can be abbreviated to one or more letters (for example, T, TR, or TRU for TRUE), but these abbreviations must be unique. Affirmative answers are YES, TRUE, and 1. Negative answers include: NO, FALSE, 0, and pressing **Return**. Entering QUIT or pressing **Ctrl/Z** indicates that you want to stop processing the command at that point. When you respond by entering ALL, the command continues to process, but no further prompts are given. If you type a response other than one of those in the list, DCL issues an error message and redisplay the prompt.

### **/CREATED (default)**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/CREATED** qualifier selects directories based on their dates of creation. This qualifier is incompatible with the **/BACKUP**, **/EXPIRED**, and **/MODIFIED** qualifiers, which also allow you to select directories according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

### **/EXCLUDE=(*filespec*[,...])**

Excludes the specified directories from the SET DIRECTORY operation. You can include a directory but not a device in the file specification. The asterisk (\*) and the percent sign (%) wildcard characters are allowed in the file specification; however, you cannot use relative version numbers to exclude a specific version. If you specify only one directory, you can omit the parentheses.

### **/EXPIRED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/EXPIRED** qualifier selects directories according to their expiration dates. (The expiration date is set with the

**SET FILE/EXPIRATION\_DATE** command.) The **/EXPIRED** qualifier is incompatible with the **/BACKUP**, **/CREATED**, and **/MODIFIED** qualifiers, which also allow you to select directories according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

#### **/LOG**

#### **/NOLOG (default)**

Controls whether the system displays the directory specification of each directory that is modified as the command executes.

#### **/MODIFIED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/MODIFIED** qualifier selects directories according to the dates on which they were last modified. This qualifier is incompatible with the **/BACKUP**, **/CREATED**, and **/EXPIRED** qualifiers, which also allow you to select directories according to time attributes. If you specify none of these four time modifiers, the default is the **/CREATED** qualifier.

#### **/OWNER\_UIC[=*uic*]**

Requires control access, a system UIC, or privilege.

Specifies an owner UIC for the directory. The default UIC is that of the current process.

#### **/SINCE[=*time*]**

Selects only those directories dated on or after the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: **BOOT**, **JOB\_LOGIN**, **LOGIN**, **TODAY** (default), **TOMORROW**, or **YESTERDAY**. Specify one of the following qualifiers with the **/SINCE** qualifier to indicate the time attribute to be used as the basis for selection: **/BACKUP**, **/CREATED** (default), **/EXPIRED**, or **/MODIFIED**.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic **Date**.

#### **/STYLE=*keyword***

Specifies the file name format for display purposes.

The valid keywords for this qualifier are **CONDENSED** and **EXPANDED**. Descriptions are as follows:

| Keyword             | Description                                                                                                                                                                           |
|---------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CONDENSED (default) | Displays the file name representation of what is generated to fit into a 255-length character string. This file name may contain a DID or FID abbreviation in the file specification. |
| EXPANDED            | Displays the file name representation of what is stored on disk. This file name does not contain any DID or FID abbreviations.                                                        |

The keywords **CONDENSED** and **EXPANDED** are mutually exclusive. This qualifier specifies which file name format is displayed in the output message, along with the confirmation if requested.

File errors are displayed with the CONDENSED file specification unless the EXPANDED keyword is specified.

See the relevant section in the *VSI OpenVMS User's Manual* [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE\\_ACCESS](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE_ACCESS)] for more information.

### **/SYMLINK=keyword**

The valid keywords for this qualifier are [NO]WILDCARD and [NO]ELLIPSIS. Descriptions are as follows:

| Keyword    | Description                                                                      |
|------------|----------------------------------------------------------------------------------|
| WILDCARD   | Indicates that symlinks are enabled during wildcard searches.                    |
| NOWILDCARD | Indicates that symlinks are disabled during directory wildcard searches.         |
| ELLIPSIS   | Equivalent to WILDCARD (included for command symmetry).                          |
| NOELLIPSIS | Indicates that symlinks are matched for all wildcard fields except for ellipsis. |

If the file named in the **SET DIRECTORY** command is a symlink, the command operates on the symlink target.

### **/VERSION\_LIMIT[=n]**

Sets the maximum number of versions that files in a specified directory can have. If you do not set a version limit, a value of 0 is used, indicating that the number of file versions is limited only to the Files-11 architectural limit of 32,767. If you change the version limit for a directory, the new version limit applies only to files created after the change has been made. When creating a file, if the total number of versions of that file name exceeds the specified version limit, then the file with the lowest version number is deleted from the directory without notification to the user.

The version limit set on a directory has no effect on the version limit set on a particular file in that directory. To set a version limit on a particular file in a directory, use the **SET FILE/VERSION\_LIMIT[=n]** command.

To view the version limit on a directory, use the **DIRECTORY/FULL** command on a directory file and look at the File Attributes field of the output.

## Examples

1. `$ SET DIRECTORY/VERSION_LIMIT=5/CONFIRM [VERCAMMEN...]`

The **SET DIRECTORY** command in this example sets a version limit of 5 for all files in the VERCAMMEN directory (the root directory) and all subdirectories of [VERCAMMEN]. The **/CONFIRM** qualifier requests that you confirm whether the specified directory should actually be modified. Note that this version limit applies only to files created after the command is entered.

2. `$ SET DIRECTORY/VERSION_LIMIT=8 [.JAIMON...]`

In this example, the **SET DIRECTORY** command sets a version limit of 8 for all files in the JAIMON subdirectory and any of its subdirectories (for example, [.JAIMON.ADRIAN]). The setting for these specific directories overrides any version limit that might be set for the root directory and its other subdirectories.

3. `$ SET DIRECTORY/OWNER_UIC=[360,020] [WOERTMAN], [MOSER]`

The **SET DIRECTORY** command in this example modifies both the [WOERTMAN] and [MOSER] directories, changing their owner UICs. Using the **/OWNER\_UIC** qualifier requires SYSPRV (system privilege).

## SET DISPLAY

**SET DISPLAY** — Directs the output of an OpenVMS DECwindows application. Output can be directed from any processor running a DECwindows application, including workstations, to any DECwindows workstation. Both source and destination nodes must be part of the same network.

### Format

**SET DISPLAY** [*display-device*]

### Parameter

*display-device*

Specifies a logical name for the workstation display you are creating or modifying. If you are directing application output to multiple workstation displays, you can use different logical names to point to each display. If you do not specify a *display-device* parameter, the logical name DECW\$DISPLAY is used. This means that, by default, application output will be displayed on the workstation display device referred to by DECW\$DISPLAY.

By entering the command **SHOW DISPLAY**, you can see the default workstation node where applications will be displayed, as well as related device, screen, and transport information.

If you specified your own logical name in the **SET DISPLAY/CREATE** command, include that logical name in the **SHOW DISPLAY** command.


### Description

DECwindows gives you the ability to run applications across a network. The **SET DISPLAY** command enables you to direct the output of client applications across the network to an alternate workstation (X display server) for viewing. For example, the **SET DISPLAY** command allows you to:

- Redirect the output from local client applications to a remote workstation for display.
- Redirect the output from remote client applications to your local workstation for display. Although the application runs on another processor, it looks the same as any other application running locally on your workstation.

By running applications on a remote processor for local display on your workstation monitor, you can take advantage of larger computers that might be better suited to a specific computing task. By default, applications running on your workstation are displayed on your workstation. While DECwindows must be available on both nodes, only the display (X server) node must be a workstation.

The **SET DISPLAY** command affects only those applications running from the process from which you enter the command. This means that although you might be running one application on your workstation and displaying it on another workstation, you can continue to run applications on your workstation for display in other windows on your workstation as illustrated in *Figure 1, "Running Remote and Local Applications"*.

**Figure 1. Running Remote and Local Applications**

Qualifiers to the **SET DISPLAY** command enable you to create the display device and manage aspects of the network connection between the client application and the X display server, as described in the following sections.

## Redirecting Application or Display Output

To direct application output to another DECwindows workstation, enter the **SET DISPLAY** command in the following form:

```
SET DISPLAY/CREATE/NODE=workstation_display/TRANSPORT=transport_name
```

If you do not specify the **/TRANSPORT** qualifier, the value defined by the logical `DECW$SETDISPLAY_DEFAULT_TRANSPORT` is used. If this logical is not defined, the value of `DECNET` is used as the default.

Subsequently, you can redirect the display to other workstation devices by entering a DCL command in the following form:

```
SET DISPLAY/NODE=workstation_display
```

## Specifying Workstation Access

By default, you are authorized to run client applications locally on your workstation (X display server). You cannot log into another node and direct applications to display on your workstation unless you explicitly authorize yourself to do so. This prevents unauthorized users on other nodes in the network from directing output to or receiving input from your workstation without your specific permission.

Using the DECwindows Session Manager, you or a privileged user can grant other users running remote applications access to your workstation using one of the following access control schemes:

- User-based access control
- Token-based access control (Alpha/Integrity servers only)
  - Magic Cookie (based on the MIT-MAGIC-COOKIE-1 protocol)
  - Kerberos (based on the MIT-KERBEROS-5 protocol)

Once access is granted, authorized users can use the **SET DISPLAY** command to create a display device that accesses the remote workstation, or more specifically, the remote X display server.

When using a display device to access a remote X display server, make sure that the node or host name you specify in the **SET DISPLAY** command represents a workstation on which you are authorized to display applications. For example, if you specify **SET DISPLAY /CREATE /NODE=HUBBUB** from node ZEPHYR, and are not authorized to display applications on the workstation HUBBUB, an error message is displayed indicating that you are not authorized to use the device.

On Alpha and Integrity server systems, the **/GENERATE**, **/REVOKE**, and **/[NO]XAUTHORITY** qualifiers to **SET DISPLAY** enable you to specify additional authorization information when directing client applications to a workstation that uses a token-based access control scheme.

---

## Note

The MIT-KERBEROS-5 protocol does not currently support key generation, as defined by the SECURITY extension. Do not use the **/GENERATE** and **/REVOKE** qualifiers when connecting to an X display server protected by Kerberos access control.

---

For information about displaying applications on other workstation nodes, using the DECwindows Session Manager to authorize remote connections, and supported access control schemes see the DECwindows documentation.

## Using Proxy Servers (Alpha/Integrity servers Only)

Some system configurations use Low-Bandwidth X (LBX) proxy servers to manage communication between client applications and one or more X display servers. With DECwindows, an LBX proxy server configuration can be categorized as either standalone or managed. Managed configurations use a proxy manager application to further filter and direct incoming connection requests by client applications.

The **/PROXY** qualifier specifies that a proxy manager application be used to locate a managed proxy server. The **/PMPORT** and **/PMTRANSPORT** qualifiers identify the port and network transport for the proxy manager. The **/[NO]LBXAUTHENTICATE** and **/LBXDATA** qualifiers specify the authorization protocol used between the proxy server and the X display server.

For information about using and configuring an LBX proxy server or a proxy manager, see the DECwindows documentation.

## Specifying Named Properties (Alpha/Integrity servers Only)

Named property values are designed to store configuration information associated with the display device, such as the network address of a session manager. By using the **/VALUE** qualifier, you can set or modify one or more values associated with the display device.

See also the description of the [SHOW DISPLAY](#) command for more information.

## Specifying the Device Mode

By using one of the following qualifiers: **/EXECUTIVE\_MODE**, **/SUPERVISOR\_MODE**, or **/USER\_MODE**, you can specify the mode of the device you are creating. The default is the **/SUPERVISOR\_MODE** qualifier.

See also the description of the [SHOW DISPLAY](#) command for more information.

## Qualifiers

### **/CREATE**

Creates the workstation display device (WSA *n*:) on which a DECwindows application is displayed. You must specify the **/CREATE** qualifier the first time you use the **SET DISPLAY** command, but you need not respecify it if you continue to redirect output from applications to other workstations with subsequent **SET DISPLAY** commands.

When you specify the **/CREATE** qualifier without the **/NODE** qualifier, the workstation device defaults to the current node. Additionally, if you omit the **/TRANSPORT** qualifier, the transport defaults to either the value specified by the DECW\$SETDISPLAY\_DEFAULT\_TRANSPORT logical, if defined, or to DECNET.

### **/DELETE**

Cancels the redirected display by deassigning the logical name DECW\$DISPLAY and deleting the created display device. If you specified a logical name as the *display-device* parameter with the **SET DISPLAY/CREATE** command, entering the **SET DISPLAY/DELETE display-device** command cancels the redirected display by deassigning the logical name you specified and deleting the created display device.

The DECwindows Session Manager defines DECW\$DISPLAY in your job logical name table when you open a terminal (DECterm) window. When you redirect application output to another workstation with the **SET DISPLAY/CREATE** command, an additional DECW\$DISPLAY logical name is defined in your process logical name table. This definition supersedes the definition in the job logical name table. Output from applications run from the process in which you executed the **SET DISPLAY/CREATE** command will be displayed on the workstation referred to by the definition of DECW\$DISPLAY in the process logical name table. Enter the **SHOW DISPLAY** command to see where this application will be displayed. To see whether multiple definitions for DECW\$DISPLAY exist, enter the command **SHOW LOGICAL DECW\$DISPLAY**.

If DECW\$DISPLAY is still defined (for example, in the job logical name table) after you specify the **/DELETE** qualifier, any DECwindows applications run from this process will be displayed on the workstation device to which output is now directed. Enter the **SHOW DISPLAY** command if you are unsure of the node to which DECW\$DISPLAY refers.

---

### Caution

If you modify or delete the definition of DECW\$DISPLAY from the job logical name table, you will be unable to start another session. Be careful not to specify the **/DELETE** qualifier without having first redirected the display with the **SET DISPLAY/CREATE** command.

---

You cannot specify the **/DELETE** and **/CREATE** qualifiers on the same command line.

### **/EXECUTIVE\_MODE**

Creates an executive-mode device and assigns the logical name DECW\$DISPLAY to point to it. This qualifier must be used with the **/CREATE** qualifier. Devices created with the **/EXECUTIVE\_MODE** qualifier are deleted only in the following situations:

- They are explicitly deleted with the **/DELETE** qualifier.
- The system is rebooted.

To modify or delete executive-mode devices, you must have SYSNAM (system logical name) privilege.

### **/GENERATE[=(keyword[=value][,...]) (Alpha/Integrity servers only)**

Requires a trusted network connection to an X display server and the SECURITY extension must be enabled on that server.

Instructs the display device to connect to the X display server and generate anew authorization key (consisting of the authorization protocol name and a magic cookie). This authorization key is then stored in the X authority file currently in use. If you do not want to overwrite any previously existing keys for this display device, use the **/XAUTHORITY** qualifier to write the generated key to an alternate X authority file.

---

### **Note**

The MIT-KERBEROS-5 protocol does not currently support key generation, as defined by the SECURITY extension. Do not use the **/GENERATE** qualifier when connected to an X display server protected by Kerberos access control.

---

Each generated key follows the default settings unless otherwise specified. This means that, by default, each generated authorization key:

- Follows the MIT-MAGIC-COOKIE-1 protocol
- Grants an untrusted connection to the X server
- Is not associated with a particular application group
- Maintains a timeout period of 60 seconds before which it must be used (otherwise, it is automatically revoked)

Possible keyword values are as follows:

| Keyword   | Description                                                                                                                                                                                                                          |
|-----------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| TRUSTED   | Specifies that the key grant unrestricted access to the X server. This keyword permits a client application to perform all actions.                                                                                                  |
| UNTRUSTED | Specifies that the key grant restricted access to the X server. This keyword restricts client applications to a subset of X server extensions and prevents access to windows other than those created by the requesting application. |

| Keyword                 | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|-------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| TIMEOUT= <i>seconds</i> | Specifies the number of seconds after which the key is revoked automatically if not in use. The timeout period begins immediately, and refreshes once all connections using this key have closed.                                                                                                                                                                                                                                                            |
| NOTIMEOUT               | Specifies that the key has no expiration and must be explicitly revoked.                                                                                                                                                                                                                                                                                                                                                                                     |
| GROUP= <i>groupid</i>   | Specifies that the key is associated with a particular application group and is to be revoked if that group is deleted. Although the use of application groups is supported by DECwindows Motif via the XC-APPGROUP extension, DECwindows Motif does not currently supply any utilities or desktop applications to create these groups. To create an application group, you must use an X Window System application or utility external to DECwindows Motif. |
| PROTOCOL= <i>name</i>   | Specifies the protocol to be used to authenticate the key. Valid values are server dependent. For the DECwindows X display server, the only valid value for the <i>name</i> parameter is MIT-MAGIC-COOKIE-1. If you are connecting to a third-party X server, the names of any additional authorization protocols on that X server that support the SECURITY extension and key generation are also valid.                                                    |

The keyword sets **TRUSTED**/**UNTRUSTED** and **TIMEOUT**/**NOTIMEOUT** are mutually exclusive. Do not enter both values on the same command line.

**/LBXAUTHENTICATE=protocol-name** (Alpha/Integrity servers only)

**/NOLBXAUTHENTICATE** (Alpha/Integrity servers only)

Specifies the authorization protocol used to grant the LBX proxy server access to the X display server. This qualifier is used with the **/PROXY** and **/CREATE** qualifiers when creating an initial LBX proxy server connection. If a proxy server connection already exists, these qualifiers are ignored. If you do not specify **/LBXAUTHENTICATE**, the authorization protocol is obtained from the current X authority file. If you specify **/NOLBXAUTHENTICATE**, the proxy server defaults to the X authority file of the user who started the proxy manager application.

Valid values for the *protocol-name* parameter are MIT-MAGIC-COOKIE-1 and MIT-KERBEROS-5. If you supply a *protocol-name* value of MIT-MAGIC-COOKIE-1, you must also specify the value of the magic cookie using the **/LBXDATA** qualifier.

**/LBXDATA=value** (Alpha/Integrity servers only)

Specifies a data value for the authorization protocol used between the LBX proxy server and the X display server. This qualifier must be used with the **/LBXAUTHENTICATE**, **/PROXY**, and **/CREATE** qualifiers.

When you issue a

**SET DISPLAY/CREATE/PROXY/LBXAUTHENTICATE=MIT-MAGIC-COOKIE-1**  
command, use this qualifier to provide a hexadecimal magic cookie value to the MIT-MAGIC-COOKIE-1 protocol.

**/NODE=workstation\_display**

Defines the workstation on which you want to display DECwindows applications. The node name you provide cannot be a cluster alias (a name that represents multiple nodes configured in an OpenVMS Cluster), but must instead identify an actual node.

You must create a workstation display device with the **/CREATE** qualifier before you can redirect the output from applications to other workstations. Do not enter the **SET DISPLAY/NODE=workstation\_display** command without having previously specified the **/CREATE** qualifier.

When you specify the **/CREATE** qualifier without the **/NODE** qualifier, the workstation defaults to the current node.

Make sure that you are authorized to display applications on the workstation you specify. For more information about using the DECwindows Session Manager to authorize yourself to display applications from other nodes, see the DECwindows documentation.

Each node, both source and destination, must be defined in the other's network node database. For example, to display applications on node HUBBUB from ZEPHYR, HUBBUB must be entered in ZEPHYR's network node database, and ZEPHYR must be entered in HUBBUB's network node database. In addition, users on ZEPHYR must be authorized in the DECwindows Session Manager to display applications on HUBBUB. For information about entering nodes in a network node database, see the DECnet-Plus for OpenVMS documentation.

#### **/PMPORT=[port-number] (Alpha/Integrity servers only)**

Specifies the port number on which the proxy manager is listening. This qualifier is used with the **/PROXY** and **/CREATE** qualifiers. The default port is 6500.

#### **/PMTRANSPORT=transport-name (Alpha/Integrity servers only)**

Specifies the network transport used to connect to the proxy manager. This qualifier is used with the **/PROXY** and **/CREATE** qualifiers.

Valid values for the *transport-name* parameter are the same as those listed for the **/TRANSPORT** qualifier. If you do not specify a transport, then the network transport specified by the **/TRANSPORT** qualifier is used.

#### **/PROXY[=node] (Alpha/Integrity servers only)**

Specifies that a proxy manager application should be used to locate an LBX proxy server, which serves as an intermediary for processing client and server connections for a display device. Use an LBX proxy server when connecting to a remote node located over a low-bandwidth network connection, such as the Internet. The proxy manager should run on the local network. This qualifier is used with the **/CREATE** qualifier.

When you create a display device using the **SET DISPLAY/CREATE/PROXY** command, you can use that device to connect to an X display server exactly the same as you would with any other display device. The client connects to the LBX proxy server returned by the proxy manager, which in turn connects to the X display server.

The value of the **/PROXY** qualifier specifies the node on which the proxy manager is running. The proxy manager is responsible for starting or locating a proxy server to provide access to the X display server specified by the transport, node, and server values. The proxy manager returns the transport, node, and server values for the selected proxy server to the display device. If you do not specify a value for the *node* parameter, the default location is the current node.

The **/PMPORT** and **/PMTRANSPORT** qualifiers can be used to further specify the proxy manager's location.

**/QUOTA=(*quota-name=value[,...]*) (Alpha/Integrity servers only)**

Requires SYSPRV (system privilege) privilege or the DECW\$WS\_QUOTA rights identifier. If using an executive mode device, SYSNAM (system name) privilege is also required.

Modifies the value of the name count or data space quota associated with the display device. These quotas influence the amount of non-paged pool available for storing named properties.

Possible values for the *quota-name* parameter are as follows:

- **NAME\_COUNT** – The name count quota restricts the total number of named properties associated with the device. The default name count quota is the value of the DECW\$WS\_DEFAULT\_NAME\_COUNT logical, or 12 if the logical is not defined.
- **DATA\_SPACE** – The data space quota restricts the total amount of space available (in bytes) for storing property values. Note that this space includes some data overhead and may not total the exact length of the values. The default data space quota is the value of the DECW\$WS\_DEFAULT\_DATA\_SPACE logical, or 10752 if the logical is not defined.

**/REVOKE (Alpha/Integrity servers only)**

Requires a trusted network connection to an X display server and that the SECURITY extension be enabled on that server.

Revokes an authorization key created with the **/GENERATE** qualifier.

If you specify the **/REVOKE** qualifier, the revoke operation is performed before the other actions on the **SET DISPLAY** command. For example, you can use both the **/REVOKE** and **/GENERATE** qualifiers on the same command line, in any order, to revoke one key and generate another.

Do not use with the **/CREATE** qualifier.

**/SCREEN=*screen-number***

Defines the screen to be associated with this display device. In some hardware configurations, the system supports more than one screen. In such a configuration, you can specify the screen to which the application is directed.

**/SERVER=*server-number***

Defines the server to be associated with the display device indicated by the *display-device* parameter to the **SET DEVICE** command. Using the transport mechanism, the server passes data between the user and the application. In some hardware configurations, the system supports more than one server. In such a configuration, you can specify the server to which the application is directed.

On Alpha and Integrity server systems in LBX proxy server configurations, this qualifier specifies either an X display server or a standalone LBX proxy server. Standalone LBX proxy servers are not managed by the proxy manager and are manually assigned a server number on startup.

If you do not specify the *display-device* parameter, the **SET DISPLAY/SERVER** command associates the server with the display device indicated by the logical name DECW\$DISPLAY.

**/SUPERVISOR\_MODE (default)**

Creates a supervisor-mode device and assigns the logical name DECW\$DISPLAY to point to it. This qualifier must be used with the **/CREATE** qualifier. When the user logs out, the device is deleted.

**/TRANSPORT=transport-name**

Defines the transport mechanism, for example, DECnet or local, that passes information between the application and the workstation. The transport mechanism is used to send input from the user to the application and output from the application to the display device. In proxy manager configurations, the value specified for this qualifier also acts as a default value for the **/PMTRANSPORT** qualifier.

The *transport-name* parameter can be one of the following values:

- TCPIP or DECNET

Specifies the appropriate network transport for applications running and displaying on different nodes. You can specify the default transport value used with the **SET DISPLAY/CREATE** command by defining the DECW\$SETDISPLAY\_DEFAULT\_TRANSPORT logical in the job, process, or system table. The value of this logical is then used each time you enter the **SET DISPLAY/CREATE** command without the **/TRANSPORT** qualifier. If you specify neither the qualifier nor the logical, the value of DECNET is used as default.

- LOCAL

Optimizes the performance of applications running and displaying on the same node.

On Alpha and Integrity server systems, the valid set of values for the *transport-name* parameter is further determined by the DECwindows logical DECW\$IPV6\_SUPPORT. This logical specifies which Internet Protocol version is supported: IPv4 or IPv6. See the DECwindows Motif documentation for more information about the DECW\$IPV6\_SUPPORT logical and support for the IPv6 protocol.

When using a proxy manager on Alpha and Integrity server systems, this qualifier specifies the transport that the selected LBX proxy server should use to connect to the X server.

When using a standalone proxy server (specified by the **/SERVER** qualifier), this qualifier specifies the transport that the client should use to connect to the proxy server.

**/USER\_MODE**

Creates a user-mode display device and assigns the logical name DECW\$DISPLAY to point to it. This qualifier must be used with the **/CREATE** qualifier. The lifetime of a user-mode device is one DECwindows image: when the next DECwindows image exits, the device is deleted.

**/VALUE=(NAME=property-name,action[=data]) (Alpha/Integrity servers only)**

Sets, deletes, or modifies a named property value associated with the display device. Named property values are intended to store configuration information associated with the display device, such as the network address of a session manager.

Use the following options to specify the type of action to perform:

- DELETE – Deletes the specified property value.
- SET=data – Sets the specified property to the supplied value.
- APPEND=data – If the property exists, adds the supplied value to the end of list of values associated with the property. If the property does not exist, it is created and set to the supplied value.

Use the **SHOW DISPLAY/VALUES** command to display all existing named properties and their current values. Property names are restricted to 31 characters. Names that include a dollar sign (\$) are reserved by VSI for use with OpenVMS products and facilities. For example, names starting with the string DECW\$ are reserved for DECwindows Motif.

**/XAUTHORITY=[filespec] (Alpha/Integrity servers only)**

**/NOXAUTHORITY (Alpha/Integrity servers only)**

Directs the display device to use a specific X authority file when connecting the X display server. The X authority file contains data that grants or restricts access to the X display server depending on the authorization protocol in use. If a file specification is not entered with this qualifier, the default of SYS\$LOGIN:DECW\$XAUTHORITY.DECW\$XAUTH is used. If the file specification is entered and the file does not currently exist, it is created automatically when an entry is made into the file.

Note that with this qualifier, all X authority file specifications resolve to a physical device (rather than a logical device) in order to remain available to other detached processes. If you specify a search list, and the file is not found, the X authority file specification resolves to the first directory in the search list.

Use **/NOXAUTHORITY** to clear the setting and return to the file referenced by the DECW\$XAUTHORITY logical or the default file if the logical is not defined.

## Examples

```
1. $ SHOW DISPLAY
   Device:      WSA1:  [super]
   Node:        0
   Transport:   LOCAL
   Server:      0
   Screen:      0

$ SET DISPLAY/CREATE/NODE=ZEPHYR/EXECUTIVE_MODE
$ SHOW DISPLAY
   Device:      WSA2:  [exec]
   Node:        ZEPHYR
   Transport:   DECNET
   Server:      0
   Screen:      0
$ SPAWN/NOWAIT/INPUT=NL: RUN SYS$SYSTEM:DECW$CLOCK

$ SET DISPLAY/DELETE

$ SHOW DISPLAY
   Device:      WSA1:  [super]
   Node:        0
   Transport:   LOCAL
   Server:      0
   Screen:      0
```

In this example, you are logged in to your workstation (device WSA1:), here referred to as node 0. (0 is the standard shorthand notation for representing your node.) You want to run the DECwindows Clock on your workstation and display it on another workstation, ZEPHYR.

Assuming you are authorized to display applications on ZEPHYR, you redirect the application's output to ZEPHYR with the **SET DISPLAY** command. The device created on ZEPHYR is an

executive-mode device. You enter the **SHOW DISPLAY** command to verify the location of the redirected display. You then run `Clock`. When you finish running `Clock`, you disable the redirected display by entering the **SET DISPLAY/DELETE** command. Finally, you enter the **SHOW DISPLAY** command to verify that any applications subsequently run on your node will also be displayed there.

Note that a new workstation display device, `WSA2`, is created when you enter the **SET DISPLAY/CREATE** command. When you cancel the redirected display with the **SET DISPLAY/DELETE** command, application output is once again displayed on the workstation display device referred to by `WSA1`.

```
2. $ SET DISPLAY/CREATE/NODE=FLOPSY RABBIT
$ SHOW DISPLAY RABBIT

Device:    WSA2:    [super]
Node:      FLOPSY
Transport: DECNET
Server:    0
Screen:    0

$ RUN/DETACHED/OUTPUT=WSA2: SYS$SYSTEM:DECW$CLOCK

$ SET DISPLAY/CREATE/NODE=ZEPHYR ZNODE
$ SHOW DISPLAY ZNODE

Device:    WSA3:    [super]
Node:      ZEPHYR
Transport: DECNET
Server:    0
Screen:    0

$ RUN/DETACHED/OUTPUT=WSA3: SYS$SYSTEM:DECW$CALENDAR

$ RUN SYS$SYSTEM:DECW$BOOKREADER
$ SHOW DISPLAY

Device:    WSA1:    [super]
Node:      0
Transport: LOCAL
Server:    0
Screen:    0
```

In this example, you are logged in to your node (device `WSA1 :`), and want to direct the output from applications to several workstation displays in the same session. By specifying different logical names in the **SET DISPLAY** command, you can redirect the output without changing the logical name definition for `DECW$DISPLAY`. This allows you to display the output from most applications on your default display but occasionally display output on another workstation. You can also continue to run and display applications on your node. In this example, `Clock` is displayed on node `FLOPSY`, `Calendar` is displayed on node `ZEPHYR`, and `Book reader` is displayed on your workstation.

Note that to run your applications with the DCL command **RUN/DETACHED**, you must use the device name that equates to the logical display device name you specified in the **SET DISPLAY** command. Use the **SHOW DISPLAY** command to obtain this device name.

```
3. $ SET DISPLAY/CREATE/GENERATE=TRUSTED-
   _$ /XAUTHORITY=XAUTHORITY_TEMP/NODE=ZEPHYR
$ PIPE SHOW DISPLAY/EXTR | RSH FLOPSY "XAUTH NMERGE SYS$INPUT"
```

```
$ SET HOST FLOPSY
$ SET DISPLAY/NODE=ZEPHYR
$ RUN SYS$SYSTEM:DECW$CLOCK
```

In this example, you are logged into your workstation (WSA1 :) and want to run the DECwindows Clock application on a remote node (FLOPSY) and display it on another workstation (ZEPHYR). Both systems are using Magic Cookie authorization to control access to the X display server.

Assuming you are already authorized to connect to the server on node ZEPHYR, you create a display device that connects to ZEPHYR and generates a new authorization key. This key grants trusted connections to the server on ZEPHYR within 60 seconds of key generation. To restrict trusted access to the server, the key is stored in a new X authority file, XAUTHORITY\_TEMP.DECW\$XAUTH.

The authorization key is then extracted and copied to FLOPSY, and merged with other entries in your X authority file on that system. You then set host to node FLOPSY and set display to node ZEPHYR. When you run the clock application from FLOPSY, it connects to the server on ZEPHYR and is allowed access as specified by the generated authorization key.

- ```
4. $ SET DISPLAY/CREATE/VALUE=-
   _$ (NAME=DECW$SESSION_MANAGER,SET="tcpip/zephyr:9510")
   $ SHOW DISPLAY/SYMBOLS/ALL
      Device:      WSA23:  [super]
      Node:        0
      Transport:   DECNET
      Server:      0
      Screen:      0
      User-defined values:
        "DECW$SESSION_MANAGER" = "tcpip/zephyr:9510"
   $ SHOW SYMBOL DECW$DISPLAY__DECW$SESSION_MANAGER
      DECW$DISPLAY__DECW$SESSION_MANAGER == "tcpip/zephyr:9510"
   $ SET DISPLAY UNTRUSTED/CREATE/XAUTHORITY=TEMP/GENERATE-
   _$ /VALUE=(NAME=DECW$SESSION_MANAGER,-)
   _$ SET="'DECW$DISPLAY__DECW$SESSION_MANAGER' "
```

In this example, you create a display device, and set the DECW\$SESSION\_MANAGER property to the network address of a session manager on remote node ZEPHYR using port number 9510. The **SHOW DISPLAY/SYMBOLS** command then defines a DCL symbol for the port value. The symbol is then used to set the port value for a new display device.

- ```
5. $ SET DISPLAY/CREATE/PROXY=GATEWY/NODE=hubbub.company.com-
   _$ /PMTRANSPORT=DECNET/NOLBXAUTHENTICATE/TRANSPORT=TCPIP
   $ SHOW DISPLAY
      Device:      WSA23:  [super]
      Node:        HUBBUB.COMPANY.COM
      Transport:   TCPIP
      Server:      0
      Screen:      0
      Connection will use:
        LBX proxy on node:  gateway.company.com
        Transport to proxy: TCPIP
        Server number:      63
   $ RUN SYS$SYSTEM:DECW$CLOCK
```

In this example, you are logged into a local workstation (FLOPSY) and want to connect to an external host (hubbub.company.com), which is outside of your company's firewall. You use the proxy manager on a gateway host (GATEWY) to start the LBX proxy server, connect to the external host, and display the DECwindows Clock application.

Note that DECnet is used within the local area network (LAN) to communicate to the proxy manager, and TCP/IP is used by the proxy server to communicate to the X display server on the external host. When using a managed proxy server, the proxy server chooses the transport for the client-to-proxy server connection.

## SET ENTRY

**SET ENTRY** — Changes the current status or attributes of a job not currently executing in a queue. **Requires delete (D) access to the job or manage(M) access to the queue.**

### Format

**SET ENTRY** *entry-number*[,...]

### Parameter

*entry-number*[,...]

Specifies the entry number of the job you want to change. If you specify more than one entry, separate the entry numbers with commas (,).

The system assigns a unique entry number to each queued print or batch job in the system. By default, the **PRINT** and **SUBMIT** commands display the entry number when they successfully queue a job for processing. These commands also create or update the local symbol \$ENTRY to reflect the entry number of the most recently queued job. To find a job's entry number, enter the **SHOW ENTRY** or the **SHOW QUEUE** command.

### Description

The **SET ENTRY** command allows you to change the status or attributes of one or more jobs, as long as the jobs are not executing currently. You cannot affect individual files within a multifile job with the **SET ENTRY** command.

The qualifiers enable you to specify different attributes or delete attributes. Some qualifiers apply to both batch and print jobs. Others are restricted to either batch jobs or print jobs. The defaults for all the **SET ENTRY** qualifiers are the attributes and status that the job has before you enter the **SET ENTRY** command.

This command requires delete (D) access to the job, manage (M) access to the queue, or OPER (operator) privilege.

### Qualifiers

**/AFTER=***time*  
**/NOAFTER**

Requests that the specified job be held until after a specific time. If the specified time has already passed, the job is scheduled for processing.

You can specify either absolute time or a combination of absolute and delta times. For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\\_AND\\_TIME\\_SECT](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT)] or the online help topic Date.

## Note

Releasing or rescheduling a job before its submission time is not supported for security reasons. Therefore, if you set the system time to a future time and submit a job on anode where the queue manager is running, you cannot release or reschedule that job back to the present time if you reset the system time.

For example, you can set the system time to a future time of January 1, 2020 and submit a job to run on January 9, 2020; however, if you set the system time back to the present time and try to release the job to the present time, the job will be released to January 1, 2020.

This situation impacts the following qualifiers: **/AFTER**, **/NOHOLD**, and **/RELEASE**.

---

To specify **/AFTER** for a job on hold, you must also specify **/NOHOLD** in order to cause the job to be held only until the specified time. Jobs can be released before the specified time by using the **/NOAFTER** or **/RELEASE** qualifier with the **SET ENTRY** command.

## **/BURST**

## **/NOBURST**

Controls whether two file flag pages with a burst bar between them are printed preceding each file in a job.

Use the **/[NO]BURST** qualifier to override the **/DEFAULT** qualifier options that have been set for the output queue you are using. The **/[NO]BURST** qualifier does not override the **/SEPARATE** qualifier options set for the queue.

When you specify the **/BURST** qualifier for a file, the **/[NO]FLAG** qualifier does not add or subtract a flag page from the two flag pages that are printed preceding a file.

## **/CHARACTERISTICS=(characteristic[,...])**

## **/NOCHARACTERISTICS**

Specifies the name or number of one or more characteristics to be associated with the job. Characteristics can refer to such things as color of ink. If you specify only one characteristic, you can omit the parentheses.

A characteristic's number must range from 0 to 127. To see which characteristics have been defined for your system, use the **SHOW QUEUE/CHARACTERISTICS** command. To see which characteristics are associated with a particular queue, use the **SHOW QUEUE/FULL** command.

A print job can be processed on an execution queue if none, some, or all of the characteristics associated with the queue also are associated with the job. That is, the job's characteristics must be a subset of the queue's characteristics. However, if any of the characteristics associated with the job are not associated with the queue, the job remains pending until one or more of the following occurs:

- The characteristics specified with the queue are changed to make the job's characteristics a subset of the queue's characteristics (using, for example, the **SET QUEUE/CHARACTERISTICS** command).
- The characteristics specified with the job are changed to make the job's characteristics a subset of the queue's characteristics (using, for example, the **SET ENTRY/CHARACTERISTICS** command).
- The job is moved to a queue on which all the job's characteristics have been specified (using, for example, the **SET ENTRY/REQUEUE** command).

- The job is deleted (using, for example, the **DELETE/ENTRY** command).

**/CLI=*filename***

Specifies the name of a command language interpreter (CLI) to use in processing the batch job. The file name specifies that the CLI be SYSS\$SYSTEM:*filename*.EXE. If you do not specify the **/CLI** qualifier, the job is run by the CLI specified in the user authorization file (UAF), or whatever CLI was specified when the job was originally submitted to the queue.

**/COPIES=*n***

Specifies the number of copies to print. The value of *n* can be any number from 1 to 255. When you use the **/COPIES** qualifier with the **SET ENTRY** command, the number of copies can apply only to the entire print job. You cannot use this qualifier to specify different numbers of copies for individual files within a multifile job.

**/CPUTIME=*time***

Specifies a CPU time limit for the batch job. You can specify the *time* parameter as delta time, the value 0, INFINITE, or NONE. If the queue on which the job executes has a defined CPUMAXIMUM value, the smaller of the specified job and queue values is used. If the queue on which the job executes does not have a specified maximum CPU time limit, the smaller of the **SUBMIT** command and user authorization file (UAF) values is used. If the queue on which the job executes does not have a specified maximum CPU time limit and the UAF has a specified CPU time limit of NONE, either the value 0 or the keyword INFINITE allows unlimited CPU time. If you specify NONE, the specified queue or UAF value is used. CPU time values must be greater than or equal to the number specified by the system parameter PQL\_MCPULM.

For more information on specifying CPU time limits, see the "CPU Time Limit Specifications and Actions" table for the **INITIALIZE/QUEUE** command in the [VSI OpenVMS DCL Dictionary: A-M \[https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\\_119\]](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_119). For information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual \[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\\_AND\\_TIME\\_SECT\]](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) or the online help topic Date.

**/FEED****/NOFEED**

Controls whether form feeds are inserted into the print job when the printer reaches the bottom margin of the form in use. You can suppress this automatic form feed (without affecting any of the other carriage control functions that are in place) by using the **/NOFEED** qualifier.

When you use the **/FEED** qualifier with the **SET ENTRY** command, the qualifier applies to all files in the print job. You cannot use this qualifier to specify form feeds for individual files within a multifile job.

**/FLAG****/NOFLAG**

Controls whether a flag page is printed preceding each file in a print job. The flag page contains the name of the user submitting the job, the job entry number, and other information about the file being printed.

Use the **/[NO]FLAG** qualifier to override the installation-defined defaults that have been set for the output queue you are using or to override the qualifier specified in the **PRINT** command that queued the job.

**/FORM=form**

Specifies the name or number of the form to be associated with the print job. If you omit the **/FORM** qualifier, the default form for the execution queue is associated with the job.

Forms have attributes such as print image width and length or paper stock, which the print symbiont associates with a job when the job is processed. To see which forms have been defined for your system, use the **SHOW QUEUE/FORM** command. To find out which form is mounted currently on a particular queue and which form is specified as that queue's default form, use the **SHOW QUEUE/FULL** command.

The stock of the form associated with the job must match the stock of the form mounted on the execution queue on which you want the job to be processed. If the stocks do not match, the job remains pending until one or more of the following occurs:

- A form with the same stock as the job's form is mounted on the queue(using, for example, the **SET QUEUE/FORM\_MOUNTED** command).
- A form with the same stock as the queue's mounted form is specified with the job (using, for example, the **SET ENTRY/FORM** command).
- The job is moved to a queue on which the stock of the mounted form matches the stock of the job's form (using, for example, the **SET ENTRY/REQUEUE** command).
- The job is deleted (using, for example, the **DELETE/ENTRY** command).

**/HEADER****/NOHEADER**

Controls whether a heading line is printed at the top of each output page in a print job.

**/HOLD****/NOHOLD**

Controls whether the job is to be made available for processing or held for processing later. If you specify the **/HOLD** qualifier, the job is not released for processing until you enter **SET ENTRY/NOHOLD** or **SET ENTRY/RELEASE**.

You can use the **/NOHOLD** qualifier to release jobs that have been held for the following reasons:

- A job was submitted with the **/HOLD** qualifier.
- A completed job is being retained in a queue.
- A user-written symbiont has refused a job.

---

**Note**

Releasing or rescheduling a job before its submission time is not supported for security reasons. Therefore, if you set the system time to a future time and submit a job on anode where the queue manager is running, you cannot release or reschedule that job back to the present time if you reset the system time.

For example, you can set the system time to a future time of January 1, 2020 and submit a job to run on January 9, 2020; however, if you set the system time back to the present time and try to release the job to the present time, the job will be released to January 1, 2020.

This situation impacts the following qualifiers: **/AFTER**, **/NOHOLD**, and **/RELEASE**.

---

**/JOB\_COUNT=*n***

Requests that an entire print job be printed *n* times, where *n* is a decimal integer from 1 to 255. This qualifier overrides the **/JOB\_COUNT** qualifier with the **PRINT** command.

**/KEEP****/NOKEEP**

Controls whether the batch job log file is deleted after it is printed.

**/LOG\_FILE[=*filespec*]****/NOLOG\_FILE**

Creates a log file with the specified file specification. You can specify a different device name, as long as the process executing the batch job has access to the device on which the log file will reside. Logical names in the file specification are translated in the context of the process that executes the **SET ENTRY** command.

If you omit the **/LOG\_FILE** qualifier and specify the **/NAME** qualifier, the log file is written to a file having the same file name as that specified by the **/NAME** qualifier; the file type is .LOG. When you omit the **/LOG\_FILE** qualifier, the job-name value used with the **/NAME** qualifier must be a valid file name.

**/LOWERCASE****/NOLOWERCASE**

Indicates whether the print job must be printed on a printer that can print both uppercase and lowercase letters. The **/NOLOWERCASE** qualifier means that files can be printed on printers that print only uppercase letters. If all available printers can print both uppercase and lowercase letters, you do not need to specify the **/LOWERCASE** qualifier.

**/NAME=*job-name***

Names the job. The job name must be 1 to 39 alphanumeric characters. The **SHOW ENTRY** and **SHOW QUEUE** commands display the job name. For batch jobs, the job name is also used for the batch job log file. For print jobs, the job name is also used on the flag page of the printed output.

The default job name is the name of the first file in the job.

**/NOCHECKPOINT**

For a batch job, erases the value established by the most recently executed **SET RESTART\_VALUE** command. For a print job, clears the stored checkpoint so that the job will restart from the beginning.

**/NODELETE**

Cancels file deletion for a job that was submitted with the **/DELETE** qualifier. If you did not specify the **/DELETE** qualifier when the job was originally submitted to the queue, you cannot use the **SET ENTRY** command to establish file deletion at a later time. You cannot use the **/NODELETE** qualifier to cancel deletion of individual files in a multifile job.

**/NOTE=*string***

Specifies a message of up to 255 characters to appear on the flag page of the print job. Enclose messages containing lowercase letters, blanks, or other non alphanumeric characters (including spaces) in quotation marks (" ").

**/NOTIFY**  
**/NONOTIFY**

Controls whether a message notifies you when your job has been completed or aborted. Notification is sent to any terminal session on the same OpenVMS Cluster system to which you are logged in.

**/OPERATOR=*string***

Specifies a message string of up to 255 characters to be sent to the operator just before the print job begins to print. Enclose the message in quotation marks ( " ") if it contains spaces, special characters, or lowercase characters.

**/PAGES=(*lowlim*,*uplim*)**

Specifies the number of pages to print for the specified job. You can use the **/PAGES** qualifier to print portions of long files. By default, all pages of the file are printed. When you use the **/PAGES** qualifier with the **SET ENTRY** command, the qualifier can apply only to an entire job. You cannot use this qualifier to specify different numbers of pages to be printed for individual files within a multifile job.

The *lowlim* specifier refers to the first page of the file that you want to print. If you omit the *lowlim* specifier, the printing starts on the first page of the file.

The *uplim* specifier refers to the last page of the file that you want to print. When you want to print to the end of the file but do not know how many pages are in the file, use quotation marks ( " ") as the *uplim* specifier.

You can omit the parentheses when you specify only a value for the *uplim* specifier. For example, **/PAGES=10** prints the first 10 pages of the file; **/PAGES=( 5 , 10 )** prints pages 5 to 10; **/PAGES=( 5 , " " )** starts printing at page 5 and continues until the end of the file is reached.

**/PARAMETERS=(*parameter*[,...])**

Specifies from one to eight optional parameters to be passed to the job. Each parameter can have as many as 255 characters. If you specify only one parameter, you can omit the parentheses. To specify a parameter that contains any special characters or delimiters, enclose the parameter in quotation marks.

For batch jobs, the parameters define values to be equated to the symbols named P1 to P8 in each command procedure in the job. The symbols are local to the specified command procedures.

**/PASSALL**  
**/NOPASSALL**

Specifies whether the symbiont bypasses all formatting of the print job and sends the output QIO to the driver with format suppressed. All qualifiers affecting formatting, as well as the **/HEADER**, **/PAGES**, and **/PAGE\_SETUP** qualifiers, are ignored.

When you use the **/PASSALL** qualifier with the **SET ENTRY** command, the qualifier applies to the entire job. You cannot use this qualifier to specify PASSALL mode for individual files within a multifile job.

**/PRINTER[=*queue-name*]**  
**/NOPRINTER**

Queues the batch job log file for printing when the job is completed. The default output queue for the log file is SYSS\$PRINT. The **/PRINTER** qualifier allows you to specify an output queue. The **/NOPRINTER** qualifier assumes the **/KEEP** qualifier.

**/PRIORITY=*n***

Requires OPER (operator) or ALTPRI (alter priority) privilege to raise the priority above the value of the queue's maximum scheduling priority.

Specifies the job-scheduling priority of the job. The value of *n* is an integer in the range of 0 to 255, where 0 is the lowest priority and 255 is the highest.

The default value for the **/PRIORITY** qualifier is the value of the system parameter DEFQUEPRI. No privilege is needed to set the priority lower than the queue's maximum scheduling priority.

**/RAD=*n***

Specifies the RAD number on which the submitted batch job is to execute.

When a job is submitted to a batch queue that does not have a RAD setting, the job will execute using the RAD specified. If the batch queue has a RAD setting, the job will execute using the RAD specified on the queue.

RAD is supported on AlphaServer GS series systems and starting from OpenVMS Version 8.4, support is extended to NUMA capable Integrity servers.

**/RELEASE**

You can use the **/RELEASE** qualifier to release jobs that have been held for the following reasons:

- A job was submitted with the **/AFTER** qualifier.
- A job was submitted with the **/HOLD** qualifier.
- A completed job is being retained in a queue.
- A user-written symbiont has refused a job.

---

**Note**

Releasing or rescheduling a job before its submission time is not supported for security reasons. Therefore, if you set the system time to a future time and submit a job on a node where the queue manager is running, you cannot release or reschedule that job back to the present time if you reset the system time.

For example, you can set the system time to a future time of January 1, 2020 and submit a job to run on January 9, 2020; however, if you set the system time back to the present time and try to release the job to the present time, the job will be released to January 1, 2020.

This situation impacts the following qualifiers: **/AFTER**, **/NOHOLD**, and **/RELEASE**.

---

**/REQUEUE=*queue-name*[:]**

Requests that the job be moved from the original queue to the specified queue.

**/RESTART****/NORESTART**

Specifies whether a batch or print job is restarted after a system failure or a **STOP/QUEUE/REQUEUE** command.

***/RETAIN=option***

Specifies the circumstances under which you want your jobs to be retained in a queue. When a job is retained in the queue, you can issue the **SHOW QUEUE** command after the job completes to see the status of the job. Without job retention, no record of a job is left in a queue after a job completes.

Use the following options to specify job retention:

- **ALWAYS** – Holds the job in the queue regardless of the job's completion status.
- **DEFAULT** – Holds the job in the queue as specified by the queue's retention policy.
- **ERROR** – Holds the job in the queue only if the job completes unsuccessfully.
- **UNTIL=time-value** – Holds the job in the queue for the specified length of time, regardless of the job's completion status.

---

**Note**

You cannot specify a **/NORETAIN** qualifier with the **SET ENTRY** command (as system managers can with the commands **INITIALIZE/QUEUE**, **START/QUEUE**, and **SET QUEUE**); however, you can specify **/RETAIN=DEFAULT** with the **SET ENTRY** command. The default option holds the job in the queue as specified by the queue's retention policy. If the system manager has not specified retention for the queue, the job is not retained.

---

## How Job Retention Is Determined

Although you can specify job retention options for your own jobs, the job retention option you specify may be overridden by the job retention option of the queue on which your job executed. If you submit or print a job to a generic queue, the generic queue's job retention setting may also override the job retention option you specify. This section describes how job retention is determined.

An execution queue's job retention setting takes precedence over a generic queue's job retention setting; however, if the job's completion status does not match the job retention setting (if any) on the execution queue, then the generic queue's job retention setting attempts to control job retention. If the job's completion status does not match the job retention setting (if any) on the generic queue, then the user-specified job retention setting is used. Jobs submitted directly to execution queues are not affected by job retention settings on generic queues.

If the execution queue's retention setting applies, the job is retained on the execution queue. Likewise, if the generic queue's retention setting applies, the job is retained on the generic queue. If the user-specified setting applies, the job is retained in the queue to which it was submitted.

The following example illustrates how the queue manager determines job retention:

Suppose you submit a job to a generic queue and specify **/RETAIN=ALWAYS**, and the job completes successfully.

First, the queue manager compares the job's completion status to the execution queue's retention setting. Suppose the queue is set with **/RETAIN=ERROR** (retains only jobs that complete unsuccessfully). The job is not retained in the execution queue because the error condition was not met.

Second, the queue manager compares the job's completion status to the generic queue's retention setting. Suppose the generic queue has no retention setting. The queue manager's comparison again fails to retain the job.

Finally, the queue manager compares the job's completion status to the retention setting you specified for the job. This comparison reveals that the job should be retained. Because the user-specified setting leads the queue manager to retain the job, the job is held in the queue to which the job was submitted – in this case, the generic queue.

For more information on types of queues, see the **INITIALIZE/QUEUE** command in the [VSI OpenVMS DCL Dictionary: A-M](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_119) [https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\_119]. For more information on setting retention options for queues, see the **START/QUEUE** or **SET QUEUE** command, or the **INITIALIZE/QUEUE** command in the [VSI OpenVMS DCL Dictionary: A-M](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_119) [https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\_119].

## Timed Retention

Timed retention, which you specify using the **UNTIL=***time-value* option, allows you to retain a job in the queue only as long as you need it. This eliminates the need to delete the job from the queue later.

For example, the following command retains job 172 in the queue until 7:31 on April 19, when the job will automatically be deleted from the queue.

```
$ SET ENTRY/RETAIN=UNTIL=19-APR-2001:07:31:0.0 172
```

However, depending on the queue's job retention policy, the job might be retained indefinitely. The job retention policy set on the queue takes precedence over the user-specified job retention setting. Because system managers cannot specify timed job retention for a queue, any jobs retained as a result of a queue's setting are retained indefinitely.

If you specify the **/RETAIN=UNTIL=***time-value* option, you must supply a time value. The time value is first interpreted as a delta time, then as a combination time, and finally as absolute time. If you specify a delta time, the delta begins when the job completes. For example, if you specify **SET ENTRY/RETAIN=UNTIL="+3:00"**, the job will be retained for three hours after the job completes. For information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT].

### **/SETUP=***module*[,...]

Extracts the specified modules from the device control library (containing escape sequence modules for programmable printers) and copies the modules to the printer before each file in a print job is printed.

When you use the **/SETUP** qualifier with the **SET ENTRY** command, the qualifier applies to the entire print job. You cannot use this qualifier to specify different setup modules for individual files within a multifile job.

### **/SPACE**

### **/NOSPACE**

Controls whether the output of a print job is double-spaced. Specifying the **/NOSPACE** qualifier causes the output to be single-spaced. When you use the **/SPACE** qualifier with the **SET ENTRY**

command, the qualifier applies to the entire job. You cannot use this qualifier to specify different spacing for individual files within a multifile job.

**/TRAILER****/NOTRAILER**

Controls whether a trailer page is printed at the end of each file in a print job. The trailer page displays the entry number, as well as information about the user submitting the job and the files being printed.

When you use the **/TRAILER** qualifier with the **SET ENTRY** command, trailer pages are placed at the end of each file in a multifile job.

Use the **/[NO]TRAILER** qualifier to override the installation-defined defaults that have been set for the output queue you are using or the qualifier specified in the **PRINT** command that queued the job.

**/WSDEFAULT=*n***

Defines, for a batch job, a working set default, which is the default number of physical pages that the job can use.

If the queue on which the job executes has a nonzero default working set, the smaller of the specified job and queue values is used. If the queue on which the job executes has a working set default of zero, the smaller of the specified job value and the value established in the user authorization file (UAF) is used.

Specify the value of *n* as a number of 512-byte pagelets on Alpha. Note that the operating system rounds up this value to the nearest CPU-specific page so that the actual amount of physical memory allowed may be larger than the specified amount on Alpha. If you specify zero or NONE, the specified queue or UAF value is used. Working set default values must range between the numbers specified by the system parameters PQL\_MWSDEFAULT and WSMAX.

**/WSEXTENT=*n***

Defines, for the batch job, a working set extent, which is the maximum amount of physical memory that the job can use. The job uses the maximum amount of physical memory only when the system has excess free pages. If the queue on which the job executes has a nonzero working set extent, the smaller of the specified job and queue values is used. If the queue on which the job executes has a working set extent of zero, the smaller of the specified job value and the value established in the user authorization file (UAF) is used.

Specify the value of *n* as a number of 512-byte pagelets on Alpha. Note that the operating system rounds up this value to the nearest CPU-specific page so that the actual amount of physical memory allowed may be larger than the specified amount on Alpha. If you specify zero or NONE, the specified queue or UAF value is used. Working set extent values must range between the numbers specified by the system parameters PQL\_MWSEXTENT and WSMAX.

**/WSQUOTA=*n***

Defines, for the batch job, a working set quota, which is the amount of physical memory that the job is guaranteed. If the queue on which the job executes has a nonzero working set quota, the smaller of the specified job and queue values is used. If the queue on which the job executes has a working set quota of zero, the smaller of the specified job value or the value established in the user authorization file (UAF) is used.

Specify the value of *n* as a number of 512-byte pagelets on Alpha. Note that the operating system rounds up this value to the nearest CPU-specific page so that the actual amount of physical memory allowed may be larger than the specified amount on Alpha. If you specify zero or NONE, the specified queue or UAF value is used. Working set quota values must range between the numbers specified by the system parameters PQL\_MWSQUOTA and WSMAX.

## Examples

1. 

```
$ PRINT/HOLD    MYFILE.DAT
   Job MYFILE (queue SYS$PRINT, entry 112) holding
$ SET ENTRY 112/RELEASE/JOB_COUNT=3
```

The **PRINT** command in this example requests that the file MYFILE.DAT be queued to the system printer, but placed in a hold status. The **SET ENTRY** command releases the job for printing and requests that three copies of the job be printed.

2. 

```
$ SUBMIT CLIMATE
   Job CLIMATE (queue SYS$BATCH, entry 211) pending
$ SET ENTRY 211/HOLD/NAME=TEMP
```

The **SUBMIT** command in this example queues the command procedure CLIMATE.COM for processing as a batch job. The **SET ENTRY** command places the job in a hold state and changes the job name to TEMP, assuming that the job has not yet begun execution.

3. (wide)  

```
$ PRINT/FLAG=ALL/AFTER=20:00 MEMO.MEM, LETTER.MEM, REPORT.MEM/SPACE
   Job MEMO (queue SYS$PRINT, entry 172) holding until 20:00
$ SET ENTRY 172 /BURST/NOSPACE/HEADER
```

The **PRINT** command in this example requests that three files be printed after 8:00 P.M. on the default printer with flag pages preceding each file. It also requests that the file REPORT.MEM be double-spaced. Later a **SET ENTRY** command calls for a burst page at the beginning of each file and requests that all files in the job be single-spaced. This command also requests that headers be printed on each page of each file in the job.

4. 

```
$ SUBMIT/HOLD/QUEUE=ANYRADQ  TEST.COM
Job TEST (queue ANYRADQ, entry 23) holding

$ SET ENTRY 23 /RAD=1
$ SHOW ENTRY/FULL 23
Entry  Jobname      Username      Blocks  Status
-----
   23  TEST          SYSTEM              Holding
      On idle batch queue ANYRADQ
      Submitted 24-JUL-2001 14:19:37.44 /KEEP /NOPRINT /PRIORITY=100 /
RAD=0
      File: _$1$DKB200:[SWEENEY.CLIUTL]TEST.COM;1
```

In this example, TEST.COM is submitted to the queue ANYRADQ, and the **SET ENTRY** command is used to set the RAD to 1.

## SET FILE

**SET FILE** — Modifies the characteristics of one or more files. **See the qualifier descriptions for restrictions.**

## Format

**SET FILE** *filespec* [, ...]

## Parameter

*filespec* [, ...]

Specifies one or more files to be modified. If you specify more than one file, separate the file specifications with commas (.). The asterisk (\*) and the percent sign (%) wildcard characters are allowed.

## Description

The **SET FILE** command modifies a number of file characteristics.

## Qualifiers

**/ATTRIBUTE=(file-attribute[,...])**

Sets the attributes associated with a file. The following table lists possible keywords and the relationship to both ACP-QIO and OpenVMS RMS File attributes:

| Keyword              | ACP-QIO File Attribute <sup>1</sup> | OpenVMS RMS File Attribute <sup>2</sup> |
|----------------------|-------------------------------------|-----------------------------------------|
| ATTDATE= <i>date</i> | FAT\$C_ATTDATE                      | XAB\$Q_ATT                              |
| ACCDATE= <i>date</i> | FAT\$C_ACCDATE                      | XAB\$Q_ACC                              |
| BAKDATE= <i>date</i> | FAT\$C_BAKDATE                      | XAB\$Q_BDT                              |
| BKS: <i>value</i>    | FAT\$B_BKTSIZE= <i>byte</i>         | FAB\$B_BKS= <i>byte</i>                 |
| CBT                  | FH2\$V_CONTIGB, FHC<br>\$V_CONTIGB  | FAB\$V_CBT, XAB\$V_CBT                  |
| CREDATE= <i>date</i> | FAT\$C_CREDATE                      | XAB\$Q_CDT                              |
| DEQ: <i>value</i>    | FAT\$W_DEFEXT= <i>word</i>          | FAB\$W_DEQ= <i>word</i>                 |
| EBK: <i>value</i>    | FAT\$L_EFBLK= <i>longword</i>       | XAB\$L_EBK= <i>longword</i>             |
| EXPDATE= <i>date</i> | FAT\$C_EXPDATE                      | XAB\$Q_EDT                              |
| FFB: <i>value</i>    | FAT\$W_FFBYTE= <i>word</i>          | XAB\$W_FFB= <i>word</i>                 |
| FSZ: <i>value</i>    | FAT\$B_VFCSIZE= <i>byte</i>         | FAB\$B_FSZ= <i>byte</i>                 |
| GBC: <i>value</i>    | FAT\$W_GBC= <i>word</i>             | FAB\$W_GBC= <i>word</i>                 |
| HBK: <i>value</i>    | FAT\$L_HIBLK= <i>longword</i>       | XAB\$L_HBK= <i>longword</i>             |
| LRL: <i>value</i>    | FAT\$W_RSIZE= <i>word</i>           | XAB\$W_LRL= <i>word</i>                 |
| MODDATE= <i>date</i> | FAT\$C_MODDATE                      | XAB\$Q_MOD                              |
| MRS: <i>value</i>    | FAT\$W_MAXREC= <i>word</i>          | FAB\$W_MRS= <i>word</i>                 |
| ORG:IDX              | FAT\$V_FILEORG=FAT<br>\$C_INDEXED   | FAB\$B_ORG=FAB\$C_IDX                   |
| ORG:REL              | FAT\$V_FILEORG=FAT<br>\$C_RELATIVE  | FAB\$B_ORG=FAB\$C_REL                   |

| Keyword              | ACP-QIO File Attribute <sup>1</sup> | OpenVMS RMS File Attribute <sup>2</sup> |
|----------------------|-------------------------------------|-----------------------------------------|
| ORG:SEQ              | FAT\$V_FILEORG=FAT\$C_SEQUENTIAL    | FAB\$B_ORG=FAB\$C_SEQ                   |
| RAT:BLK              | FAT\$B_RATTRIB=FAT\$M_NOSPAN        | FAB\$B_RAT=FAB\$M_BLK                   |
| RAT:CR               | FAT\$B_RATTRIB=FAT\$M_IMPLIEDCC     | FAB\$B_RAT=FAB\$M_CR                    |
| RAT:FTN              | FAT\$B_RATTRIB=FAT\$M_FORTRANCC     | FAB\$B_RAT=FAB\$M_FTN                   |
| RAT:MSB              | FAT\$B_RATTRIB=FAT\$M_MSBVAR        | FAB\$B_RAT=FAB\$M_MSB                   |
| RAT:NONE             | FAT\$B_RATTRIB=0                    | FAB\$B_RAT=0                            |
| RAT:PRN              | FAT\$B_RATTRIB=FAT\$M_PRINTCC       | FAB\$B_RAT=FAB\$M_PRN                   |
| REVDATE= <i>date</i> | FAT\$C_REVDATE                      | XAB\$Q_RDT                              |
| RFM:FIX              | FAT\$V_RTYPE=FAT\$C_FIXED           | FAB\$B_RFM=FAB\$C_FIX                   |
| RFM:STM              | FAT\$V_RTYPE=FAT\$C_STREAM          | FAB\$B_RFM=FAB\$C_STM                   |
| RFM:STMCR            | FAT\$V_RTYPE=FAT\$C_STREAMCR        | FAB\$B_RFM=FAB\$C_STMCR                 |
| RFM:STMLF            | FAT\$V_RTYPE=FAT\$C_STREAMLF        | FAB\$B_RFM=FAB\$C_STMLF                 |
| RFM:UDF              | FAT\$V_RTYPE=FAT\$C_UNDEFINED       | FAB\$B_RFM=FAB\$C_UDF                   |
| RFM:VAR              | FAT\$V_RTYPE=FAT\$C_VARIABLE        | FAB\$B_RFM=FAB\$C_VAR                   |
| RFM:VFC              | FAT\$V_RTYPE=FAT\$C_VFC             | FAB\$B_RFM=FAB\$C_VFC                   |
| VRS: <i>value</i>    | FAT\$W_VERSIONS= <i>word</i>        | XAB\$W_VERLIMIT= <i>word</i>            |

<sup>1</sup>For further information, see the [VSI OpenVMS I/O User's Reference Manual](https://docs.vmssoftware.com/vsi-openvms-io-user-s-reference-manual/) [https://docs.vmssoftware.com/vsi-openvms-io-user-s-reference-manual/].

<sup>2</sup>For further information, see the [VSI OpenVMS Record Management Services Reference Manual](https://docs.vmssoftware.com/vsi-openvms-record-management-services-reference-manual/) [https://docs.vmssoftware.com/vsi-openvms-record-management-services-reference-manual/].

## **/BACKUP** **/NOBACKUP**

Specifies that the Backup utility (BACKUP) records the contents of the file. The **/NOBACKUP** qualifier causes BACKUP to record the attributes of the file but not its contents. This qualifier is valid only for Files-11 Structure On-Disk Level 2 and 5 files.

The **/NOBACKUP** qualifier is useful for saving files that contain unimportant data, such as SWAPFILES.

## **/BEFORE[=*time*]**

Selects only those files dated prior to the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: BOOT, LOGIN,

TODAY (default), TOMORROW, or YESTERDAY. Specify the **/CREATED** or the **/MODIFIED** qualifier to indicate the time attribute to be used as the basis for selection. The **/CREATED** qualifier is the default.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic Date.

#### **/BY\_OWNER[=*uic*]**

Selects only those files whose owner user identification code (UIC) matches the specified owner UIC. The default UIC is that of the current process.

Specify the UIC by using standard UIC format as described in the relevant section in the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC_SECTION) [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC\_SECTION].

#### **/CACHING\_ATTRIBUTE=*keyword***

Use this qualifier to control which files are cached by the Extended File Cache. It sets the caching attribute for a file or directory in a Files-11 ODS-2 or ODS-5 volume.

The caching attribute of a file is the default caching option that is used by the Extended File Cache when an application accesses the file without specifying which caching option it wants to use.

The *keyword* can be either **WRITETHROUGH** or **NO\_CACHING**. Use **WRITETHROUGH** for files that you want to be cached. Use **NO\_CACHING** for files that you don't want to be cached.

The Extended File Cache does not cache directories. The caching attribute of a directory controls only how the caching attribute is inherited by new files and subdirectories created in the directory:

- When you create a new directory or file, it inherits its caching attribute from its parent directory.
- When you create a new version of an existing file, the new file inherits its caching attribute from the highest version of the existing file.

When you use the **INITIALIZE** command to create a new Files-11 volume, the caching attribute of its root directory (000000.DIR;1) is set to write-through. This means that by default, all the files and directories you create in the volume will inherit a caching attribute of write-through unless you use **SET FILE/CACHING\_ATTRIBUTE**.

When you change the caching attribute of a directory, it does not affect the caching attribute of any existing files and subdirectories in the directory.

When you change the caching attribute of a file, it does not affect the type of caching being used by any applications that are currently accessing the file.

#### **/CONFIRM**

##### **/NOCONFIRM (default)**

Controls whether a request is issued before each **SET FILE** operation to confirm that the operation should be performed on that file. The following responses are valid:

YES            NO            QUIT

|               |       |               |
|---------------|-------|---------------|
| TRUE          | FALSE | <b>Ctrl/Z</b> |
| 1             | 0     | ALL           |
| <b>Return</b> |       |               |

You can use any combination of uppercase and lowercase letters for word responses. Word responses can be abbreviated to one or more letters (for example, T, TR, or TRU for TRUE), but these abbreviations must be unique. Affirmative answers are YES, TRUE, and 1. Negative answers include: NO, FALSE, 0, and pressing **Return**. Entering QUIT or pressing **Ctrl/Z** indicates that you want to stop processing the command at that point. When you respond by entering ALL, the command continues to process, but no further prompts are given. If you type a response other than one of those in the list, DCL issues an error message and redisplay the prompt.

### **/CREATED (default)**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/CREATED** qualifier selects files based on their dates of creation. This qualifier is incompatible with the **/MODIFIED** qualifier, which also allows you to select files according to time attributes. The **/CREATED** qualifier is the default qualifier.

### **/DATA\_CHECK=[([NO]READ,[NO]WRITE)]**

Specifies whether a read data check (rereading each record), a write data check (reading each record after it is written), or a combination of the two is performed on the file during transfers. By default, a write data check is performed.

### **/END\_OF\_FILE**

Resets the end-of-file (EOF) mark to the highest block allocated.

### **/ENTER=new-filespec**

The *new-filespec* parameter is used to create either an alias or a hard link for the file specified in the **SET FILE** command. For detailed information about using hard links and aliases, see the relevant section in the [VSI OpenVMS System Manager's Manual \[https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#HARD\\_LINKS\]](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#HARD_LINKS).

Normally you would use **/ENTER** to create an alias or a hard link in a directory different from the one where the original file name resides. If the names are not in different directories, you or another user could subsequently lose data during a delete or purge operation. The **DELETE** and **PURGE** commands and the file version limit feature can behave unpredictably if the original name and the new name are in the same directory.

To remove an alias or hard link, use the **SET FILE/REMOVE** command. Exercise caution when using the **DELETE** and **SET FILE/REMOVE** commands, or you could end up with either an inaccessible file that has no name or a name that does not refer to a file. Follow these guidelines to avoid such problems:

- Use **SET FILE/REMOVE** to remove an alias; do not use the **DELETE** command to remove an alias.
- Do not use **SET FILE/REMOVE** to remove the original file name.

If you do not follow these guidelines and encounter problems, use **ANALYZE/DISK/REPAIR** to move inaccessible files to the SYSLOST directory and remove names that no longer refer to files.

**/ERASE\_ON\_DELETE**

Specifies that the specified files are erased from the disk (not just written over) when the **DELETE** or **PURGE** command is issued for the files. See the **DELETE/ERASE** command in the [VSI OpenVMS DCL Dictionary: A–M](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_61) [https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\_61] for more information.

**/EXCLUDE=(filespec[,...])**

Excludes the specified file from the **SET FILE** operation. You can include a directory name but not a device name in the file specifications. The asterisk (\*) and the percent sign (%) wildcard characters are allowed in the file specification; however, you cannot use relative version numbers to exclude a specific version. If you specify only one file, you can omit the parentheses.

**/EXPIRATION\_DATE=date****/NOEXPIRATION\_DATE**

Requires read (R), write (W), and control access. Being the owner of the file is one way to get control access.

Controls whether an expiration date is assigned to the specified files.

Specify the date according to the rules described in the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic Date. Absolute date keywords are allowed. If you specify zero as the date, today's date is used.

**/EXTENSION[=n]**

Sets the extend quantity default for the file. The value of the parameter *n* can range from 0 to 65,535. If you omit the value specification or specify a value of 0, OpenVMS Record Management Services (OpenVMS RMS) calculates its own value for the **/EXTENSION** qualifier.

See the [SET RMS\\_DEFAULT](#) command for a description of the **/EXTEND\_QUANTITY** qualifier.

**/GLOBAL\_BUFFER[=keyword[=n]]****/NOGLOBAL\_BUFFER**

For OpenVMS versions prior to Version 8.3, sets the OpenVMS Record Management Services (OpenVMS RMS) global buffer count (the number of buffers that can be shared by processes accessing the file) for the specified files. The value *n* must be an integer in the range from 0 to 32,767. A value of 0 disables buffer sharing.

The **/SHARE** qualifier can be used to enable or disable global buffers on a file currently being accessed; however, any new global buffer settings will only be applied to new accessors of the file. If a file is already open with global buffers, any new number of global buffers will not take effect until the file is closed by all accessors of the file.

For OpenVMS V8.3 and later, sets the OpenVMS RMS global buffer count for the specified files. Note, you can specify only one type of global buffer qualifier in the same command string.

The *keyword* can be:

- **COUNT=n** – The value *n* sets the longword count of the number of global buffers. For indexed files, this keyword allows you to exceed the traditional maximum of 32767. For other files, the maximum of 32767 still applies.

- **PERCENT=*p*** – The value *p* expresses the size of the global cache as a percentage of the total number of used blocks currently used in the file.
- **DEFAULT** – Requests RMS at runtime to recalculate the global cache size based on an algorithm that makes use of two global buffer SYSGEN parameters, **GB\_CACHEALLMAX** and **GB\_DEFPERCENT**.

The following qualifiers can also be used with the **/SHARE** qualifier:

- **/GLOBAL\_BUFFER=*n***
- **/GLOBAL\_BUFFER=COUNT=*n***
- **/GLOBAL\_BUFFER=PERCENT=*n***
- **/GLOBAL\_BUFFER=DEFAULT**
- **/NOGLOBAL\_BUFFER**
- **/[NO]STATISTICS**

## **/LOG**

### **/NOLOG (default)**

Displays the file specification of each file modified as the command executes.

## **/MODIFIED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/MODIFIED** qualifier selects files according to the dates on which they were last modified. This qualifier is incompatible with the **/CREATED** qualifier, which also allows you to select files according to time attributes. If you do not specify the **/MODIFIED** qualifier, the default is the **/CREATED** qualifier.

## **/MOVE**

### **/NOMOVE**

Controls whether movefile operations are enabled on the specified file.

When you create a file, movefile operations are enabled on that file. You should disable movefile operations on specialized files that are accessed other than through the XQP (such as files accessed through logical I/O to a disk).

Note that movefile operations are automatically disabled on critical system files. Do not enable movefile operations on these files.

## **/NODIRECTORY**

Use with extreme caution. Requires SYSPRV (system privilege).

Removes the directory attributes of a file and allows you to delete the corrupted directory file even if other files are contained in the directory. When you delete a corrupted directory file, the files contained within it are lost.

Use **ANALYZE/DISK\_STRUCTURE/REPAIR** to place the lost files in [SYSLOST]. You can then copy the lost files to a new directory. This qualifier is valid only for Files-11 On-Disk Structure Level 2 files. For more information about the Verify utility, see the relevant section

in the *VSI OpenVMS System Management Utilities Reference Manual, Volume 1: A-L* [[https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-i-a-l/#\\_1\\_ERRORREPORTINGANDREPAIR](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-i-a-l/#_1_ERRORREPORTINGANDREPAIR)].

### **/OWNER\_UIC[=*uic*]**

This qualifier has been superseded by the **SET SECURITY/OWNER** command.

### **/PROTECTION[=(*ownership[:access][,...]*)]**

This command has been superseded by the **SET SECURITY/PROTECTION** command.

### **/REMOVE**

Use with caution.

Enables you to remove one of the names of a file that has more than one name, without deleting the file. If you have created an additional name for a file with the **/ENTER** qualifier of **SET FILE**, you can use the **/REMOVE** qualifier to remove either the original name or the alias. The file still exists and can be accessed by whatever name or names remain in effect.

However, if you accidentally remove the name of a file that has only one name, you cannot access that file with most DCL commands; use the **ANALYZE/DISK\_STRUCTURE** utility to retrieve the file.

When **SET FILE/REMOVE** is executed on a symbolic link, the link is not removed. No error is displayed.

### **/SEMANTICS=*semantics-tag***

### **/NOSEMANTICS**

Use the **/SEMANTICS** qualifier to create or change a semantics tag. Use the **/NOSEMANTICS** qualifier to remove a semantics tag from a file. For more information, see the *Guide to OpenVMS File Applications* [<https://docs.vmssoftware.com/guide-to-openvms-file-applications/>] [<https://docs.vmssoftware.com/guide-to-openvms-file-applications/>].

### **/SHARE**

Allows you to enable or disable global buffers or statistics on a file currently being accessed by other users.

Requires SYSPRV privilege.

Only new accessors of the file acquire the new settings. For example, if a file is opened with no global buffers specified and the **SET FILE/GLOBAL=*n*/SHARE** command is issued, only new accessors of the file will use global buffers. If **/STATISTICS** is enabled on an active file, only operations performed by new accessors of the file are measured.

If a file is already open with global buffers, any new number of global buffers will not take effect until the file is closed by all accessors of the file.

The **/SHARE** qualifier is valid only with the following qualifiers:

- **/[NO]GLOBAL\_BUFFER=*n***
- **/[NO]STATISTICS**

**/SHELVBABLE**  
**/NOSHELVBABLE**

Controls whether the file is shelvable.

**/SINCE[=*time*]**

Selects only those files dated on or after the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: **BOOT**, **JOB\_LOGIN**, **LOGIN**, **TODAY** (default), **TOMORROW**, or **YESTERDAY**. Specify the **/CREATED** or the **/MODIFIED** qualifier to indicate the time attribute to be used as the basis for selection. The **/CREATED** qualifier is the default.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic **Date**.

**/STATISTICS**  
**/NOSTATISTICS (default)**

Enables the gathering of RMS statistics on the specified file. These statistics can then be viewed by using the Monitor utility, which is invoked with the DCL command **MONITOR**. The **SET FILE/STATISTICS** command applies an application ACE to the specified file. The ACE does not affect access control and is only meaningful to the application assigning it.

The **/SHARE** qualifier can be used to enable or disable statistics on a file currently being accessed. However, only statistics of new accessors of the file will be measured.

**/STYLE=*keyword***

Specifies the file name format for display purposes.

The valid keywords for this qualifier are **CONDENSED** and **EXPANDED**. Descriptions are as follows:

| Keyword             | Description                                                                                                                                                                           |
|---------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CONDENSED (default) | Displays the file name representation of what is generated to fit into a 255-length character string. This file name may contain a DID or FID abbreviation in the file specification. |
| EXPANDED            | Displays the file name representation of what is stored on disk. This file name does not contain any DID or FID abbreviations.                                                        |

The keywords **CONDENSED** and **EXPANDED** are mutually exclusive. This qualifier specifies which file name format is displayed in the output message, along with the confirmation if requested.

File errors are displayed with the **CONDENSED** file specification unless the **EXPANDED** keyword is specified.

See the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE_ACCESS) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE\_ACCESS] for more information.

**/SYMLINK=*keyword***  
**/NOSYMLINK (default)**

If an input file is a symbolic link, the file referred to by the symbolic link is the file that is set.

The **/SYMLINK** qualifier indicates that the symbolic link itself is set.

The valid keywords for this qualifier are [NO]WILDCARD, [NO]ELLIPSIS, and [NO]TARGET. Descriptions are as follows:

| Keyword    | Description                                                                                                   |
|------------|---------------------------------------------------------------------------------------------------------------|
| NOWILDCARD | Indicates that symlinks are disabled during directory wildcard searches.                                      |
| WILDCARD   | Indicates that symlinks are enabled during wildcard searches.                                                 |
| NOELLIPSIS | Indicates that symlinks are matched for all wildcard fields except for ellipsis.                              |
| ELLIPSIS   | Equivalent to WILDCARD (included for command symmetry).                                                       |
| TARGET     | Indicates that if the named file is a symlink, then the symlink is followed to operate on the symlink target. |
| NOTARGET   | Indicates that the command operates on the named file whether it is an ordinary file or a symlink.            |

If the file named in the **SET FILE** command is a symlink, the command by default operates on the symlink target.

## **/TRUNCATE**

Truncates the file at the end of the block containing the end-of-file (EOF) marker, that is, the qualifier releases allocated but unused blocks of the file.

## **/UNLOCK**

Clears a file marked as deaccess locked. Deaccess locking is required by and used by those few applications that maintain their own locking and consistency, typically without the use of the OpenVMS distributed lock manager, and potentially also without the use of RMS. When an application using deaccess locking does not correctly deaccess the file (often due to an application or system failure), the file is marked as locked, and is thus inaccessible until the integrity of the contents of the file are verified and the **SET FILE/UNLOCK** command is used.

This command does not affect the state of files that are locked using RMS or the distributed lock manager.

For details on file deaccess locking, see the [VSI OpenVMS I/O User's Reference Manual \[https://docs.vmssoftware.com/vsi-openvms-io-user-s-reference-manual/\]](https://docs.vmssoftware.com/vsi-openvms-io-user-s-reference-manual/), the ACP-QIO interface documentation, and specifically the FIB\$V\_DLOCK option available on the IO\$\_CREATE and IO\$\_ACCESS functions.

The **SET FILE/UNLOCK** command can clear the cause of the following error message:

```
%SYSTEM-W-FILELOCKED, file is deaccess locked
```

However, this command cannot resolve the cause of the error message:

```
%RMS-W-FLK, file currently locked by another user
```

## **/VERSION\_LIMIT[=n]**

Sets the maximum number of versions that a specified file can have in a directory. If you do not set a version limit, a value of 0 is used, indicating that the number of file versions is limited only to the Files-11 architectural limit of 32,767. When creating a file, if the total number of versions of that

file name exceeds the specified version limit, then the file with the lowest version number is deleted from the directory without notification to the user.

If you set the version limit to 3 when there are already five versions of that file in a directory, there will continue to be five versions of that file unless you specifically delete some or purge the directory. Once the number of file versions is equal to or less than the current version limit, this version limit is maintained.

The version limit applies to all existing versions of a specified file in a directory regardless of whether or not you specified any version in the command.

To view the version limit on a file, use the **DIRECTORY/FULL** command on a file name and look at the File Attributes field of the output or use the `F$FILE_ATTRIBUTES(filename,"VERLIMIT")` lexical function.

## Examples

1. `$ SET FILE/EXPIRATION_DATE=19-DEC-2001:11:00 BATCH.COM;3`

The **SET FILE** command requests that the expiration date of the file `BATCH.COM;3` be set to 11:00 A.M., December 19, 2001.

2. `$ SET FILE/BEFORE=31-DEC/ERASE_ON_DELETE PERSONNEL*.SAL`

This **SET FILE** command calls for all files that match the file specification `PERSONNEL*.SAL` and are dated before December 31 of the current year to have their disk locations erased whenever one of them is deleted with commands such as **DELETE** or **PURGE**.

3. `$ SET FILE/OWNER_UIC=[360,020]/VERSION_LIMIT=100 MYFILE.DAT`

The **SET FILE** command modifies the characteristics of the file `MYFILE.DAT`, changing the owner user identification code (\*). You must have system privilege (SYSPRV) to change the owner UIC.

4. `$ SET FILE/NOMOVE TEST.FDL`  
`$ DIRECTORY/FULL TEST.FDL`

```
Directory SYS$SYSDEVICE:[BERGMANN]
```

```
TEST.FDL;1    File ID:  (10,8,0)
```

```
 .
 .
 .
```

```
File attributes: Allocation: s, Extend: 0, Global buffer count: 0
                  No version limit, MoveFile disabled
```

```
 .
 .
 .
```

Movefile operations are disabled on the file `TEST.FDL`. A **DIRECTORY/FULL** command on the file `TEST.FDL` affirms that the file attribute Movefile is disabled.

5. `$ SET FILE/ATTRIBUTES=ORG:SEQ -`  
`_ $ TEST$:[DATA]SET_ATTRIBUTES.DATA_FILE/LOG`  
`%SET-I-MODIFIED, TEST$:[DATA]SET_ATTRIBUTES.DATA_FILE;1 MODIFIED`

The command, **SET FILE/ATTRIBUTES**, changes the file organization of the specified file.

6. \$ SET FILE/PROTECTION=(S:RWE,O=RWE,G:RE,W:RE) TEMP.DIR  
\$ DIRECTORY/PROTECTION TEMP.DIR

Directory DKB0:[FULGHUM]

TEMP.DIR;1 (RWE,RWE,RE,RE)

This example sets the protection on the TEMP.DIR file with the **SET FILE** command and then displays the protection of the file with the **DIRECTORY** command.

7. \$ SET FILE/SHARE/GLOBAL\_BUFFER=5000/STATISTICS INVENTORY.IDX

This example sets 5000 global buffers on the INVENTORY.IDX file and enables statistics. If the file is open and the **SET FILE** command is issued without the **/SHARE** qualifier, the following error is returned: SYSTEM-W-ACCONFLICT (file access conflict). The **/SHARE** qualifier allows the global buffers and statistics to be enabled on an open file; however, these settings only apply to new accessors of the file.

8. \$ SET FILE/GLOBAL\_BUFFER=100 NEWFILE.DAT  
\$ SET FILE/GLOBAL\_BUFFER=COUNT=100000 NEWFILE.DAT

In a clustered environment with mixed OpenVMS versions, the same file can be opened on different nodes with different global buffer counts. For nodes prior to Version 8.3, use the old compatibility setting, and for Version 8.3 nodes and later use the new values.

9. \$ dir NEWFILE.TXT

Directory WORK:[DOCUMENTS]

NEWFILE.TXT;3  
NEWFILE.TXT;2  
NEWFILE.TXT;1

\$ set file/version\_limit=10/log NEWFILE.TXT;  
%SET-I-MODIFIED, WORK:[DOCUMENTS]NEWFILE.TXT;3 modified

This example sets the version limit of 10 on all three existing versions of NEWFILE.TXT. Note that in this case, the **/LOG** qualifier shows only the highest version file specification as modified though the version limit has been applied to all file versions.

## SET HOST

**SET HOST** — Connects your terminal (through the current host processor) to another processor, called the remote processor.

### Format

**SET HOST** *node-name*

### Parameter

*node-name*

Specifies the node name of the remote processor to which you will connect.

## Description

The **SET HOST** command connects you to another processor on a network. The command requires that:

- You must have an account on the remote system to log in.
- The **NETMBX** (network mailbox) privilege is set.

(The **SHOW NETWORK** command lists the names of nodes accessible to your node.) Once the connection is made, the remote processor prompts for a user name and password. You must have an account on the remote processor to log in.

Once you have connected to the remote processor and have logged in, you can use DCL commands just as you would on your local processor. You can even use the **SET HOST** command to connect to another remote processor.

For example, if your local node is **BOSTON**, you can use the command **SET HOST ALBANY** to connect to the node **ALBANY**. You can then use the command **SET HOST AKRON** to connect (still through **BOSTON** and **ALBANY**) to the node **AKRON**.

Use the **LOGOUT** command to log out of the last processor you have logged into and return to the previous processor. For example, when you use the **LOGOUT** command, you have logged out of (and disconnected from) the processor at node **AKRON**, but you are still logged in (and connected) to the processor at **ALBANY**. A second **LOGOUT** command logs you out of node **ALBANY**, and disconnects you from it. A third **LOGOUT** command logs you out of the local processor, **BOSTON**.

You can also abort operations and return directly to the original host processor, if necessary. Press **Ctrl/Y** at least two times in rapid succession. the following message is displayed:

```
Are you repeating ^Y to abort the remote session?
```

If you respond **Y** or **YES**, control returns to the original node. Other responses, such as **N** or **NO**, do not abort the connection. This technique is useful when you want to exit quickly without entering a series of **LOGOUT** commands, or when part of the network becomes disconnected and you want to return to the host.

Note that **SET HOST**, unlike the OpenVMS terminal driver, buffers output data from an executing program. Buffering improves performance in wide-area networks; however, in the case of programs providing output *only*, the buffering causes a discrepancy between what is happening in the remote program and what is displayed on the local terminal. That is, a program might finish executing before you see the output on the local terminal.

This discrepancy can be particularly confusing when you use the **Ctrl/Y** or the **Ctrl/C** function, or out-of-band abort characters to abort the execution of a program. For example, when you press **Ctrl/Y** or **Ctrl/C** (or enter out-of-band abort characters) during the execution of a captive command procedure, **SET HOST** immediately stops the display on the local terminal. It also aborts the current read and write operations and any pending write operations, *including all buffered write operations*. Therefore, although it seems that the remote program aborts at the point in the program at which the display on the local terminal is stopped, the program might have executed beyond that point already – and might have finished executing – before you pressed **Ctrl/Y**.

Note that several **SET HOST** qualifiers, such as **/MOP**, **/VTP**, and **/X29**, are available only if DECnet-Plus is installed on your system. For information about using these qualifiers, type the following command:

```
$ HELP DECnet-Plus
```

## Qualifiers

### **/APPLICATION\_PROTOCOL[=*protocol*]**

Specifies the protocol connection, CTERM (CTDRIVER) or RTERM (RTTDRIVER) on the specified node. CTERM protocol is the default if no connection is specified.

### **/BUFFER\_SIZE=*n***

Changes the packet size of the protocol message sent between the terminal and the remote processor if a connection to the remote processor is already established. The default buffer size is 1010 bytes; however, the buffer size *n* can range from 140 bytes to 1024 bytes. The value of the parameter *n* is reset to 140 bytes if a value below 140 is specified; a value for *n* above 1024 bytes is reset to 1024.

You can force the host node to write to the terminal in smaller packets, thereby ensuring that write operations to the terminal are displayed at more frequent intervals, by setting *n* to a value just above the minimum of 140 bytes. On slow DECnet links, setting the buffer size to a smaller value may decrease pauses between write operations when large amounts of data are being scrolled to the screen.

### **/LOG[=*filespec*]**

#### **/NOLOG (default)**

Controls whether a log file of the entire session is kept. If you use the **/LOG** qualifier without the file specification, the log information is stored in the file SETHOST.LOG.

### **/RESTORE**

#### **/NORESTORE (default)**

Saves current terminal characteristics before a remote terminal session is begun and restores them when the remote session is terminated.

## Examples

1. 

```
$ SET HOST/APPLICATION_PROTOCOL=CTERM DAKOTA
```

The **/APPLICATION\_PROTOCOL** qualifier specifies the CTERM protocol (the default) on node DAKOTA in this command line.

2. 

```
$ SET HOST ITALIC
Username: GRESO
Password: <PASSWORD>
Welcome to OpenVMS VAX Version 7.3 on node ITALIC
.
.
.
$ LOGOUT
GRESO logged out at 19-DEC-2001 15:04:25.27
%REM-S-END, Control returned to node _CASLON::
```

In this example, the name of the local node is CASLON. This **SET HOST** command connects the user terminal to the processor at the network node named ITALIC. The remote processor

then prompts for user name and password. Use the normal login procedure to log in to the remote processor.

Once you are logged in at a remote node, you can use the **SET HOST** command to establish communication with another node. After logging in to node *ITALIC*, you could type **SET HOST BODONI**.

You would again be prompted for a user name and password. If you then supply a valid user name and password, you will be logged in to node *BODONI*.

Note that when you log out of node *BODONI*, control is returned to node *ITALIC*. You must log out of node *ITALIC* to return to your local node, *CASLON*.

```
3. $ SET TERMINAL/WIDTH=80
$ SET HOST/RESTORE GENEVA
Username: Jones
Password: <PASSWORD>
$ SET TERMINAL/WIDTH=132
.
.
.
$ logout
JONES    logged out at 19-DEC-2001 11:04:51.45

%REM-S-END, control returned to node _ORACLE
```

This example shows user *JONES* on node *ORACLE* logging in to remote node *GENEVA* and specifies that the original terminal screen width be restored to 80 characters when the remote session is terminated.

## SET HOST/DTE

**SET HOST/DTE** — Connects your system to a remote system through an outgoing terminal line. **You must have an account on the remote system in order to log into that system after the connection is made. You must also have the ability to assign a channel to the terminal port specified. Your system manager can set the device protection on the terminal port to allow you access.**

### Format

**SET HOST/DTE** *terminal-name*

### Parameter

*terminal-name*

Specifies the name of an outgoing terminal line, which connects your system directly to another system or modem.

### Description

The **SET HOST/DTE** command allows you to connect your terminal to another system. Once the connection is made, the remote system prompts for a user name and password. You must have an account on the remote system to log in.

Once you have logged in to the remote system, you can use DCL commands just as you would on your local system.

To log in on lines that expect a break rather than a carriage return, press **Ctrl/break-character** to generate the break.

While connected to the remote system, you can issue configuration commands from DTE command mode. DTE commands enable you to configure a **SET HOST/DTE** session while it is in progress.

To issue DTE commands, you must get into DTE command mode by pressing **Ctrl/command-character**. By default, the command character is the at sign (@). Once you are in command mode, the DTEPAD prompt will be displayed on your screen.

Table 5, "SET HOST/DTE Session Commands" describes the DTE commands.

**Table 5. SET HOST/DTE Session Commands**

| Command              | Description                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>CLEAR</b>         | Disconnects your local system from DTEPAD. This command is equivalent to the <b>QUIT</b> command.                                                                                                                                                                                                                                                                                                                                                    |
| <b>EXIT</b>          | Returns the session to emulation mode.                                                                                                                                                                                                                                                                                                                                                                                                               |
| <b>QUIT</b>          | Disconnects your local system from DTEPAD. This command is equivalent to the <b>CLEAR</b> command.                                                                                                                                                                                                                                                                                                                                                   |
| <b>SAVE filespec</b> | Saves information on the current configuration settings. The current settings are written to the specified file as a series of <b>SET DTE</b> commands. You can later use this file as an initialization file.                                                                                                                                                                                                                                       |
| <b>SEND BREAK</b>    | Sends a break to remote systems that expect a break rather than a carriage return.                                                                                                                                                                                                                                                                                                                                                                   |
| <b>SET DTE</b>       | Modifies configurable characteristics of DTEPAD while in a <b>SET HOST/DTE</b> session. You can use the <b>SET HOST/DTE</b> qualifiers in command mode.                                                                                                                                                                                                                                                                                              |
| <b>SHOW DTE</b>      | Displays the current settings of all the configurable characteristics of DTEPAD. It also displays the number of bytes of data transmitted and received during the current <b>SET HOST/DTE</b> session and the number of errors detected by the terminal port.                                                                                                                                                                                        |
| <b>SPAWN</b>         | <p>Creates a subprocess of your current <i>local</i> process. The command is identical to the DCL <b>SPAWN</b> command except that the DTE <b>SPAWN</b> command has fewer qualifiers, as follows:</p> <pre> /INPUT=filespec /LOGICAL_NAMES and /NOLOGICAL_NAMES /OUTPUT=filespec /PROCESS=subprocess-name /SYMBOLS and /NOSYMBOLS /WAIT and /NOWAIT </pre> <p>See the <a href="#">SPAWN</a> command for more information about these qualifiers.</p> |

To terminate a session, you should first log out of the remote system. Then quit DTEPAD by pressing **Ctrl/escape-character**. By default, the escape character is a backslash (\). Alternatively, quit DTEPAD by entering the **QUIT** or the **CLEAR** command from DTE command mode.

## Qualifiers

### ***/BREAK=break-character***

Selects the break character. The break character is used to generate a break on lines that expect a break rather than a carriage return. To generate a break, press **Ctrl/break-character**.

The break character can be any ASCII character between @ and z, except C, M, Q, S, Y, or the left bracket ([). You cannot select a character currently defined as either the command character (see the description of the [\*/COMMAND=command-character\*](#) qualifier) or the escape character (see the description of the [\*/ESCAPE=escape-character\*](#) qualifier).

The ASCII characters between @ and z include the alphabetic characters in both upper and lower cases, the at sign (@), the backslash (\), the right bracket (]), the circumflex (^), the underscore (\_), and the grave accent (`).

By default, the break character is the right bracket (]).

### ***/COMMAND=command-character***

Selects the command character. Use the command character to access DTE command mode by pressing **Ctrl/command-character**.

The command character can be any ASCII character between @ and z, except C, M, Q, S, Y, or the left bracket ([). You cannot select a character currently defined as either the break character (see the description of the [\*/BREAK=break-character\*](#) qualifier) or the escape character (see the description of the [\*/ESCAPE=escape-character\*](#) qualifier).

The ASCII characters between @ and z include the alphabetic characters in both upper and lower cases, the at sign (@), the backslash (\), the right bracket (]), the circumflex (^), the underscore (\_), and the grave accent (`).

By default, the command character is the at sign (@).

### ***/DIAL=(NUMBER:number [,MODEM\_TYPE:modem-type])***

Allows a modem attached to the outgoing terminal line to be autodialed using the autodial protocol of that modem. The NUMBER keyword is the telephone number to be autodialed and is a required parameter.

Before you dial a new number, you must log out of the current remote system.

On Alpha, the MODEM\_TYPE keyword defaults to DMCL (any modem that uses the DEC Modem Command Language).

Each modem type requires a specific modem dialer code. Check with your system manager to see which modem dialer codes are installed on your system.

In addition, the MODEM\_TYPE keyword can be used to specify a modem type other than DF03, DF112, or DMCL. A template is provided for users interested in supporting other modems with autodial capabilities (see SYS\$EXAMPLES:DTE\_DF03.MAR).

### ***/ECHO***

### ***/NOECHO (default)***

Determines whether the terminal input is echoed by your local system. By default, all echoing is performed by the remote system.

**/EIGHT\_BIT (default)**  
**/NOEIGHT\_BIT**

Determines whether the outgoing terminal line supports 8-bit or 7-bit characters. By default, 8-bit characters are supported. If you specify **/NOEIGHT\_BIT**, then 7-bit characters are supported.

**/ERROR\_ACTION=CONTINUE (default)**  
**/ERROR\_ACTION=EXIT**

Specifies the error action by using the EXIT or the CONTINUE keyword.

When an error is detected on the outgoing terminal line, the error is reported to the local system and an error message is displayed on your terminal.

If the error action is CONTINUE, then communication with the remote system continues uninterrupted.

If the error action is EXIT, then the local system immediately exits from the remote system.

**/ESCAPE=escape-character**

Selects the escape character. You can use the escape character to exit from DTEPAD by pressing **Ctrl/escape-character**.

The escape character can be any ASCII character between @ and z, except C, M, Q, S, Y, or the left bracket ([). You cannot select a character currently defined as either the break character (see the description of the [\*\*/BREAK=break-character\*\*](#) qualifier) or the command character (see the description of the [\*\*/COMMAND=command-character\*\*](#) qualifier).

By default, the escape character is a backslash (\).

The ASCII characters between @ and z include the alphabetic characters in both upper and lower cases, the at sign (@), the backslash (\), the right bracket (]), the circumflex (^), the underscore (\_), and the grave accent (`).

**/FLOW\_CONTROL (default)**  
**/NOFLOW\_CONTROL**

Determines whether XON/XOFF flow control is enabled. By default, flow control is enabled.

XON/XOFF flow control is a means of preventing data-overflow errors. Incoming data is stored in receive buffers; when these buffers are full, a signal is sent to the remote system to stop transmission. Once there is sufficient space in the receive buffers, another message is sent to restart transmission.

You should disable XON/XOFF flow control when the remote system has no XON/XOFF flow control.

**/INIT[=filespec] (default)**  
**/NOINIT**

Sets the configurable characteristics of DTEPAD according to values contained in the specified initialization file.

If you use qualifiers in the command line to define the values of any of the configurable characteristics, these will supersede the values contained in the initialization file.

By default, DTEPAD tries to translate the logical name DTEPAD\$INI in order to find the appropriate initialization file. If you use the **/INIT** qualifier and omit the file specification, DTEPAD translates the logical name DTEPAD\$INI and finds the appropriate file. If DTEPAD\$INI is not defined, then DTEPAD uses **/NOINIT** as the default.

An initialization file can contain any combination of any of the following DTE commands:

- **SAVE**
- **SEND BREAK**
- **SET DTE**
- **SPAWN**

The following is an example of an initialization file:

```
SET DTE/MAX_BUFFERS=150SET DTE/READ_DELAY=100SEND BREAK
```

**/LOG[=*filespec*]**

**/NOLOG (default)**

Controls whether a log file of the session is kept.

If you use the **/LOG** qualifier and omit the file specification, then the log information is written to the file DTEPAD.LOG.

When used to log a modem session, the log file contains any noise that occurred on the phone line. For example, typing a file in order to get it recorded in the log file could result in noise being recorded along with the file data. Therefore, the use of a log file is not recommended for the purpose of file transfers.

VSI recommends that you use asynchronous DECnet to transfer files.

**/MAX\_BUFFERS=*number-buffers***

Specifies the maximum number of receive buffers. Receive buffers are buffers used to receive incoming data from the modem port. They are allocated as they are required.

By default, the maximum number of receive buffers is 100. The minimum number you can specify is 20.

**/PARITY=NONE (default)**

**/PARITY=ODD**

**/PARITY=EVEN**

Selects parity on the outgoing terminal line.

**/READ\_DELAY=*delay***

Specifies the modem port read delay in milliseconds. The modem port read delay is the time interval during which data in the modem port is transferred into receive buffers at the terminal.

By default, the modem port read delay is 50 milliseconds. This is also the minimum value.

A long modem port read delay slows the rate at which data is displayed at your terminal, and also increases the risk of data-overflow errors; however, a longer read delay requires less CPU overhead.

**/SPEED=(*output-rate,input-rate*)**

Sets the baud rate at which the terminal receives and transmits data. If the input and output rates are the same, specify the qualifier as **/SPEED=rate**.

Not all terminals support different input and output baud rates. For specific information on baud rates for your terminal, consult the manual for that terminal.

The default transmission rates are installation dependent.

The valid baud rates are as follows:

|     |      |      |       |        |
|-----|------|------|-------|--------|
| 50  | 150  | 1800 | 4800  | 38400  |
| 75  | 300  | 2000 | 7200  | 57600  |
| 110 | 600  | 2400 | 9600  | 76800  |
| 134 | 1200 | 3600 | 19200 | 115200 |

If you select an invalid or unsupported speed, then the terminal line speed will remain set at its previous value.

## Examples

1. `$ SET HOST/DTE TTA2:/DIAL=NUMBER:5551234`  
Username: SMITH  
Password:

This command connects the user terminal to the outgoing terminal line TTA2:, which is attached to a modem (type DF03 by default) set to autodial the phone number 555-1234. The remote processor then prompts for user name and password. Use the normal login procedure to log in to the remote system.

2. `$ SET HOST/DTE/DIAL=(NUMBER:5551234#,MODEM_TYPE:DF112) TTA2:`  
Username: SMITH  
Password:

This command accomplishes the same thing as in the first example, except that it uses the DF112 modem. The number sign (#) is required to activate the autodialer in the DF112.

3. `$ SET HOST/DTE/NOEIGHTBIT TTA2`

This command sets the outgoing terminal port, TTA2, to support 7-bit characters.

4. `$ SET HOST/DTE/NOFLOW_CONTROL TTA2`

This command disables the XON/XOFF flow control.

5. `$ SET HOST/DTE/ERROR_ACTION=EXIT TTA2`

This command sets the error action to **EXIT**.

6. `$ SET HOST/DTE/MAX_BUFFERS=150 TTA2`

This command sets the maximum number of receive buffers to 150.

7. `$ SET HOST/DTE/ESCAPE=E TTA2`

This command defines the letter E as the escape character. Note that DTEPAD is not case sensitive.

8. `$ SET HOST/DTE/LOG TTA2`

This command enables logging of the session. Since no log file is specified, the log is written to the default log file, DTEPAD.LOG.

9. `$ SET HOST/DTE/INIT=MYFILE.INI TTA2`

This command uses the initialization file MYFILE . INI.

10. `$ Ctrl/@`  
DTEPAD>

This example shows you how to access DTE command mode by pressing **Ctrl/@**, where @ is the command character.

11. DTEPAD> `SAVE MYFILE.INI`

This command saves the information on the current configuration in the file MYFILE . INI.

12. DTEPAD> `SET DTE/BREAK=G`

This command defines the letter G as the break character.

13. DTEPAD> `SET DTE/ECHO`

This command sets the terminal port so that echoing is performed by the local system.

14. DTEPAD> `SET DTE/SPEED=4800`

This command sets the input and output baud rates to 4800.

15. DTEPAD> `SET DTE/LOG=myfile.log`

This command directs logging to the file MYFILE . LOG.

16. DTEPAD> `SHOW DTE`

|                   |                 |
|-------------------|-----------------|
| Port TXA0         | EIGHT_BIT ECHO  |
| Flow control      | XON/XOFF        |
| Parity            | NONE            |
| Transmit Speed    | 4800            |
| Receive Speed     | 4800            |
| Error action      | CONTINUE        |
| Break character   | B               |
| Escape character  | \               |
| Command character | @               |
| Maximum buffers   | 100             |
| Read delay        | 50 milliseconds |
| Log file          | MYFILE.INI      |
| Number dialed     | 12345678        |
| Modem type        | DF03            |
| Bytes transmitted | 75              |
| Bytes received    | 132             |
| Errors            | 0               |

This command displays all the current settings of the configurable characteristics, the number of bytes transmitted and received, and the number of errors detected.

# SET HOST/DUP

SET HOST/DUP — Connects your terminal to a storage controller through the appropriate bus for that controller. The **/SERVER** and **/TASK** qualifiers are required. **For use only with storage controllers. Requires the DIAGNOSE privilege.**

## Format

```
SET HOST/DUP/SERVER=server-name
```

```
/TASK=task-name node-name
```

## Parameter

*node-name*

Specifies the node name of the storage controller.

## Description

The **SET HOST/DUP** command creates a virtual terminal connection and executes a utility or diagnostic program on a storage controller that uses the Diagnostic and Utilities Protocol (DUP) Standard Dialogue.

Once the connection is established, operations are performed under the control of the utility or diagnostic program.

When the utility or diagnostic program terminates, control is returned to the local system.

To abort or prematurely terminate the connection and return control to the local system, press **Ctrl/A**.

Further information regarding the operation of the utility and diagnostic programs available on a particular controller may be obtained from the appropriate documentation set for that controller.

## Preparing for Use

To use the **SET HOST/DUP** facility, you must first install FYDRIVER, the DUP class driver. To load FYDRIVER, add the following commands to the SYSTARTUP.COM command procedure in the SYS\$MANAGER directory.

On Alpha and Integrity servers, specify the following commands:

```
$ RUN SYS$SYSTEM:SYSMANSYSMAN> IO CONNECT FYA0/NOADAPTER/DRIVER=SYS  
$FYDRIVER
```

This operation requires CMKRNL (change mode to kernel) privilege.

## Qualifiers

**/LOG[=*filespec*]**

**/NOLOG (default)**

Controls whether a log file of the entire session is kept. If you use the **/LOG** qualifier without the file specification, the log information is stored in the file HSCPAD.LOG.

**/SERVER=***server-name*

Specifies the server name for the target storage controller.

This qualifier is required.

**/TASK=***task-name*

Specifies the utility or diagnostic name to be executed on the target storage controller under direction of the server.

This qualifier is required.

## Example

```
$ SET HOST/DUP/SERVER=MSCP$DUP/TASK=DIRECT R2DH5Y
%HSCPAD-I-LOCPRGEXE, Local program executing - type ^\ to exit utility
```

The **SET HOST/DUP** command in this example connects the user terminal to the utility program called **DIRECT** executing on a storage controller named **R2DH5Y** under direction of the **MSCP\$DUP** server.

## SET HOST/HSC

**SET HOST/HSC** — Connects your terminal to an HSC disk and tape controller through the computer interconnect (CI) bus. **Used only with HSC controllers. Requires the DIAGNOSE privilege.**

### Format

**SET HOST/HSC** *node-name*

### Parameter

*node-name*

Specifies the node name of the HSC.

### Description

The **SET HOST/HSC** command establishes a connection to an HSC disk and tape controller by way of the CI bus. (The **SHOW CLUSTER** command lists the names of HSC controllers that are accessible to your node.) No password is required to access the HSC; however, only **SHOW** commands are accepted when the HSC Secure/Enable switch is in the Secure position.

Once the connection is made to the HSC, operations can be performed as if you were attached to the local terminal of the HSC; however, access to ODT (Octal Debugging Tool) and offline diagnostics are not permitted.

Press **Ctrl/C** to obtain a prompt from the HSC before entering commands. To exit from the HSC and return to the local system, press **Ctrl/A**.

A description of HSC commands and utilities can be obtained from the HSC documentation.

## Preparing for Use

To use the **SET HOST/HSC** facility, you must first install FYDRIVER, which is the Diagnostic and Utilities Protocol (DUP) driver associated with the CI. To load FYDRIVER, add the following commands to the SYSTARTUP.COM command procedure in the SYS\$MANAGER directory:

```
$ RUN SYS$SYSTEM:SYSGENCONNECT FYA0/NOADAPTER
```

This operation requires CMKRNL (change mode to kernel) privilege.

## Qualifier

**/LOG[=*filespec*]**  
**/NOLOG (default)**

Controls whether a log file of the entire session is kept. If you use the **/LOG** qualifier without the file specification, the log information is stored in the file HSCPAD.LOG.

## Example

```
$ SET HOST/HSC HSC001
%HSCPAD-I-LOCPROGEXE, Local program executing - type ^\ to exit, ^Y for
  prompt
HSC>
```

This **SET HOST/HSC** command connects the user terminal to the HSC named HSC001.

## SET HOST/LAT

**SET HOST/LAT** — Connects your terminal to a specified service available on the local area network (LAN), establishing one session for communication between your terminal and that service. **The service node that provides the service must be on the same extended LAN and must be running at least Version 5.0 of the LAT protocol.**

## Format

**SET HOST/LAT *service-name***

## Parameter

***service-name***

Specifies the name of the service to which you want your terminal connected. A service is a resource on the LAN. A service often consists of all of the resources of a computer system. Other examples of services are a file storage system and an application program running on a computer system. A computer system that offers one or more services is called a service node.

If several service nodes offer the same service, and you do not specify the **/NODE=*node-name*** qualifier, your terminal connects to the service node that is the least busy.

To display a list of services on your LAN, use the LAT Control Program (LATCP) **SHOW SERVICES** command. See the relevant section in the [VSI OpenVMS System Management Utilities Reference Manual, Volume 1: A-L](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-i-a-l/#LATCP_PART) [https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-i-a-l/#LATCP\_PART].

## Description

The **SET HOST/LAT** command allows you to connect your terminal to a specified service, establishing one LAT session for communication between your terminal and that service. (For an overview of the LAT protocol and its advantages, see the relevant section in the *VSI OpenVMS System Manager's Manual, Volume 2: Tuning, Monitoring, and Complex Systems* [[https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-2-tuning-monitoring-and-complex-systems/#LAT\\_PROTOCOL\\_SEC](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-2-tuning-monitoring-and-complex-systems/#LAT_PROTOCOL_SEC)].)

The service node that provides the service must be on the same extended LAN and must be running at least Version 5.0 of the LAT protocol.

Some services are password protected. You are prompted for a password unless you specify the password with the **/PASSWORD** qualifier.

Once the connection to the service is made, you can interact with the service as if your terminal is directly connected to it. Some services will prompt you. For example, if the service is an OpenVMS system, it prompts you for a user name and password. You must have an account on the service node to log in.

Press the disconnect character to end the LAT session and return to DCL command level on your local system. With some services, such as general time sharing services like OpenVMS, you can end the LAT session by logging out of the service. The default disconnect character is **Ctrl/\**. Use the **/DISCONNECT** qualifier to change the default disconnect character.

## Qualifiers

**/AUTOCONNECT**  
**/NOAUTOCONNECT**

Specifies whether connection attempts should be retried automatically when a connection fails because a service is unknown or unavailable, or because a node is unknown or unreachable. Also specifies that reconnects should be attempted automatically if a service has disconnected abnormally. The default is **/NOAUTOCONNECT**.

**/AUTOPROMPT (default)**  
**/NOAUTOPROMPT**

Causes an OpenVMS Username: prompt to appear with no user action when a **SET HOST/LAT** command is issued.

On a terminal server port, you can configure the port to have AUTOPROMPT disabled (**/NOAUTOPROMPT**) so that you are required to press Return when connecting to a node to get the Username: prompt; however, when connecting to a reverse LAT service, the AUTOPROMPT characteristic should be disabled.

**/BREAK=break-character**

Defines a character that generates a break on lines that expect a break rather than a carriage return. To generate a break, press the **Ctrl** and *break-character* keys together. The default *break-character* value is the tilde (~).

You can select any ASCII character between @ and Z, except C, M, Q, S, Y, and the left bracket ([). You cannot select a character that is already defined as the disconnect character.

**/DESTINATION\_PORT=*port-name***

Specifies the port on a node to which you want to connect. The **/NODE** qualifier is required when you specify the **/DESTINATION\_PORT** qualifier. The port must be available and must offer the service you specify. OpenVMS and certain other LAT service node systems ignore the **/DESTINATION\_PORT** qualifier.

**/DIAL=(NUMBER:*number* [,MODEM\_TYPE:*modem-type*])**

Allows a modem attached to the outgoing terminal line to be autodialed using the autodial protocol of that modem. The NUMBER keyword is the telephone number to be autodialed and is a required parameter.

The MODEM\_TYPE keyword is optional. It can be used to specify any of the following modem types:

- DMCL (any modem that uses the DEC Modem Command Language)
- DF03 (default)
- DF112

Each modem type requires a specific modem dialer code. Check with your system manager to see which modem dialer codes are installed on your system.

In addition, the MODEM\_TYPE keyword can be used to specify a modem type other than DF03, DF112, or DMCL. A template is provided for users interested in supporting other modems with autodial capabilities (see SYS\$EXAMPLES:DTE\_DF03.MAR).

**/DISCONNECT=*disconnect-character***

Defines the character that you can use to disconnect from a remote session. To generate a disconnect, press the **Ctrl** and *disconnect-character* keys together. The default *disconnect-character* is the backslash (\).

You can select any ASCII character from @ through Z, except C, M, Q, S, Y, and the left bracket ([). For example, if you specify **/DISCONNECT=A**, **Ctrl/A** will be the disconnect character. You cannot select a character that is already defined as the break character.

**/EIGHT\_BIT (default)****/NOEIGHT\_BIT**

Determines whether the outgoing terminal line supports 8-bit or 7-bit characters. By default, 8-bit characters are supported. If you specify **/NOEIGHT\_BIT**, then 7-bit characters are supported.

---

**Note**

To change the number of bits per character on the remote terminal server port, that port must have the REMOTE MODIFICATION characteristic enabled.

---

**/FRAME=*n***

The **/FRAME=*n*** qualifier allows a user making a LAT connection to a remote system to specify the number of data bits that the terminal driver expects for every character that is input or output. The value of *n* can be from 5 to 8. The default value depends on the settings for the terminal established

by the **/PARITY** and **/EIGHT\_BIT** qualifiers. The following example specifies a character frame size of 7 bits per character:

```
$ SET HOST/LAT /FRAME=7 DIAL_OUT_SVC
```

### **/LOG[=*log-file*]**

Logs all data that is delivered during the LAT session. If you do not specify a log file, the data is stored in the file **SETHOST\_LAT.LOG**.

### **/NODE=*node-name***

Specifies the node that offers the service to which you want to connect. Failover is not performed if the connection fails.

### **/PASSWORD=*password***

Specifies the password required by a service that is password protected. If you do not specify the **/PASSWORD** qualifier when requesting a connection to a password-protected service, you are prompted for a password.

### **/QUEUE**

#### **/NOQUEUE (default)**

When connecting to a reverse LAT service that is already in use (such as a dial out modem), you are notified that the service is in use and the **SET HOST/LAT** command terminates. However, LAT can allow incoming connections to be queued to any reverse LAT service that supports service queueing, which enables users to be placed on a queue when using reverse LAT services.

LAT reports your position in the queue. When the resource becomes available, you are immediately notified. You can cancel the queued connection by pressing **Ctrl/Y** and terminating the **SET HOST/LAT** command.

### **/SPEED=(*output-rate,input-rate*)**

Sets the baud rate at which the terminal receives and transmits data. If the input and output rates are the same, specify the qualifier as **/SPEED=*rate***.

Not all terminals support different input and output baud rates. For specific information on baud rates for your terminal, consult the manual for that terminal.

The default transmission rates are installation dependent.

The valid values for input and output baud rates are as follows:

```
300, 600, 1200, 2400, 4800, 9600, 19200, 38400, 57600
```

If you select an invalid or unsupported speed, the terminal line speed will remain set at its previous value.

---

## **Note**

To change the speed on the terminal server port, the **REMOTE MODIFICATION** characteristic must be enabled on that terminal server port.

When initiating a connection, **SET HOST/LAT** may attempt to set terminal server port characteristics, such as the speed and the default speed for a LAT device. If the device connected to the terminal server port has a fixed speed (such as a dial-out modem) and you do not want the host

to try to change this, disable the REMOTE MODIFICATION characteristic on that port using the following command:

```
Local> DEFINE PORT x REMOTE MODIFICATION DISABLE
Local> LOGOUT PORT x
```

Use the following command for terminal servers that support the **CHANGE** command:

```
Local> CHANGE PORT x REMOTE MODIFICATION DISABLE
```

---

## Examples

1. 

```
$ SET HOST/LAT SORTER
%LAT-S-CONNECTED, session to SORTER established
%LAT-I-TODISCON, type ^\ to disconnect the session
Username: BARKER
Password:
.
.
.
$ LOGOUT
BARKER logged out at 30-DEC-2001 11:04:51.45
%LAT-I-DISCONNECTED, session disconnected from SORTER
-LAT-I-END, control returned to node HOME
$
```

This **SET HOST/LAT** command connects the user to the service SORTER, which is a computer system. The first message confirms that the user has been connected to that service. The second message informs the user how to disconnect the session. (The user can also disconnect the session by logging out from SORTER.) SORTER then prompts for the username and password. Use the normal login procedure to log in to the system. When the user logs out of the service SORTER, the terminal displays the DCL command prompt of the user's local processor system (HOME).

2. 

```
$ SET HOST/LAT/DESTINATION_PORT=BOSTON-
_$ /NODE=STATE/DISCONNECT=F BUDGET
```

This command connects the user's terminal to the service BUDGET that is offered on port BOSTON, on service node STATE. The user can disconnect the session by pressing **Ctrl/F**.

3. 

```
$ SET HOST/LAT PURSE
Password:
```

This command attempts to connect the user's terminal to the service PURSE. The service PURSE is password protected, so the user is prompted for a password. The user could have specified the password within the **SET HOST/LAT** command, as shown in the next example.

4. 

```
$ SET HOST/LAT/PASSWORD=BEOR PURSE
```

This command connects the user's terminal to the password-protected service PURSE. The password is BEOR.

## SET HOST/RLOGIN

**SET HOST/RLOGIN** — Allows you to log in to a remote host over a TCP/IP connection and start an interactive terminal session by accessing the RLOGIN application.

## Format

```
SET HOST/RLOGIN{IPhostname | IPaddress}
```

---

### Note

You can specify the *IPhostname* or the *IPaddress*, but not both.

---

## Parameter

### *IPhostname*

Specifies the IP host name of the remote host.

### *IPaddress*

Specifies an IP address of the remote host.

## Description

The **SET HOST/RLOGIN** command allows you to log in to a remote host by invoking RLOGIN client software that runs on your system. Once you start the terminal session, you can enter commands interactively on the remote host. The parameter that specifies the remote host is either an IP host name or an IP address.

## Qualifiers

### **/AUTHENTICATE**

Specifies that Kerberos authentication should be used for acquiring access to the remote node.

### **/TERMINAL\_TYPE=type**

Sets the terminal emulator to one of the following terminal types: VT100, VT200, VT300, VT400, VT500.

### **/TRUNCATE\_USERNAME**

Specifies that the current user name should be truncated to 8 characters before attempting to connect to the remote node. The qualifier is required for communication with systems that limit the size of their login names to 8 characters. The **/TRUNCATE\_USERNAME** qualifier is ignored if **/USERNAME** is specified.

### **/USERNAME=username**

Specifies the user name for logging in to the remote node. The user name can be closed in quotes to preserve the case of the user name for case sensitive systems such as UNIX systems. If the **/USERNAME** qualifier is not specified, the default is the current user's user name.

## Example

```
$ SET HOST/RLOGIN remotest1
```

This example creates an RLOGIN connection to remote host `remotehst1` over a TCP/IP connection.

## SET HOST/TELNET

SET HOST/TELNET — Connects you to a remote host over a TCP/IP connection by invoking the TELNET application.

### Format

```
SET HOST/TELNET{IPhostname | IPaddress}
```

---

### Note

You can specify the *IPhostname* or the *IPaddress*, but not both.

---

### Parameters

#### *IPhostname*

Specifies the IP host name of the remote host.

#### *IPaddress*

Specifies an IP address of the remote host.

### Description

The **SET HOST/TELNET** command allows you to connect to a server on a remote system by invoking the TELNET client software that runs on your system. The parameter that specifies the remote host is either an IP host name or an IP address.

Most of the attributes are negotiated with the remote node. Except for the **/AUTHENTICATE** qualifier, the qualifiers are used only in exception cases (for example, cases where a remote server does not support a negotiated parameter but requires a certain characteristic for the connection).

### Qualifiers

#### **/AUTHENTICATE**

Specifies that Kerberos authentication should be used for acquiring access to the remote node.

#### **/PORT=port**

Specifies the remote TCP port to use. The default is 23.

#### **/TERMINAL\_TYPE=type**

Sets the terminal emulator to one of the following terminal types: VT100, VT200, VT300, VT400, VT500.

### Example

```
$ SET HOST/TELNET remotehst2
```

This example creates a TELNET connection to remote host `remotehst2` over a TCP/IP connection.

## SET HOST/TN3270

**SET HOST/TN3270** — Connects you to a remote IBM host over a TCP/IP connection, causing the local keyboard to emulate an IBM 3279-class terminal keyboard by invoking the TN3270 terminal emulator.

### Format

```
SET HOST/TN3270{IPhostname | IPaddress}
```

---

### Note

You can specify the *IPhostname* or the *IPaddress*, but not both.

---

### Parameters

#### *IPhostname*

Specifies the IP host name of the remote host.

#### *IPaddress*

Specifies an IP address of the remote host.

### Description

The **SET HOST/TN3270** command allows you to connect with a TELNET server on a remote IBM system by invoking the TN3270 terminal emulator TELNET client program on the local host. The parameter that specifies the remote host is either an IP host name or an IP address. The TN3270 client will automatically determine the terminal type (IBM-3278-2, IBM-3278-3, IBM-3278-4, or IBM-32798-5).

### Qualifiers

#### **/AUTHENTICATE**

Specifies that Kerberos authentication should be used for acquiring access to the remote node.

#### **/PORT=port**

Specifies the remote TCP port to use. The default is 23.

#### **/TERMINAL\_TYPE**

Sets the terminal emulator to one of the following terminal types: VT100, VT200, VT300, VT400, VT500.

### Example

```
$ SET HOST/TN3270 remotehst3
```

This example creates a connection to a TELNET server on the remote IBM system `remotehst3` over a TCP/IP connection.

## SET IMAGE (Alpha/Integrity servers Only)

**SET IMAGE** — Modifies the current attributes for the specified image file. This command can be used to modify the initial values set by the OpenVMS Integrity servers Linker for certain image attributes.

### Format

**SET IMAGE** *image-filespec*

### Parameters

*image-filespec*

Specifies the name of an OpenVMS Integrity servers image file to modify. The command overlays the current image file; it does not create a new version of the image file.

The asterisk (\*) and percent sign (%) wildcard characters are allowed in the file specification if the **/RESTORE** qualifier is used. If you omit the file type extension, the default file type `.EXE` is applied.

### Description

---

#### Note

This command can be executed on an Alpha or Integrity servers system, but it operates only on Integrity servers images.

---

### Qualifier

**/FLAGS=(keyword[,...])**

Specifies which image attribute flags to turn on or off. The original flags are set by the OpenVMS Integrity servers Linker at image link time. The possible keywords are listed below with a brief description.

---

#### Important

Beware of modifying the flag values unless you are very knowledgeable about the internals of the image.

---

| Keyword        | Description                             |
|----------------|-----------------------------------------|
| [NO]CALL_DEBUG | Call Debugger at startup.               |
| [NO]DBG_IN_DSF | Debug records in debug symbol file.     |
| [NO]DBG_IN_IMG | Debug records in image file.            |
| [NO]EXE_INIT   | Image has a pointer to EXE\$INITIALIZE. |

| Keyword        | Description                             |
|----------------|-----------------------------------------|
| [NO]IMGSTA     | Call SYS\$IMGSTA.                       |
| [NO]INITIALIZE | Image has a pointer to LIB\$INITIALIZE. |
| [NO]MAIN       | Image has a main transfer address.      |
| [NO]MKTHREADS  | Enable multiple kernel thread use.      |
| [NO]NOP0BUFS   | No P0 buffers for RMS image I/O.        |
| [NO]P0IMAGE    | Image is loaded only to P0 space.       |
| [NO]SIGNATURES | TIE Signatures are present.             |
| [NO]TBK_IN_DSF | Traceback records in debug symbol file. |
| [NO]TBK_IN_IMG | Traceback records in image file.        |
| [NO]UPCALLS    | User thread upcalls are enabled.        |

**/LOG**

Displays a message to the output device indicating whether the command successfully modified the image.

**/RESTORE**

Restores the original image attributes of the file -- that is, the initial attributes that were set by the OpenVMS Integrity servers Linker. You cannot specify the **/FLAGS** or **/SUCCESS** qualifier when **/RESTORE** is used.

**/SUCCESS**

Modifies the image link completion code value to SUCCESS. The run-time behavior of the image remains the same as the original link.

**Examples**

```

1. $ SHOW IMAGE WARNING
Show Image Version 1.2                      29-SEP-2004 10:15:52.61
WORK1:[SWEENEY.CLIUTL]WARNING.EXE;1
This is an OpenVMS IA64 (Elf format) executable image file
Image Identification Information
      Image name: WARNING
      Global Symbol Table name: WARNING
      Image file identification: X-6
      Image build identification: <unavailable>
      Link identification: Linker T02-14
      Link Date/Time: 12-JUN-2004 10:15:16.46
      Patch Date/Time: Never
      Manipulation Date/Time: Never
      Image Dynamic Data Version: 1.2
Image Completion Code Value: WARNING  State: Original
Image Link Flags state: Original
      Image Link Flags
      -----
      CALL_DEBUG      : Call debugger
      IMGSTA          : Call SYS$IMGSTA
      MAIN            : Image has main transfer
      TBK_IN_IMG      : Traceback records in image file

```

```

      DBG_IN_IMG      : Debug records in image file
$!
$ SET IMAGE/SUCCESS WARNING.EXE
$ SHOW IMAGE WARNING.EXE
Show Image Version 1.2                                29-SEP-2004 11:41:54.93
WORK1:[SWEENEY.CLIUTL]WARNING.EXE;1
This is an OpenVMS IA64 (Elf format) executable image file
Image Identification Information
      Image name: WARNING
      Global Symbol Table name: WARNING
      Image file identification: X-6
      Image build identification: <unavailable>
      Link identification: Linker T02-14
      Link Date/Time: 12-JUN-2004 10:02:53.51
      Patch Date/Time: Never
      Manipulation Date/Time: 29-SEP-2004 11:26:31.57
      Image Dynamic Data Version: 1.2
Image Completion Code Value: SUCCESS  State: Manipulated
Image Link Flags state: Original
      Image Link Flags
-----
CALL_DEBUG      : Call debugger
IMGSTA          : Call SYS$IMGSTA
MAIN            : Image has main transfer
TBK_IN_IMG      : Traceback records in image file
DBG_IN_IMG      : Debug records in image file

```

In this example the **SET IMAGE/SUCCESS** command is used to change the link completion code value in the image to SUCCESS. The output of the second **SHOW IMAGE** command displays that the image completion code value has been changed.

2. \$ SHOW IMAGE SYS\$SYSTEM:DCE\$DCED.EXE
 

```

Show Image Version 1.2                                29-SEP-2004 12:40:04.32
SYS$COMMON:[SYSEXE]DCE$DCED.EXE;199
This is an OpenVMS IA64 (Elf format) executable image file
Image Identification Information
      Image name: DCE$DCED
      Global Symbol Table name: DCE$DCED
      Image file identification: DCE T3.2-040610
      Image build identification: <unavailable>
      Link identification: Linker I01-68
      Link Date/Time: 11-JUN-2004 01:50:11.71
      Patch Date/Time: Never
      Manipulation Date/Time: Never
      Image Dynamic Data Version: 1.1
Image Completion Code Value: SUCCESS  State: Original
Image Link Flags state: Original
      Image Link Flags
-----
MAIN            : Image has main transfer
$ SET IMAGE/FLAGS=(MKTH,UPCALL) SYS$SYSTEM:DCE$DCED.EXE
$!
$ SHOW IMAGE SYS$SYSTEM:DCE$DCED.EXE
Show Image Version 1.2                                29-SEP-2004 12:43:34.90
SYS$COMMON:[SYSEXE]DCE$DCED.EXE;1
This is an OpenVMS IA64 (Elf format) executable image file
Image Identification Information
      Image name: DCE$DCED

```

```
Global Symbol Table name: DCE$DCED
Image file identification: DCE T3.2-040610
Image build identification: <unavailable>
  Link identification: Linker I01-68
    Link Date/Time: 11-JUN-2004 01:50:11.71
    Patch Date/Time: Never
    Manipulation Date/Time: 29-SEP-2004 12:43:02.14
Image Dynamic Data Version: 1.1
Image Link Flags state: Manipulated
  Current Image Flags      Original Link Flags
  -----
  MKTHREADS                MAIN
  UPCALLS
  MAIN
Image Link Flag  Description
-----
MKTHREADS       : Multiple kernel threads enabled
UPCALLS         : Upcalls enabled
MAIN            : Image has main transfer
```

The **SET IMAGE** command in this example shows how to enable multiple kernel threads and thread upcalls in the image SYS\$SYSTEM:DCE\$DCED.EXE.

```
3. $ SHOW IMAGE PATCH.EXE;61
Show Image                                     30-SEP-2004 09:06:39.57
WORK1:[SWEENEY.PATCH]PATCH.EXE;61
This is an OpenVMS IA64 (Elf format) executable image file

      Image name: PATCH
Global Symbol Table name: PATCH
      Link Date/Time: 23-SEP-2004 10:22:07.04
      Manipulation Date/Time: Never

      Link flags state: Original

      Link Flags
      -----
      CALL_DEBUG
      IMGSTA
      MAIN
      TBK_IN_IMG
      DBG_IN_IMG
$ DEFINE PATCH WORK1:[SWEENEY.PATCH]PATCH.EXE;61
$ PATCH X.LIS
      OpenVMS Integrity servers Debug64 Version 8.2

%DEBUG-I-INITIAL, Language: BLISS, Module: PATMAIN

DBG>Exit
$ SET IMAGE/FLAGS=NOCALL_DEBUG PATCH.EXE
$ PATCH X.LIS

      OpenVMS PATCH Version 8.2

%PATCH-I-NOGBL, some or all global symbols not accessible
%PATCH-I-NOLCL, image does not contain local symbols
PATCH>
```

This example demonstrates how to modify an image to stop the debugger from being called when the image is initiated. The image `PATCH.EXE` was linked with debugging enabled. The **SET IMAGE /FLAGS=NOCALL\_DEBUG** command allows the debugger to be bypassed when the image is run.

## SET KEY

**SET KEY** — Sets and locks the key definition state for keys defined with the **DEFINE/KEY** command.

### Format

**SET KEY**

### Description

When you define keypad keys using the **DEFINE/KEY** command, you can assign a specific state name to the key definition. If that state is not set when you press the key, the definition is not processed. Use the **SET KEY** command to change the current state to the appropriate state.

### Qualifiers

**/LOG (default)**  
**/NOLOG**

Controls whether the system displays a message indicating that the key state has been set.

**/STATE=state-name**  
**/NOSTATE**

Specifies the name of the state. The state name can be any alphanumeric string. If you omit the **/STATE** qualifier or use the **/NOSTATE** qualifier, the current state is left unchanged. The default state is **DEFAULT**.

### Example

```
$ SET KEY /STATE=EDITING
```

The **SET KEY** command in this example sets the key state to the state **EDITING**. You can now use the key definitions that were defined for the state **EDITING**.

## SET LOGINS

**SET LOGINS** — Sets the interactive limit (number of interactive users allowed on the system), or displays the interactive limit and the current number of interactive users. **Requires OPER (operator) privilege to set the login limit.**

### Format

**SET LOGINS**

## Parameters

None.

## Description

The SET LOGINS command is not retroactive. All users logged in to the system before you enter the **SET LOGINS** command are not affected by the command; however, once the limit you set is reached, no more users can log in to the system until someone else logs out. Users with the OPER privilege are not affected by the limit.

If you do not specify a parameter value with the **/INTERACTIVE=*n*** qualifier, the **SET LOGINS** command displays the following information:

```
Login quotas - Interactive limit=x, Current interactive value=y
```

The value *x* represents the current interactive limit, and the value *y* represents the number of users currently logged in to the system.

## Qualifier

**/INTERACTIVE[=*n*]**

Establishes the number of interactive users allowed to gain access to the system. If the parameter *n* is specified, the interactive limit is set to the value *n*. If the parameter *n* is not specified, the **SET LOGINS** command displays the current interactive limit and the number of interactive users.

## Examples

1. 

```
$ SET LOGINS/INTERACTIVE=5
%SET-I-INTSET, login interactive limit=5, current interactive value=3
```

In this example, the **SET LOGINS** command specifies that only five interactive users can be logged in to the system.

2. 

```
$ SET LOGINS/INTERACTIVE
%SET-I-INTSET, login interactive limit=9, current interactive value=6
```

When the **SET LOGINS** command is entered without a parameter, as shown in this example, the **/INTERACTIVE** qualifier requests that the current status of the login quotas be displayed. The message returned indicates that the maximum number of interactive users allowed on the system is 9 and that the number of interactive users currently logged in is 6. No change is made.

## SET MAGTAPE

**SET MAGTAPE** — Defines the default characteristics associated with a specific magnetic tape device for subsequent file operations. **The SET MAGTAPE command is valid for magnetic tape devices mounted with foreign volumes.**

## Format

**SET MAGTAPE *device-name*[:]**

## Parameter

***device-name***[:]

Specifies the name of the magnetic tape device for which the characteristics are to be set. The device must not be currently allocated to any other user.

## Qualifiers

***/DENSITY=density-value***

Specifies the default density for all write operations on the magnetic tape device when the volume is mounted as a foreign tape or as an unlabeled tape.

Valid density values are:

| Keyword                                                                                                                                                                                          | Description                                                           |
|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------|
| DEFAULT                                                                                                                                                                                          | Default density                                                       |
| 800                                                                                                                                                                                              | NRZI 800 bits per inch (BPI)                                          |
| 1600                                                                                                                                                                                             | PE 1600 BPI                                                           |
| 6250                                                                                                                                                                                             | GRC 6250 BPI                                                          |
| 3480                                                                                                                                                                                             | IBM 3480 HPC 39872 BPI                                                |
| 3490E                                                                                                                                                                                            | IBM 3480 compressed                                                   |
| 833                                                                                                                                                                                              | DLT TK50: 833 BPI                                                     |
| TK50                                                                                                                                                                                             | DLT TK50: 833 BPI                                                     |
| TK70                                                                                                                                                                                             | DLT TK70: 1250 BPI                                                    |
| 6250                                                                                                                                                                                             | RV80 6250 BPI EQUIVALENT                                              |
| NOTE: Only the keywords above are understood by TMSCP/TUDRIVER code prior to OpenVMS Version 7.2. The remaining keywords in this table are supported only on Alpha and Integrity server systems. |                                                                       |
| TK85                                                                                                                                                                                             | DLT Tx85: 10625 BPI - Cmpt III - Alpha/Integrity servers only         |
| TK86                                                                                                                                                                                             | DLT Tx86: 10626 BPI - Cmpt III - Alpha/Integrity servers only         |
| TK87                                                                                                                                                                                             | DLT Tx87: 62500 BPI - Cmpt III - Alpha/Integrity servers only         |
| TK88                                                                                                                                                                                             | DLT Tx88: (Quantum 4000) - Cmpt IV - Alpha/Integrity servers only     |
| TK89                                                                                                                                                                                             | DLT Tx89: (Quantum 7000) - Cmpt IV - Alpha/Integrity servers only     |
| QIC                                                                                                                                                                                              | All QIC drives are drive-settable only - Alpha/Integrity servers only |
| 8200                                                                                                                                                                                             | Exa-Byte 8200 - Alpha/Integrity servers only                          |
| 8500                                                                                                                                                                                             | Exa-Byte 8500 - Alpha/Integrity servers only                          |
| DDS1                                                                                                                                                                                             | Digital Data Storage 1 - 2G - Alpha/Integrity servers only            |
| DDS2                                                                                                                                                                                             | Digital Data Storage 2 - 4G - Alpha/Integrity servers only            |
| DDS3                                                                                                                                                                                             | Digital Data Storage 3 - 8-10G - Alpha/Integrity servers only         |
| DDS4                                                                                                                                                                                             | Digital Data Storage 4 - Alpha/Integrity servers only                 |
| AIT1                                                                                                                                                                                             | Sony Advanced Intelligent Tape 1 - Alpha/Integrity servers only       |
| AIT2                                                                                                                                                                                             | Sony Advanced Intelligent Tape 2 - Alpha/Integrity servers only       |

| Keyword | Description                                                     |
|---------|-----------------------------------------------------------------|
| AIT3    | Sony Advanced Intelligent Tape 3 - Alpha/Integrity servers only |
| AIT4    | Sony Advanced Intelligent Tape 4 - Alpha/Integrity servers only |
| DLT8000 | DLT 8000 - Alpha/Integrity servers only                         |
| 8900    | Exabyte 8900 - Alpha/Integrity servers only                     |
| SDLT    | SuperDLT1 - Alpha/Integrity servers only                        |
| SDLT320 | SuperDLT320 - Alpha/Integrity servers only                      |

Note that tape density keywords cannot be abbreviated.

## **/END\_OF\_FILE**

Writes a tape mark at the current position on the magnetic tape volume.

## **/FAST\_SKIP=*option***

Requires PHY\_IO privilege.

Allows you to skip by file mark or by record.

## **Note**

This tape positioning qualifier is for use on local SCSI tape drives only.

| Option           | Description                                                                                                                                                                                                                                                                                                              |
|------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| PER_IO (default) | Allows a local MK device to use the skip-by-filemarks function. The tape drive must be able to do a SCSI READ POSITION command and report blank check at end-of-data. The IO\$M_ALLOWFAST function modifier must be supplied with IO\$_SKIPFILE. Otherwise, the tape will skip files using the skip-by-records function. |
| ALWAYS           | Allows a local MK device to use the skip-by-filemarks function. The tape drive must be able to support the skip-by-filemarks function, and no modifications should be needed to the IO\$_SKIPFILE function.                                                                                                              |
| NEVER            | Specifies that a local MK device skip only by records. If you use a utility that depends on the semantics of skipping with skip-records, you may also need to use this option because it causes BACKUP or COPY to use the previous positioning.                                                                          |

## **/LOG**

## **/NOLOG**

Displays information about the operations performed on the magnetic tape volume.

## **/LOGSOFT (default)**

## **/NOLOGSOFT**

Controls whether soft errors on the specified device are to be logged in the error log file. Soft errors are errors corrected by the hardware without software intervention. This qualifier affects only devices that support hardware error correction, such as the TU78 magnetic tape drive. When used with other devices, this qualifier has no effect.

**/MEDIA\_FORMAT= [NO]COMPACTION**

Controls whether data records are automatically compacted and blocked together on a TA90E tape drive. Data compaction and record blocking increase the amount of data that can be stored on a single tape cartridge.

Note that once data compaction or noncompaction has been selected for a given cartridge, that same status applies to the entire cartridge.

**/RETENSION**

Moves a TZK10 tape cartridge to the end of the tape, and then back to the beginning of the tape. Use the **/RETENSION** qualifier on a regular basis to help maintain the integrity of TZK10 tape cartridges.

The **/RETENSION** qualifier must be used in conjunction with the **/REWIND** or **/UNLOAD** qualifier. The **/RETENSION** qualifier completes its action before **/REWIND** or **/UNLOAD**. Use **/RETENSION/REWIND** when you want the tape cartridge to remain loaded in the drive. Use **/RETENSION/UNLOAD** when you want to unload the tape cartridge after the retension operation.

This qualifier only affects TZK10 tape cartridge drives and has no effect on non-SCSI drives.

**/REWIND**

Requests that the volume on the specified device be rewound to the beginning of the magnetic tape.

**/SKIP=option**

Requests that the magnetic tape volume be positioned according to any of the following options:

| Option           | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| BLOCK: <i>n</i>  | Skips the specified number of blocks.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| END_OF_TAPE      | Positions the volume at the end-of-tape (EOT) mark.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| FILES: <i>n</i>  | Skips the specified number of tape marks (not files).<br><br>The tape is positioned just past the <i>n</i> the tape mark. If <i>n</i> is negative, the tape is still positioned after the <i>n</i> the tape mark, not before it. If the tape is already positioned immediately after a tape mark, a skip of -1 results in no net movement. (The tape moves to the preceding mark, but is then repositioned to the end of the mark, where it began.) For more information on tape marks and files, see the <a href="https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/">VSI OpenVMS System Manager's Manual, Volume 1: Essentials</a> [https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/]. |
| RECORD: <i>n</i> | Skips the specified number of records up to 32767.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |

**/UNLOAD**

Requests that the volume on the specified device be rewound and unloaded.

## Examples

1. \$ MOUNT MTB1:/FOREIGN

```
$ SET MAGTAPE MTB1: /DENSITY=800
```

The **MOUNT** command in this example mounts a foreign tape on the device MTB1. The **SET MAGTAPE** command defines the density for writing the magnetic tape at 800 bpi.

```
2. $ MOUNT MTA0:/FOREIGN
   $ SET MAGTAPE MTA0:/SKIP=FILES:4
```

The **MOUNT** command in this example mounts a foreign tape on the device MTA0; the **SET MAGTAPE** command directs the magnetic tape position to skip four files.

## SET MESSAGE

**SET MESSAGE** — Sets the format for system messages or specifies a process level message file. Lets you override or supplement the system messages.

### Format

```
SET MESSAGE [filespec]
```

### Parameter

*filespec*

Specifies the name of the process level message file. Messages in this file supersede messages for the same conditions in the system message file or in an existing process message file. The file type defaults to .EXE. The asterisk (\*) and the percent sign (%) wildcard characters are not allowed. If you do not specify this parameter, the qualifiers apply to the system message file.

### Description

The **SET MESSAGE** command specifies which message fields the OpenVMS system displays. The message format is as follows:

```
%FACILITY-L-IDENT, text
```

When a process is created, the default is to display all four message fields: facility, severity, identification, and text. To control which fields of a message are displayed, specify the appropriate qualifiers. For example, to omit the FACILITY field in message displays, specify **SET MESSAGE /NOFACILITY**.

By including the **SET MESSAGE** command in your login command file, you can select specific portions of the messages for your process.

Use the **SET MESSAGE** command, also, to override or supplement system messages. Whenever any software detects an error and invokes the \$GETMSG system service, the message files are searched in the following order: image message sections first, process-permanent message files second, and the system message file last. Thus, with the **SET MESSAGE** command, you can introduce messages earlier in the searching order; you can either override or supplement the system messages. (Note that the new message definitions affect only your process.)

If a process-permanent message file exists when you specify the **SET MESSAGE** command with a file specification, the old file is removed and the new file is added.

The message definitions you specify must result from a successful compilation with the **MESSAGE** command. For full details on how to create your own messages with the Message utility, see the relevant section in the *VSI OpenVMS Command Definition, Librarian, and Message Utilities Manual* [[https://docs.vmssoftware.com/vsi-openvms-command-definition-librarian-and-message-utilities/#MSG\\_CHAP](https://docs.vmssoftware.com/vsi-openvms-command-definition-librarian-and-message-utilities/#MSG_CHAP)].

## Qualifiers

### **/DELETE**

Removes any process-permanent message files currently in effect. Do not specify the *filespec* parameter with the **/DELETE** qualifier.

### **/FACILITY (default)**

### **/NOFACILITY**

Formats messages so that the facility name prefix appears.

### **/IDENTIFICATION (default)**

### **/NOIDENTIFICATION**

Formats messages so that the message identification prefix appears.

### **/SEVERITY (default)**

### **/NOSEVERITY**

Formats messages so that the severity level appears.

### **/TEXT (default)**

### **/NOTEXT**

Formats messages so that the message text appears.

## Examples

1. 

```
$ TYPE XXX
%TYPE-W-OPENIN, error opening DB1:[MARSHALL]XXX.LIS; as input
-RMS-E-FNF, file not found
.
.
.
$ SET MESSAGE/NOIDENTIFICATION
.
.
.
$ TYPE XXX
%TYPE-W, error opening DB1:[MARSHALL]XXX.LIS; as input
-RMS-E, file not found
```

When the first **TYPE** command is entered in this example, the error messages include all fields. Later, the **SET MESSAGE** command establishes that the IDENT portion (the abbreviation for the message text) is omitted in future messages.

2. 

```
$ SET MESSAGE NEWMSG
```

The **SET MESSAGE** command in this example specifies that the message text in NEWMSG.EXE supplements the existing system messages.

# SET NETWORK

SET NETWORK — Registers the attributes of a network service. **Requires SYSNAM (system name) privilege.**

## Format

**SET NETWORK** *network-service*

## Parameter

*network-service*

Specifies the name of a network service.

## Description

The **SET NETWORK** command allows you to control information about network services on an OpenVMS system. This information is contained in structures pointed to by executive mode logical names SYS\$NET\_SERVICES\_1 to SYS\$NET\_SERVICES\_12. Each structure defines a particular network service and contains the following information:

- Product name
- Manufacturer
- Type of network
- Node name
- Address(es)
- Interface(s) (OpenVMS device driver)
- Vendor-specific data
- Status
- Connections
- Counters
- Start command
- Stop command
- Path to the Point-to-Point Protocol utility (PPPD) shareable image

The following items are required for network registration: product name, manufacturer, type of network, node name, address. For each network service that supports the Point-to-Point Protocol (PPP), the file name of the PPPD shareable image must also be specified using the **/PPPD\_CALLOUT** qualifier.

The **SET NETWORK** command allows you to perform the following actions on the information on network services:

- Add a service (use the **/REGISTER** qualifier)
- Delete a service (use the **/REMOVE** qualifier)
- Modify the information for a service (use the **/UPDATE** qualifier)

The **/REGISTER** qualifier is the default, if you do not specify an action.

## Qualifiers

### **/ADDRESS=***address[es]*

Specifies the network address of the local node.

### **/CONNECTIONS=**

Specifies a command to be executed to display the number of network connections.

### **/COUNTERS=**

Specifies a command to be executed to display the number of network counters.

### **/DATA=**

Specifies a character string provided by the network service vendor.

### **/INTERFACE=**

Specifies the OpenVMS driver for the network service.

### **/MANUFACTURER=**

Specifies the manufacturer of the network service.

### **/NETWORK\_TYPE=**

Specifies the protocol for the network service.

### **/NODE=**

Specifies the name of the local node.

### **/PPPD\_CALLOUT=***image-name*

Specifies the name of the protected shareable image activated by PPPD. This image contains the routine `PPPD$OPEN_CONNECT`, which notifies the network service that a new physical transport exists that supports PPP. If the image resides in the `SYSS$SHARE` directory, enter the file name of the image without the suffix (such as, `PPPD_CALLOUT` instead of `PPPD_CALLOUT.EXE`); otherwise, enter the system logical that identifies the location of the image.

### **/REGISTER**

Defines a new network service.

### **/REMOVE**

Deletes a network service from the database.

**/START=**

Specifies an image to be executed when you issue the **START/NETWORK** command for the network service.

**/STATUS=**

Specifies a command to be executed to display additional status information.

**/STOP=**

Specifies an image to be executed when you issue the **STOP/NETWORK** command for the network service.

**/UPDATE**

Allows you to modify the specified data for the network service.

## Examples

```
1. $ SET NETWORK DECnet -
   _$ /MANUFACTURER= "Hewlett-Packard Company" -
   _$ /NODE="GALENA" -
   _$ /ADDRESS="19.129" -
   _$ /NETWORK_TYPE="DNA V" -
   _$ /INTERFACE="net 0" -
   _$ /DATA="Router: No" -
   _$ /STATUS="mcr ncl show node 0 all" -
   _$ /CONNECTIONS="mcr ncl show node 0 session control port * all" -
   _$ /COUNTERS="mcr ncl show node 0 session control all counters" -
   _$ /START="@sys$startup:net$startup" -
   _$ /STOP="@sys$manager:net$shutdown"
```

This command adds the network service DECnet-Plus (Phase V) to the database, with the specified characteristics.

```
2. $ SET NETWORK "TCP/IP" /REGISTER -
   _$ /MANUFACTURER="Hewlett-Packard Company" -
   _$ /NODE="ipv6.ucx.mars.univers.com" -
   _$ /ADDRESS="16.20.207.92" -
   _$ /NETWORK_TYPE="TCP/IP" -
   _$ /STATUS="TCPIP SHOW SERVICE" -
   _$ /CONNECTIONS="TCPIP SHOW DEVICE" -
   _$ /PPPD_CALLOUT="TCPIP$PPPD_CALLOUT"
```

This command creates a new TCP/IP network service, adds it to the database, and enables the PPPD utility by supplying a logical name that identifies the location of the shareable image.

```
3. $ SET NETWORK DECnet -
   _$ /MANUFACTURER= "Hewlett-Packard Company" -
   _$ /NODE="EMARET" -
   _$ /ADDRESS="12.378" -
   _$ /NETWORK_TYPE="DNA IV" -
   _$ /INTERFACE="net 0" -
   _$ /STATUS="mcr ncp show exec characteristics" -
   _$ /CONNECTIONS="mcr ncp show known link" -
   _$ /COUNTERS="mcr ncp show exec count" -
   _$ /START="@sys$manager:startnet" -
```

```
_$_ /STOP="mcr ncp set executor state shut"
```

This command adds the network service DECnet (Phase IV) to the database, with the specified characteristics.

## SET ON

**SET ON** — Enables error checking by the command interpreter after the execution of each command in a command procedure. Specify **SET NOON** to disable error checking.

### Format

**SET [NO]ON**

### Parameters

None.

### Description

During the execution of command procedures, the command interpreter normally checks the status code returned when a DCL command or program image completes and saves the numeric value of this code in the reserved symbol named \$STATUS. The low-order 3 bits of this value are also saved in the reserved symbol \$SEVERITY. Command procedure execution aborts when either an error or fatal error is detected.

Use the **SET NOON** command to override default error checking. When **SET NOON** is in effect, the command interpreter continues to place the status code value in \$STATUS and the severity level in \$SEVERITY, but does not perform any action based on the values. As a result, the command procedure continues to execute no matter how many errors are returned.

---

### Exception

If you use a **CALL**, **GOSUB**, or **GOTO** command and specify a label that does not exist in the current command procedure, the procedure issues a warning message and exits.

---

The **SET ON** or **SET NOON** command applies only at the current command level. If you use the **SET NOON** command in a command procedure that executes another procedure, the default, **SET ON**, is established while the second procedure executes.

### Example

```
$ SET NOON
$ DELETE *.SAV;*
$ SET ON
$ COPY *.OBJ *.SAV
```

This command procedure routinely copies all object modules into new files with the file type .SAV. The **DELETE** command first deletes all existing files with the .SAV file type, if any. The **SET NOON** command ensures that the procedure continues executing even if there are no files with the .SAV file type in the current directory. Following the **DELETE** command, the **SET ON** command restores error checking. Then the **COPY** command makes copies of all existing files with .OBJ file type.

# SET OUTPUT\_RATE

SET OUTPUT\_RATE — Sets the rate at which output is written to a batch job log file. **For use only within command procedures that are submitted as batch or detached jobs.**

## Format

**SET OUTPUT\_RATE**[=*delta-time*]

## Parameter

*delta-time*

The time interval at which output is written from the output buffer to the batch job log file. If no delta time is specified, the information is written in the output buffer to the log file, but the output rate is not changed from the default of once per minute. Specify *delta-time* as [dddd-][hh:mm:ss.cc]. For more information on delta time, see the relevant section in the [VSI OpenVMS User's Manual \[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\\_AND\\_TIME\\_SECT\]](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) or the online help topic Date.

## Description

When you submit a batch job, the output to be written to the log file is stored in an output buffer. Periodically, the buffer is flushed and its contents are written to the batch job log file. By default, the buffer is flushed once a minute; therefore, you can type the log file to determine how much of the job has completed while the job is still executing.

To change the default output rate, include the **SET OUTPUT\_RATE** command in the command procedure that you are submitting as a batch job. When the **SET OUTPUT\_RATE** command is executed within a batch job and a delta time is specified, DCL flushes the buffer, sets the default output rate, and starts a new output interval.

If the **SET OUTPUT\_RATE** command is executed within a batch job and a delta time is not specified, DCL flushes the buffer but does not change the default output rate and does not start a new interval.

If you issue the **SET OUTPUT\_RATE** command interactively, or within a command procedure that is executed interactively, then no action is performed.

## Example

```
$ SET OUTPUT_RATE=:0:30
.
.
.
```

This command, when executed within a batch job, changes the default output rate from once a minute to once every 30 seconds.

# SET PASSWORD

SET PASSWORD — Changes a password or system password. Also, can establish a secondary password or system password, or remove a secondary password. **See the qualifier descriptions for restrictions.**

## Format

**SET PASSWORD**

## Parameters

None.

## Description

All user accounts on a system have passwords. A password is required for logging in to the system.

To maintain secrecy, users should change their passwords from time to time. The **SET PASSWORD** command offers a means of making this change.

A system manager can control which users have the right to change their passwords, and can establish a minimum password length and the maximum period of time that a password can remain unchanged. The OpenVMS system automatically screens passwords against a dictionary and a history list to prevent the use of native language words or the reuse of old passwords. A system manager can add words readily associated with the site to the dictionary, thus disallowing them as passwords.

Systems can also have passwords (not to be confused with the password associated with the **SYSTEM** account). The system manager uses the **SET PASSWORD/SYSTEM** command to change the system password from time to time.

A user password can contain up to 32 alphanumeric and special characters. Unless your system manager has set the **PWDMIX** flag in your authorization account record, the only special characters permitted are the dollar sign (\$) and underscore (\_). Without the **PWDMIX** authorization, all lowercase characters are converted to uppercase before the password is encrypted. For example, "eagle" is the same as "EAGLE".

If you have **PWDMIX** authorization, you can specify uppercase and lowercase alphabetic characters, and you can use any special characters in the printable character set. However, avoid using characters that have special significance for layered products that accept passwords. For example, a double quotation mark (") would be unacceptable in a password in a DECnet access control string.

---

## Note

Blank spaces are permissible within a password, but they are not considered part of the password, and OpenVMS ignores them. For example, "MY PASSWORD" is an acceptable password, but the system only records "MYPASSWORD." This means that "MYPA SSWORD" is also a valid password for the account in question.

A password that contains blank spaces will fail in contexts where spaces have meaning. For example, the syntax of an access control string assumes there is one and only one space, preceding the password, for example:

```
$ DIR JULY04"JEFFERSON PRESIDENT": :TEST.SDML
```

If you enter the following command, it will fail:

```
$ DIR JULY04"JEFFERSON PRE SIDENT": :TEST.SDML
```

---

Use the following procedure to change your password:

1. Enter the **SET PASSWORD** command.
2. The system prompts you for your current password. Enter your current password.
3. The system prompts you for a new password. Enter a new password, or press Return to disable your current password.
4. The system prompts you to verify the password. Enter the new password to verify. (If the two entries of the new password do not match, the password does not change.)

The following guidelines are recommended to minimize the chances of passwords being discovered by trial-and-error or by exhaustive search:

- Make passwords at least 6 characters long.
- Avoid names or words that are readily associated with you.
- Change your passwords at least once every month.

To ensure that the previous guidelines are met, use the **/GENERATE[=value]** qualifier. This qualifier generates random passwords of up to 12 characters in length. The system manager can require individual users to use generated passwords. For more information about this, see the description of the Authorize utility's **/GENERATE\_PASSWORD** qualifier in the *VSI OpenVMS System Management Utilities Reference Manual, Volume 1: A-L* [[https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-i-a-l/#AUTHORIZE\\_PART](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-i-a-l/#AUTHORIZE_PART)].

## External Authentication

If external authentication is enabled on your system and user accounts in the SYSUAF file are marked for external authentication, those users are authenticated using their external user IDs and passwords.

When a user has logged in using external authentication, the **SET PASSWORD** command attempts to notify the external authentication service of any password change. The following messages are displayed when this takes place:

```
%SET-I-SNDEXTAUTH, Sending password request to external authenticator
%SET-I-TRYPWDSYNCH, Attempting password synchronization
```

If the external authentication service cannot be contacted or the password change is rejected, an error message is displayed to the user:

```
%SET-E-EXTPWDERR, Password could not be set by external authenticator
```

If the user was not externally authenticated but the EXTAUTH flag is set (the user logged in with **/LOCAL\_PASSWORD**), the new password is only set locally in the SYSUAF file (normal OpenVMS password policy checks do not apply in this case).

## Qualifiers

### **/ALGORITHM=keyword**

Selects a specific password generation algorithm.

The **/ALGORITHM** qualifier requires the **/GENERATE** qualifier.

The valid keywords for this qualifier are the following:

- **ALPHABETIC** – Selects the alphabetic password generator. (Formerly the only password generator).
- **MIXED\_CHARACTER** – Selects the mixed-character password generator. Mixed-character passwords are valid only for users with the PwdMix flag set in their user authorization records.

These keywords are mutually exclusive and cannot be negated.

#### **/GENERATE[=*value*]**

Generates a list of five random passwords. Press Return to repeat the procedure until a suitable password appears.

*Value* is a number from 1 to 10 that restricts the length of the password. For any value *n*, the **SET PASSWORD** command generates passwords of from *n* to (*n*+2) characters long.

If no value is specified, **SET PASSWORD** uses a default value of 6, and generates passwords from 6 to 8 characters long. Values greater than 10 are not accepted and produce errors.

If your system manager has established a minimum password length for your account, **SET PASSWORD/GENERATE=*n*** compares that length with the optional value specified with the **/GENERATE** qualifier, and uses the larger of the two values. If you do not specify a value with the **/GENERATE** qualifier, the account minimum length is used.

---

### **Note**

If the **SET PASSWORD/GENERATE** command fails to work properly, consult your system manager to be sure that either the file SYS\$LIBRARY:VMS\$PASSWORD\_DICTIONARY.DATA exists, or the logical name VMS\$PASSWORD\_DICTIONARY is correctly defined.

---

#### **/SECONDARY**

Creates or allows you to replace a secondary password. The procedure is the same as setting your primary password.

Once a secondary password has been established, you will receive two PASSWORD: prompts when logging in. The primary password should be typed in first, followed by the secondary password.

Secondary passwords make it possible to set up an account that requires two different people to access it. Each person knows one of the two passwords, and both passwords are required to log in successfully.

To remove your secondary password, press **Return** when **SET PASSWORD/SECONDARY** prompts you for a new password and verification. After you do this, you will receive a single PASSWORD: prompt when logging in. If you remove the secondary password, your system manager must restore it.

The **/SECONDARY** and **/SYSTEM** qualifiers are incompatible.

#### **/SYSTEM**

Requires the SECURITY privilege.

Changes the system password rather than a user password.

A system password can be from 0 to 32 alphanumeric characters. The dollar sign (\$) and underscore (\_) are also permitted. Uppercase and lowercase characters are equivalent. All lowercase characters are converted to uppercase before the password is encrypted.

A system password is valid only for the node it is set on. In an OpenVMS Cluster, each node can have a different system password.

If a terminal line has the system password (SYSPWD) characteristic set, no terminal prompts are sent to that terminal until the system password is entered.

The **/SYSTEM** and **/SECONDARY** qualifiers are incompatible. For more information about the use of system passwords, see the relevant section in the *VSI OpenVMS Guide to System Security* [[https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#SETTING\\_SYST\\_PWDS](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#SETTING_SYST_PWDS)].

## Example

```
$ SET PASSWORD
Old password: HONCHO
New password: BIG_ENCHILADA
Verification: BIG_ENCHILADA
```

In response to the **SET PASSWORD** command, the system first prompts for the old password and then for the new password. The system then prompts again for the new password to verify it. The password changes if the user is authorized to change this account's password, if the old password is given correctly, and if the new password is given identically twice; otherwise, an error message appears and the password remains unchanged.

In a real session, neither the old password nor the new password and its verification appear on the screen or paper.

## SET PREFERRED\_PATH

**SET PREFERRED\_PATH** — Access to a MSCP/TMSCP class device may be available to an OpenVMS node from more than one host or storage controller. Use the **SET PREFERRED\_PATH** command to specify a particular host or preferred path to access a specific MSCP class disk or TMSCP class tape device.

## Format

**SET PREFERRED\_PATH** *device-name*:

## Parameter

*device-name*:

Specifies the name of a MSCP class disk or TMSCP class tape device.

## Description

If a preferred path is specified, the normal OpenVMS path selection process is modified to select the user-specified path over other available paths, assuming the user-specified path is available.

This command is only meaningful for MSCP/TMSCP class devices that have more than one path available.

## Qualifiers

### **/HOST=***host\_name*

Tells the MSCP/TMSCP class driver that you want this host to be the preferred access path to the specified device. The class driver remembers this host name until it is changed by taking one of the following actions:

- Issuing another **SET PREFERRED\_PATH** command specifying a different host
- Using the **/NOHOST** qualifier
- Rebooting the system

Note that simply specifying a preferred path does not mean that it is immediately selected if the disk or tape device is currently using another path. Use the **/FORCE** qualifier along with the **/HOST** qualifier to force the preferred path to be used immediately.

The *host\_name* is the name of the host that will be the preferred path to the disk or tape device.

### **/FORCE**

Tells the class driver to initiate the path selection process immediately. If this qualifier is omitted when a new host name is specified, a switch from the current path to the new preferred path will not occur until some other event initiates the path selection process.

### **/NOHOST**

Clears any previously defined preferred path assignment. Restores usual OpenVMS path selection behavior.

## Examples

1. `$ SET PREFERRED_PATH $10$DUA10: /HOST=HSC014`

Prior to issuing this command, the `$10$DUA10:` disk device has host HSC015 as its primary path and host HSC014 as its secondary path. Issuing this command selects host HSC014 as the preferred path.

Note that the preferred path has been recorded by the class driver; however, the disk will remain on the current path (HSC015) until the next time the path selection process is initiated.

2. `$ SET PREFERRED_PATH $10$DUA10: /HOST=HSC014 /FORCE`

To make the path change occur immediately, include the **/FORCE** qualifier on the command line with the preferred path specification.

3. `$ SET PREFERRED_PATH $10$DUA10: /FORCE`

Issue this command to initiate path selection processing if the specified device has a primary path that differs from the preferred path.

If the preferred path is available, the device moves to that path.

4. `$ SET PREFERRED_PATH $10$DUA10: /NOHOST`

Remove the specified preferred path by using the **/NOHOST** qualifier if the device should no longer have a preferred path.

## SET PREFIX

SET PREFIX — Allows you to set a prefix control string for verified command lines.

### Format

**SET** [**NO**]**PREFIX***string*

### Parameter

*string*

Specifies the FAO control string to be used in generating a prefix to a verified command line. The following rules apply:

- No more than 64 characters are allowed in the control string.
- The resulting string can be no longer than 64 characters.
- Basic formatting FAO directives can be used ("!", "\_", "^", "!", "%F", and "n\*c").
- Time and date FAO directives can be used ("!%T" and "!%D").
- Repeat counts can be used ("!n(DD)").
- Output field length specifications can be used ("!lengthDD").
- Combination of repeat count and output field length can be used("!n(lengthDD)").
- FAO directives that require arguments will always receive a value of zero.

### Description

The **SET PREFIX** command allows you to prefix verified command lines with a custom string. This string is a limited FAO control string that specifies date and time information as well as constant information and formatting controls (that is, tabs, form feeds, and so on). For example, this allows you to use a full date and time prefix (a time stamp) to identify batch runs and to verify that a batch job ran at the expected time.

See the documentation on the F\$FAO lexical function in the [VSI OpenVMS DCL Dictionary: A–M](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#d0e33542) [<https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#d0e33542>] for more information about FAO control strings.

The first line of a verified command is prefixed with the result of the control string. The control string is evaluated before the command itself is executed. Any continuation lines are prefixed with a blank string in order to make them flush with the first line of the command. Command input and output are not prefixed. The prefix control string can later be retrieved by using **VERIFY\_PREFIX** with **F\$ENVIRONMENT**.

## Example

```
$
SET VERIFY
$
@TEST
$ SET DEFAULT SYS$LOGIN
$ SHOW DEFAULT
  USER$: [JENSEN]
$
SET PREFIX "(!5%T) "
$
@TEST
(17:52) $ SET DEFAULT SYS$LOGIN
(17:52) $ SHOW DEFAULT
  USER$: [JENSEN]
```

This example demonstrates the difference between having and not having a prefix for verification. The first command turns on verification. (Verification must be turned on to see the prefix.) The second command invokes a test procedure to show what the output looks like without a prefix. The third and fourth lines reflect the contents of the test procedure invoked in the preceding command. The third command sets the prefix to an FAO control string so that the first five characters of the standard time will be shown for each command. The last command invokes the test procedure again to demonstrate what the output looks like with a prefix.

## SET PRINTER

**SET PRINTER** — Establishes the characteristics of a specific line printer. The default values listed for qualifiers to the **SET PRINTER** command are the defaults for an initially bootstrapped system. **Requires OPER (operator) privilege. If the printer is a spooled device, LOG\_IO (logical I/O) privilege is required to modify its characteristics.**

### Format

```
SET PRINTER printer-name[:]
```

### Parameter

*printer-name*[:]

Specifies the name of a line printer to set or modify its characteristics.

### Qualifiers

**/CR**

**/NOCR (default)**

Controls whether the printer driver outputs a carriage return character. Use this qualifier for printers on which line feeds do not imply carriage returns.

Specify the **/NOCR** qualifier for printers where the line feed, form feed, vertical feed, and carriage return characters empty the printer buffer. The **/NOCR** qualifier causes carriage return characters to be held back and output only if the next character is not a form feed or vertical tab. Carriage return characters are always output on devices that have the carriage return function characteristic set.

**/FALLBACK****/NOFALLBACK (default)**

Determines whether the printer attempts to translate characters belonging to the DEC Multinational character set into 7-bit equivalent representations. If a character cannot be translated, an underscore ( \_ ) character is substituted.

If the **/PASSALL** qualifier is in effect, it has precedence over the **/FALLBACK** qualifier.

**/FF (default)****/NOFF**

Indicates whether the printer performs a mechanical form feed. Use the **/NOFF** qualifier when the printer does not automatically perform mechanical form feeds. This qualifier allows the driver to convert form feeds into multiple line feeds and to output them.

**/LA11**

Specifies the printer as an LA11. This qualifier provides information for the **SHOW PRINTER** command, which, in turn, provides the user with information about specific printers. If no printer type is specified, LP11 is assumed.

**/LA180**

Specifies the printer as an LA180. This qualifier provides information for the **SHOW PRINTER** command, which, in turn, provides the user with information about specific printers. If no printer type is specified, LP11 is assumed.

**/LOG****/NOLOG (default)**

Determines whether information confirming the printer setting is displayed at the terminal from which the **SET PRINTER** command was entered.

**/LOWERCASE****/NOLOWERCASE**

Indicates whether the printer prints both uppercase and lowercase letters or only uppercase. When the operator specifies the **/NOLOWERCASE** qualifier, all letters are translated to uppercase.

The **/[NO]LOWERCASE** and **/[NO]UPPERCASE** qualifiers are complementary; that is, the **/LOWERCASE** qualifier is equivalent to the **/NOUPPERCASE** qualifier, and the **/NOLOWERCASE** qualifier is equivalent to the **/UPPERCASE** qualifier.

**/LP11 (default)**

Specifies the printer as an LP11. This qualifier provides information for the **SHOW PRINTER** command, which, in turn, provides the user with information about specific printers. LP11 is the default printer type.

**/PAGE=*lines-per-page***

Establishes the number of lines per page on the currently installed form; the number of lines can range from 1 to 255 and defaults to 64. The printer driver uses this value to determine the number of line feeds that must be entered to simulate a form feed.

**/PASSALL****/NOPASSALL (default)**

Controls whether the system interprets special characters or passes them as 8-bit binary data.

If you specify the **/PASSALL** qualifier, the printer driver does not expand tab characters to spaces, fill carriage return or line feed characters, or recognize control characters.

**/POLLED****/NOPOLLED (default)**

Instructs the LRDRIVER to run in polled mode instead of interrupt mode.

In polled mode, the printer is checked on a regular basis to determine if it is ready to receive additional data. The polling timer runs only while there is more data to be sent to the printer.

**/PRINTALL****/NOPRINTALL (default)**

Controls whether the line printer driver outputs printable 8-bit multinational characters.

**/RESET**

Resets the USB pipe associated with the USB printer, thereby canceling all print jobs.

**/TAB****/NOTAB (default)**

Controls how the printer handles TAB characters. The **/NOTAB** qualifier expands all tab characters to spaces and assumes tab stops at 8-character intervals.

Use the **/TAB** qualifier when you do not want the system to convert tabs to spaces, but want the printer to process the tab characters. The OpenVMS system requires that printers expand tabs at 8-character intervals.

**/TRUNCATE (default)****/NOTRUNCATE**

Controls whether the printer truncates data exceeding the value specified by the **/WIDTH** qualifier. Note that the **/TRUNCATE** and **/WRAP** qualifiers are incompatible.

**/UNKNOWN**

Specifies the printer as nonstandard. This qualifier provides information for the **SHOW PRINTER** command, which, in turn, provides the user with information about specific printers. If no printer type qualifier is specified, LP11 is assumed.

**/UPPERCASE****/NOUPPERCASE**

Indicates whether the printer prints both uppercase and lowercase letters or only uppercase ones. When you specify the **/UPPERCASE** qualifier, all letters are translated to uppercase.

The **/[NO]UPPERCASE** and **/[NO]LOWERCASE** qualifiers are complementary; that is, the **/UPPERCASE** qualifier is equivalent to the **/NOLOWERCASE** qualifier, and the **/NOUPPERCASE** qualifier is equivalent to the **/LOWERCASE** qualifier.

**/WIDTH=*n***

Establishes the number of characters per output line on currently installed forms. The width, *n*, can range from 0 to 65535 for LP11 controllers, and from 0 to 255 for DMF32 controllers. The default value is 132 characters per line.

**/WRAP****/NOWRAP (default)**

Controls whether the printer generates a carriage return and a line feed when it reaches the end of a line.

If the **/NOWRAP** qualifier is specified, the printer writes characters out in the last position on the line.

If the **/WRAP** qualifier is specified, the terminal generates a carriage return and a line feed whenever the end of a line is reached.

Note that the **/TRUNCATE** and **/WRAP** qualifiers are incompatible.

## Examples

1. \$ SET PRINTER/PAGE=60/WIDTH=80 LPA0:

The **SET PRINTER** command in this example establishes the size of an output page as 60 lines and the width of a line as 80 characters for printer LPA0.

2. \$ SET PRINTER/LA11 LPB0:

The **SET PRINTER** command in this example establishes the line printer LPB0 as an LA11 printer.

3. \$ SET PRINTER/LOWERCASE LPA0:

The **SET PRINTER** command in this example requests that lowercase printing be enabled on line printer LPA0.

## SET PROCESS

**SET PROCESS** — Changes the execution characteristics associated with the specified processor kernel thread for the current terminal session or job. If no process is specified, changes are made to the current process. **Requires GROUP privilege to change other processes in the same group. Requires WORLD privilege to change processes outside your group.**

### Format

**SET PROCESS** [*process-name*]

### Parameter

*process-name*

Requires that you own the process or that you have GROUP privilege and that the process is in your group.

Specifies the name of the process for which the characteristics are to be changed. Process names can be up to 23 alphanumeric characters long in the following format:

*[node-name::]process-name*

- The node name can have as many as 6 alphanumeric characters.
- The colons (:) count for 2 characters.
- The process name can have as many as 15 characters.

A local process name can look like a remote process name; therefore, if you specify ATHENS::SMITH, the system checks for a process named ATHENS::SMITH on the local node before checking node ATHENS for a process named SMITH.

The default process is the current process.

Process names are unique only within a particular UIC group. You cannot specify the process name for a process outside of your group. To change the characteristics of a process outside of your group, you must use the qualifier **/IDENTIFICATION=pid**. The process name parameter is ignored. If you include neither the process name nor the **/IDENTIFICATION** qualifier, the current process is assumed.

## Qualifiers

**/AFFINITY (Alpha/Integrity servers only)**

**/NOAFFINITY**

Allows bits in the kernel thread affinity mask to be set or cleared individually, in groups, or all at once. This qualifier is mutually exclusive with the **/CAPABILITY** qualifier.

---

### Note

The **SET PROCESS/[NO]AFFINITY** command fails if none of the specified CPUs has the capabilities required by the process.

---

The **/NOAFFINITY** qualifier clears all affinity bits currently set in the current or permanent affinity masks, based on the setting of the **/PERMANENT** qualifier. Specifying the **/AFFINITY** qualifier has no direct effect, but merely indicates the target of the operations specified by the following secondary qualifiers:

| Qualifier                    | Description                                                                                                                                                                                                                               |
|------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>/SET=(n[ , . . . ])</b>   | Sets affinity for currently active CPUs defined by the CPU IDs <i>n</i> , where <i>n</i> has the range of 0 to 31.                                                                                                                        |
| <b>/CLEAR=(n[ , . . . ])</b> | Clears affinity for currently active CPUs defined by the position values <i>n</i> , where <i>n</i> has the range of 0 to 31.                                                                                                              |
| <b>/PERMANENT</b>            | Performs the operation on the permanent affinity mask as well as the current affinity mask, making the changes valid for the life of the kernel thread. (The default behavior is to affect only the affinity mask for the running image.) |

The secondary qualifiers can all be used at once as long as the affinity bits defined in the **/SET** and **/CLEAR** parameters do not overlap.

The privileges required to execute the **SET PROCESS/AFFINITY** command match those required by the \$PROCESS\_AFFINITY system service. ALTPRI is the base privilege required to make any modifications, and the only privilege required to modify the current owner's kernel thread. Modifications within the same UIC group require GROUP privilege. Modifications to any unrelated kernel thread require WORLD privilege.

As with the other **SET PROCESS** qualifiers, the bit operations occur on the current process if no **/IDENTIFICATION** qualifier or explicit process name parameter is specified. Specifying a process name does not imply that all kernel threads associated with the process are affected; the **SET PROCESS** command affects only the initial kernel thread of a multithreaded process.

**/AUTO\_UNSHELVE**  
**/NOAUTO\_UNSHELVE**

Controls whether the process automatically unshelves files.

Note that the **/NOAUTO\_UNSHELVE** qualifier does not work across a cluster. It can be issued only for a process on the same node, including as the default case, the process from which the command is issued.

**/CAPABILITY**  
**/NOCAPABILITY**

Allows bits in the process user capability mask to be set or cleared individually, in groups, or all at once. This qualifier is mutually exclusive with the **/AFFINITY** qualifier.

---

## Note

The **SET PROCESS/[NO]CAPABILITY** command fails if there is no CPU with the required set of capabilities.

---

The **/NOCAPABILITY** qualifier clears all user capability bits currently set in the current or permanent capability masks, based on the setting of the **/PERMANENT** qualifier. Specifying the **/CAPABILITY** qualifier has no direct effect, but merely indicates the target of the operations specified by the following secondary qualifiers:

| Qualifier                    | Description                                                                                                                                                                                                                                                 |
|------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>/SET=(n[ , . . . ])</b>   | Sets all user capabilities defined by the position values <i>n</i> , where <i>n</i> has the range of 1 to 16.                                                                                                                                               |
| <b>/CLEAR=(n[ , . . . ])</b> | Clears all user capabilities defined by the position values <i>n</i> , where <i>n</i> has the range of 1 to 16.                                                                                                                                             |
| <b>/PERMANENT</b>            | Performs the operation on the permanent user capability mask as well as the current user capability mask, making the changes valid for the life of the kernel thread. (The default behavior is to affect only the capabilities mask for the running image.) |

The secondary qualifiers can all be used at once as long as the user capability bits defined in the **/SET** and **/CLEAR** parameters do not overlap.

The privileges required to execute the **SET PROCESS/CAPABILITY** command match those required by the \$PROCESS\_CAPABILITIES system service. ALTPRI is the base privilege required

to make any modifications, and the only privilege required to modify the current owner's kernel thread. Modifications within the same UIC group require GROUP privilege. Modifications to any unrelated kernel thread require WORLD privilege.

As with the other **SET PROCESS** qualifiers, the bit operations occur on the current process if no **/IDENTIFICATION** qualifier or explicit process name parameter is specified. Specifying a process name does not imply that all kernel threads associated with the process are affected; the **SET PROCESS** command affects only the initial kernel thread of a multithreaded process.

#### ***/CASE\_LOOKUP=keyword***

The valid keywords for this qualifier are BLIND and SENSITIVE.

VSI strongly recommends that you use caution when enabling case sensitivity in your processes.

See the [Guide to OpenVMS File Applications \[https://docs.vmssoftware.com/guide-to-openvms-file-applications/\]](https://docs.vmssoftware.com/guide-to-openvms-file-applications/) for additional information.

#### ***/CLEAR=(n[,...])***

Clears all user capabilities or CPU affinities defined by the position values *n* specified by the **/CAPABILITY** or the **/AFFINITY** qualifier.

#### ***/DUMP[=NOW] [/ID=pid] [process-name]*** ***/NODUMP (default)***

Causes the contents of the address space to be written to the file named (image-name).DMP in the current default directory (where the image name is the same as the file name) when an image terminates because of an unhandled error. To specify a target process, indicate either the process ID or the process name.

Using the NOW option (available on Alpha and Integrity server systems only) causes the targeted process to dump as soon as possible. This is especially useful for hung processes.

You can then analyze the dump with the **ANALYZE/PROCESS\_DUMP** utility, the Debugger, or the System Dump Analyzer (SDA).

#### ***/GLOBAL***

Modifies the global cell SCH\$GL\_DEFAULT\_PROCESS\_CAP. This global cell is used to initialize the user capability mask of processes when they are started.

#### ***/IDENTIFICATION=pid***

Requires GROUP or WORLD privilege for processes other than your own.

Specifies the process identification (PID) value of the kernel thread for which characteristics are to be changed. The target process must be on the same node as the process from which the command is issued. The **/IDENTIFICATION** qualifier overrides the *process-name* parameter.

The PID is assigned by the system when the process is created. When you specify a PID, you can omit the leading zeros.

If you use the **/IDENTIFICATION** qualifier, the *process-name* parameter is ignored.

## Note

The **/IDENTIFICATION** qualifier allows the **SET PROCESS** command to affect individual kernel thread PIDs; because each thread is a separate runnable entity, this command treats them as discrete entities in terms of affinities and capabilities.

### **/KERNEL\_THREAD\_LIMIT=*n***

Changes the limit of the number of kernel threads that can be created in the process. If the value specified is higher than the SYSGEN parameter MULTITHREAD, an error message is returned. Specifying the value 0 makes the process use the systemwide limit set by the MULTITHREAD parameter.

Per-process kernel thread limits can be controlled using one of the following DCL commands:

```
$ SET PROCESS/KERNEL_THREAD_LIMIT=n
$ RUN/KERNEL_THREAD_LIMIT=n
$ SPAWN/KERNEL_THREAD_LIMIT=n
```

### **/NAME=*string***

Changes the name of the current process to a string of 1 to 15 characters.

### **/PARSE\_STYLE=(*keyword*)**

Allows a user to indicate how commands are to be parsed.

Setting a particular parse style tells DCL how it should handle command syntax. User programs can also examine the state of this setting if they need to use different parse rules.

The valid keywords for this qualifier are TRADITIONAL and EXTENDED. These keywords are mutually exclusive and cannot be negated.

If the **/PARSE\_STYLE** qualifier is not specified, the default is the TRADITIONAL format.

| Keyword                                 | Description                                                                                              |
|-----------------------------------------|----------------------------------------------------------------------------------------------------------|
| TRADITIONAL (default)                   | Indicates that commands should be examined using the former (prior to Version 7.2) rules for DCL syntax. |
| EXTENDED (Alpha/Integrity servers only) | Indicates that commands should be examined using a syntax that allows ODS-5 file specifications.         |

The main differences for DCL when EXTENDED parse rules are in effect are:

- Arguments to foreign commands are case preserved. You can get the command string by calling LIB\$GET\_FOREIGN.

C/C++ programs that use the argc/argv mechanism will have unquoted arguments in lowercase unless the C Run-Time Library logical DECC\$ARGV\_PARSE\_STYLE is set to ENABLE. When DECC\$ARGV\_PARSE\_STYLE is enabled, case is preserved in command line arguments when the process is set up for extended DCL parsing using **/PARSE\_STYLE=EXTENDED**.

- Some characters that were previously treated as token delimiters are no longer delimiters. The pound sign (#), circumflex (^), and question mark (?) fall into this category.
- A circumflex (^) is an escape character, which can be used to indicate that the next character in the command string is to be treated as if it were quoted, thereby losing its syntactic significance.

EXTENDED parsing also modifies DCL's rules for parsing a parameter or qualifier that is defined as a file specification in a command's definition:

- File specifications will not be in uppercase.
- Any number of commas (,) may be placed between directory delimiters ([] and <>).
- Directory file ID's (DIDs) can be included in the file specification.
- Any number of periods (.) or semi-colons (;) may be included in the file specification.

See the *VSI OpenVMS System Manager's Manual, Volume 1: Essentials* [<https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/>] for more information.

### **/PERMANENT**

Performs the operation on the permanent affinity or capability mask as well as the current mask, making the changes valid for the life of the kernel thread. (The default behavior is to affect the current mask only for the running image.) The **/PERMANENT** qualifier is only valid in conjunction with the **/CAPABILITY** or the **/AFFINITY** qualifier.

### **/PRIORITY=*n***

Requires ALTPRI (alter priority) privilege to set the priority higher than the base priority of the specified process.

Changes the priority for the specified kernel thread. If you do not have the ALTPRI privilege, the value you specify is compared to your current base priority, and the lower value is always used.

### **/PRIVILEGES=(*privilege*[,...])**

Requires SETPRV (set privilege) privilege as an authorized privilege to enable any privilege you do not have in your authorized privilege mask.

Enables the following process privileges:

|         |          |           |          |
|---------|----------|-----------|----------|
| ACNT    | ALLSPOOL | ALTPRI    | AUDIT    |
| BUGCHK  | BYPASS   | CMEXEC    | CMKRNL   |
| DETACH  | DIAGNOSE | DOWNGRADE | EXQUOTA  |
| GROUP   | GRPNAM   | GRPPRV    | IMPORT   |
| LOG_IO  | MOUNT    | NETMBX    | OPER     |
| PFNMAP  | PHY_IO   | PRMCEB    | PRMGBL   |
| PRMMBX  | PSWAPM   | READALL   | SECURITY |
| SETPRV  | SHARE    | SHMEM     | SYSGBL   |
| SYSLCK  | SYSNAM   | SYSPRV    | TMPMBX   |
| UPGRADE | VOLPRO   | WORLD     |          |

Use the **SHOW PROCESS/PRIVILEGES** command to determine what authorized privileges are enabled currently.

### **/RAD=HOME=*n***

Changes the home resource affinity domain (RAD) of a process.

This command only works on the current process.

RAD is supported on AlphaServer GS series systems and starting from OpenVMS Version 8.4, support is extended to NUMA capable Integrity servers.

## **/RESOURCE\_WAIT** **/NORESOURCE\_WAIT**

Enables resource wait mode so that the process waits for resources to become available. If you specify the **/NORESOURCE\_WAIT** qualifier, the process receives an error status code when system dynamic memory is not available or when the process exceeds one of the following resource quotas: direct I/O (DIOLM) limit, buffered I/O (BIOLM) limit, buffered I/O byte (BYTLM) count limit (buffer space), timer queue quota, mailbox buffer quota, or pipe quota.

### **Caution**

Disabling resource waiting should be performed with caution, as doing so can have unexpected effects on constituent sharable images and runtime libraries. See the \$SETRWM service in the *VSI OpenVMS System Services Reference Manual: GETUTC-Z* [[https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-getutc-z/#JUN\\_518](https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-getutc-z/#JUN_518)] for additional information.

## **/RESUME**

Allows a process suspended by a previous **SET PROCESS/SUSPEND** command to resume operation. The **/RESUME** qualifier is equivalent to the **/NOSUSPEND** qualifier.

## **/SCHEDULING\_CLASS= "class\_name"** **/NOSCHEDULING\_CLASS**

Adds a process to, or removes a process from, a scheduling class. This command does not modify the permanent class scheduling database file. Therefore, the effect of this command can be viewed as temporary placement into, or removal from, a scheduling class.

## **/SET=(n[,...])**

Sets all user capabilities or CPU affinities defined by the position values *n* specified by the **/CAPABILITY** or the **/AFFINITY** qualifier.

## **/SSLOG=(STATE={ON | OFF | UNLOAD} [,COUNT=*n*][,FLAGS=[NO]ARG])**

Valid on Alpha and Integrity server systems only.

Requires CMEXEC, CMKRNL, or SETPRV privilege to log argument values. The SYSGEN parameter SYSSER\_LOGGING must be enabled or the command will fail.)

Enables or disables system service logging, using a log file (named SSLOG.DAT by default) to log data.

Keywords are as follows:

| Keyword         | Description                                                                                                                  |
|-----------------|------------------------------------------------------------------------------------------------------------------------------|
| COUNT= <i>n</i> | Specifies how many P2-space buffers to log. (Default: 2)                                                                     |
| FLAGS=[NO]ARG   | Specifies whether service argument values are to be logged. (Default: ARG) ARG requires CMEXEC, CMKRNL, or SETPRV privilege. |

| Keyword             | Description                                                                  |
|---------------------|------------------------------------------------------------------------------|
| STATE= <i>state</i> | Turns system service logging on or off. Possible states are:                 |
| ON                  | Enables system service logging.                                              |
| OFF                 | Disables (turns off) system service logging; logging can still be reenabled. |
| UNLOAD              | Stops logging and closes the log file, which is named SSLOG.DAT by default.  |

When enabling SSLOG for a process, you can specify the number of buffers to be used for logging. Buffers are allocated in P2 space and are charged against the process's paging file quota. Each buffer is 65,024<sub>10</sub> bytes or FE00<sub>16</sub> bytes. The buffer space remains allocated and the quota is charged until the process is deleted.

Between the time when SSLOG is first enabled and when the log file is closed, logging can be stopped and resumed.

Before you delete the process, you should stop all logging and close the log file. The log file does not close automatically.

To analyze the log file, use the DCL command **ANALYZE/SSLOG**, which is described in online help and in the relevant section in the [VSI OpenVMS System Analysis Tools Manual \[https://docs.vmssoftware.com/vsi-openvms-system-analysis-tools-manual/#CHAPT14\]](https://docs.vmssoftware.com/vsi-openvms-system-analysis-tools-manual/#CHAPT14).

**/SUSPEND[=SUPERVISOR]**

**/SUSPEND=KERNEL**

**/NOSUSPEND**

Requires privileges as described in text.

Temporarily stops the process's activities. The process remains suspended until another process resumes or deletes it. Use the qualifiers **/NOSUSPEND** and **/RESUME** to resume a suspended process.

Specify either of the following keywords with the **/SUSPEND** qualifier to produce different results:

| Keyword                 | Description                                                                                                                                                                                                                                                                                                                                                                                                |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| SUPERVISOR<br>(default) | Specifies that the named process is to be suspended to allow the delivery of asynchronous system traps (ASTs) at EXEC or KERNEL mode. Specifying this keyword is optional.                                                                                                                                                                                                                                 |
| KERNEL                  | Specifies that the named process is to be suspended such that no ASTs can be delivered. To specify the KERNEL keyword, you must be in either KERNEL mode or EXEC mode, or have CMKRNL (change mode to kernel) and CMEXEC (change mode to executive) privilege enabled. Note that this was the default behavior of the <b>SET PROCESS/SUSPEND</b> command for versions of OpenVMS prior to VMS Version 5.0. |

Depending on the operation, the process from which you specify the **/SUSPEND** qualifier requires privileges. You must have GROUP privilege to suspend another process in the same group, unless that process has the same user identification code (UIC). You must have WORLD privilege to suspend any other process in the system.

When you enter the **SET PROCESS/SUSPEND=KERNEL/ID=** command in a cluster environment, the KERNEL keyword is ignored if the target process and the current process reside

on different cluster nodes. As a result, process suspension is handled as if you had specified the **SUPERVISOR** keyword (the default).

Note that you can specify **SET PROCESS/SUSPEND=KERNEL** to override a previous **SET PROCESS/SUSPEND=SUPERVISOR**. **SET PROCESS/SUSPEND=SUPERVISOR** does not, however, override **SET PROCESS/SUSPEND=KERNEL**.

### **/SWAPPING (default)**

#### **/NOSWAPPING**

Requires the PSWAPM (process swap) privilege to disable swapping for your process.

Permits the process to be swapped. By default, a process that is not currently executing can be removed from physical memory so that other processes can execute. If you specify the **/NOSWAPPING** qualifier, the process is not swapped out of the balance set when it is in a wait state.

### **/SYMLINK=keyword**

Controls the behavior of all directory wildcard searches used in the RMS\$SEARCH service. Note that these directory wildcards are not overridden by command qualifiers or other explicit RMS characteristics. Keyword options are:

| <b>Keyword</b> | <b>Description</b>                                                               |
|----------------|----------------------------------------------------------------------------------|
| NOWILDCARD     | Indicates that symlinks are disabled during directory wildcard searches.         |
| WILDCARD       | Indicates that symlinks are enabled during wildcard searches.                    |
| NOELLIPSIS     | Indicates that symlinks are matched for all wildcard fields except for ellipsis. |
| ELLIPSIS       | Equivalent to WILDCARD (included for command symmetry).                          |

On the command line, you can set a flag to select the **/SYMLINK** qualifier. It uses the keywords **DEFAULT**, **[NO]WILDCARD**, **[NO]ELLIPSIS**, and **[NO]TARGET**. In addition, **/SYMLINK** and **/NOSYMLINK** without any keywords are interpreted as **/SYMLINK=NOTARGET** and **/SYMLINK=TARGET**, respectively.

### **/TOKEN=keyword**

Changes the maximum size of tokens (elements) in a DCL command. (A token is any element in a command line that is bounded by spaces. For example, the command **COPY X.TXT Y.TXT** contains three tokens.) The token size is determined by the setting of bit 1 in the DCL\_CTLFLAGS system parameter. By default, the bit is clear, indicating that traditional tokens (255 bytes) are being used. If the bit is set, extended tokens (4000 bytes) are used. The corresponding key words for **/TOKEN** are **TRADITIONAL** and **EXTENDED**. You can use **SHOW PROCESS/TOKEN** to determine the current token size setting.

### **/UNITS[=keyword]**

Specifies whether the amount of disk space reported by certain utilities is to be displayed in blocks or bytes. Keyword options are:

| <b>Keyword</b> | <b>Description</b>             |
|----------------|--------------------------------|
| BLOCKS         | Displays disk space in blocks. |
| BYTES          | Displays disk space in bytes.  |

Blocks is the default until **/UNITS** is set to BYTES. If you specify **/UNITS** with no keyword, disk space is reported in blocks.

Displays that are affected by changing the value of **/UNITS** include output from certain forms of the following commands: **COPY**, **DELETE**, **DIRECTORY**, **PURGE**, **SHOW DEVICE**, **SHOW MEMORY**, and **SHOW QUOTA**. Note that input to these commands can be specified only in blocks. The **DIRECTORY**, **SHOW DEVICES**, and **SHOW MEMORY** commands have a qualifier that lets you override the default **SET PROCESS/UNITS** setting for a single command.

## Examples

1. \$ SET PROCESS/PRIVILEGE=EXQUOTA

The **SET PROCESS** command in this example assigns the current process the privilege of exceeding quotas.

2. \$ SET PROCESS/NORESOURCE\_WAIT

The **SET PROCESS** command in this example disables resource wait mode for the current process.

3. \$ RUN/PROCESS\_NAME=TESTER CALC  
%RUN-S-PROC\_ID, identification of created process is 0005002F  
\$ SET PROCESS/PRIORITY=10 TESTER

The **RUN** command in this example creates a subprocess and gives it the name TESTER. Subsequently, the **SET PROCESS/PRIORITY** command assigns the subprocess a priority of 10.

4. \$ SHOW PROCESS/SUBPROCESS

```
19-APR-2001 15:17:28.41  User: DAVIS Process ID:   31900218
                          Node: OCALA  Process name: "DAVIS"
```

Processes in this tree:

```
DAVIS *
  DAVIS_1
  DAVIS_2
```

```
$ SET PROCESS/SUSPEND DAVIS_1
$
```

The **SET PROCESS/SUSPEND** command in this example suspends the process DAVIS\_1 such that ASTs can be delivered to it. Because no key word was specified, the **/SUSPEND=SUPERVISOR** version is assumed.

5. \$ SHOW PROCESS/SUBPROCESS OCALA::TESTA

```
19-APR-2001 12:17:24.45  User: TESTA    Process ID:   31400208
                          Node: OCALA    Process name:  "TESTA"
```

Processes in this tree:

```
TESTA *
  TESTA_1
  TESTA_2
$ SET PROCESS OCALA::TESTA_2 /SUSPEND=KERNEL
$
```

The **SET PROCESS/SUSPEND=KERNEL** command in this example suspends the process TESTA\_2 on node OCALA such that no ASTs can be delivered to it.

6. \$ SET PROCESS CPUSCHED/AFFINITY/SET=1/PERMANENT  
\$ SET PROCESS CPUSCHED/CAPABILITY/SET=8/PERMANENT  
\$ SHOW CPU/FULL  
COBRA7, a DEC 4000 Model 620  
Multiprocessing is ENABLED. Streamlined synchronization image loaded.  
Minimum multiprocessing revision levels: CPU = 1

System Page Size = 8192  
System Revision Code =  
System Serial Number =  
Default CPU Capabilities:  
    System:            QUORUM RUN  
Default Process Capabilities:  
    System:            QUORUM RUN

PRIMARY CPU = 00

CPU 00 is in RUN state  
Current Process: \*\*\* None \*\*\*  
Serial Number: AY24870417  
Revision: A200  
VAX floating point operations supported.  
IEEE floating point operations and data types supported.  
Processor is Primary Eligible.  
PALCODE: Revision Code = 5.48  
    PALcode Compatibility = 0  
    Maximum Shared Processors = 2  
    Memory Space: Physical address = 00000000 00000000  
                    Length = 0  
    Scratch Space: Physical address = 00000000 00000000  
                    Length = 0

Capabilities of this CPU:  
    System:            PRIMARY QUORUM RUN  
    User bitmask:      00000040  
Processes which can only execute on this CPU:  
    NETACP            PID = 0000008E            Reason: PRIMARY Capability

CPU 01 is in RUN state  
Current Process: CPUSCHED            PID = 00000095  
Serial Number: AY24870406  
Revision: A200  
VAX floating point operations supported.  
IEEE floating point operations and data types supported.  
PALCODE: Revision Code = 5.48  
    PALcode Compatibility = 0  
    Maximum Shared Processors = 2  
    Memory Space: Physical address = 00000000 00000000  
                    Length = 0  
    Scratch Space: Physical address = 00000000 00000000  
                    Length = 0

Capabilities of this CPU:  
    System:            QUORUM RUN  
    User bitmask:      00000080  
Processes which can only execute on this CPU:

```
CPUSCHED    PID = 00000095 Reason: Affinitized to this CPU
                                     Reason: User capabilities - 00000080)

$ SET PROCESS/NOAFFINITY/PERMANENT
$ SET PROCESS/NOCAPABILITY/PERMANENT
$ SHOW CPU/FULL
COBRA7, a DEC 4000 Model 620
Multiprocessing is ENABLED. Streamlined synchronization image loaded.
Minimum multiprocessing revision levels: CPU = 1

System Page Size = 8192
System Revision Code =
System Serial Number =
Default CPU Capabilities:
    System:          QUORUM RUN
Default Process Capabilities:
    System:          QUORUM RUN

CPU 00 is in RUN state
Current Process: *** None ***
Serial Number:  AY24870417
Revision:       A200
VAX floating point operations supported.
IEEE floating point operations and data types supported.
Processor is Primary Eligible.
PALCODE: Revision Code = 5.48
    PALcode Compatibility = 0
    Maximum Shared Processors = 2
    Memory Space:  Physical address = 00000000 00000000
                      Length = 0
    Scratch Space: Physical address = 00000000 00000000
                      Length = 0
Capabilities of this CPU:
    System:          PRIMARY QUORUM RUN
    User bitmask:    00000040
Processes which can only execute on this CPU:
    NETACP          PID = 0000008E Reason: PRIMARY Capability

CPU 01 is in RUN state
Current Process: CPUSCHED          PID = 00000095
Serial Number:  AY24870406
Revision:       A200
VAX floating point operations supported.
IEEE floating point operations and data types supported.
PALCODE: Revision Code = 5.48
    PALcode Compatibility = 0
    Maximum Shared Processors = 2
    Memory Space:  Physical address = 00000000 00000000
                      Length = 0
    Scratch Space: Physical address = 00000000 00000000
                      Length = 0
Capabilities of this CPU:
    System:          QUORUM RUN
    User bitmask:    00000080
Processes which can only execute on this CPU:
    *** None ***

$ SET PROCESS/NOAFFINITY/PERMANENT
$ SET PROCESS/NOCAPABILITY/PERMANENT
```

```

$ SHOW CPU/FULL
System: EUROS, HPE rx2600 (900MHz/1.5MB) SMP execlet = 3 : Enabled :
Streamlined. Config tree = Version 6 Primary CPU = 0 HWRPB
CPUs = 2 Page Size = 8192 Revision Code = Serial Number
= US30464615 Default CPU Capabilities: System: QUORUM RUN
Default Process Capabilities: System: QUORUM RUNCPU 0
State: RUN CPUDB: 8901C000 Handle: 00005D70
Owner: 000004C8 Current: 000004C8 Partition 0
(EUROS) ChgCnt: 1 State: Present, Primary,
Reassignable Process: * None * Capabilities: System:
PRIMARY QUORUM RUN RAD0 User: Ustr2 Slot Context: 901EB000
CPU - State.....: RC, PA, PP, CV, PV, PMV, PL
Type.....: Itanium Major = 31, Minor = 0
Speed.....: 900 Mhz LID.....: 00000000
Variation.....: IEEE FP, Primary Eligible
Serial Number...: 0001a968930a1a25 Revision.....:
Halt Request...: 0 Software Comp...: 7.0
PALCODE - Revision Code...: 1.1 Compatibility...: 0
Max Shared CPUs: 0 Bindings: * None * Fastpath:
FGB0 PKA0 PEA0 EIA0 Features: Autostart
- Enabled. Fastpath - Selection enabled as Preferred CPU.CPU 1
State: RUN CPUDB: 89163480 Handle: 00005E80
Owner: 000004C8 Current: 000004C8 Partition 0 (EUROS)
ChgCnt: 1 State: Present, Reassignable
Process: TEST11 PID: 20201192 Capabilities: System:
QUORUM RUN RAD0 Slot Context: 901EC000 CPU - State.....:
RC, PA, PP, CV, PV, PMV, PL Type.....: Itanium
Major = 31, Minor = 0 Speed.....: 900 Mhz
LID.....: 01000000 Variation.....:
IEEE FP Serial Number...: 000363b4b0c5c862
Revision.....: Halt Request...: 0
Software Comp...: 7.0 PALCODE - Revision Code...: 1.1
Compatibility...: 0 Max Shared CPUs: 0 Bindings:
TEST11 PID = 20201192 Reason: Affinitized to this CPU
Fastpath: FGA0 EWA0 PKB0 BGO Features:
Autostart - Enabled. Fastpath - Selection enabled as Preferred
CPU.
$

```

In this example, CPU 1 has user capability 8 enabled (user mask = 80). User capability 8 is set for the initial kernel thread of process CPUSCHED, and CPU affinity is set to 1. Either of these settings forces the initial kernel thread to run only on CPU 1, as shown by the **SHOW PROCESS** command.

Then, the **SET PROCESS/NOAFFINITY/NOCAPABILITY** command clears all CPU affinities and user capability requirements for the initial kernel thread of process (CPUSCHED), and the binding to CPU 1 disappears.

#### 7. \$ SET PROCESS/SSLOG=(STATE=ON,COUNT=4)

This command turns on system service logging with four P2 space buffers, each having a size of FE00<sub>16</sub> bytes. If the process has SETPRV, CMKRNL, or CMEXEC privilege, argument values are logged.

#### 8. \$ SET PROCESS/SSLOG=(STATE=UNLOAD)

This command stops logging and closes the log file.

# SET PROMPT

SET PROMPT — Replaces the default DCL prompt (\$) with the specified string.

## Format

[=*string*]

## Parameter

*string*

Specifies the new prompt string. The following rules apply:

- All valid ASCII characters can be used.
- No more than 64 characters are allowed.
- To include spaces or lowercase letters, enclose the string in quotation marks (" "). Otherwise, letters are converted automatically to uppercase; leading and trailing spaces are removed.

If you do not specify the string parameter with the **SET PROMPT** command, the default DCL prompt (\$) is restored.

## Description

The **SET PROMPT** command customizes prompts for your main process or a subprocess.

When a continued command is read from the terminal or an indirect command is read from a command procedure, DCL places an underscore in front of the prompt string.

## Qualifier

**/CARRIAGE\_CONTROL (default)**

**/NOCARRIAGE\_CONTROL**

Inserts carriage return and line feed characters before the prompt string. Type the qualifier after the string parameter.

## Example

```
$ SET PROMPT ="What's next?"
What's next? SHOW TIME
 19-APR-2001 14:08:58
```

The **SET PROMPT** command in this example replaces the DCL prompt (\$) with the phrase What's next?. When you see the prompt on your screen, you can enter any DCL command. This example uses the **SHOW TIME** command.

# SET PROTECTION/DEFAULT

SET PROTECTION/DEFAULT — Establishes the default protection for files created by the current process.

## Format

[ = ( *code* ) ] /DEFAULT

## Parameter

### *code*

Specifies the category of protection to be assigned by default to all files subsequently created by the current process. To override this protection, you must specify an explicit protection using either the **SET SECURITY/PROTECTION** command or the **/PROTECTION** qualifier on the **CREATE** command. If you do not specify a protection code, the current default remains unchanged.

The protection code is made up of the following components:

- Ownership category – system (S), owner (O), group (G), or world (W). Each category can be abbreviated to its first character.
- Access category – Read (R), write (W), execute (E), or delete (D). The access category is assigned to each ownership category. A null access specification means no access.

---

## Note

Use the **SET SECURITY/PROTECTION** command to reset security characteristics of the directory or file.

---

## Example

```
$ SET PROTECTION=(GROUP:RWED,WORLD:R) /DEFAULT
```

The **SET PROTECTION/DEFAULT** command in this example sets the default protection to grant unlimited access to other users in the same group and read (R) access to all users. The default protections for system and owner are not changed.

# SET QUEUE

**SET QUEUE** — Changes the attributes of the specified queue. **Requires manage (M) access to the queue.**

## Format

**SET QUEUE** *queue-name* [ : ]

## Parameter

*queue-name* [ : ]

Specifies the name of an execution queue or a generic queue.

## Description

After you have created a queue with the **INITIALIZE/QUEUE** command, use the **SET QUEUE** command to change the queue's status or attributes.

The defaults for the **SET QUEUE** qualifiers depend on the qualifiers of the queue when it was initialized. For example, the default for **/JOB\_LIMIT** with **INITIALIZE/QUEUE** is 1. However, if the queue you are altering was initialized with a job limit of 3, and if you do not specify the **/JOB\_LIMIT** qualifier with the **SET QUEUE** command, the job limit remains at 3 for that queue.

## Qualifiers

### **/BASE\_PRIORITY=*n***

Specifies the base process priority at which jobs are initiated from a batch execution queue. The base priority specifier can be any decimal value from 0 to 15.

You also can specify this qualifier for an output execution queue. In this context the **/BASE\_PRIORITY** qualifier establishes the base priority of the symbiont process when the symbiont process is created.

### **/BLOCK\_LIMIT=(*[lowlim],[uplim]*)**

#### **/NOBLOCK\_LIMIT**

Limits the size of print jobs that can be processed on an output execution queue. This qualifier allows you to reserve certain printers for certain size jobs. You must specify at least one of the parameters.

The *lowlim* parameter is a decimal number referring to the minimum number of blocks that are accepted by the queue for a print job. If a print job is submitted that contains fewer blocks than the *lowlim* value, the job remains pending until the block limit for the queue is changed. After the block limit for the queue is decreased sufficiently, the job is processed.

The *uplim* parameter is a decimal number referring to the maximum number of blocks that are accepted by the queue for a print job. If a print job is submitted that exceeds this value, the job remains pending until the block limit for the queue is changed. After the block limit for the queue is increased sufficiently, the job is processed.

If you specify only an upper limit for jobs, you can omit the parentheses. For example, **/BLOCK\_LIMIT=1000** means that only jobs with 1000 blocks or less are processed in the queue. To specify only a lower job limit, you must use a null string (") to indicate the upper limit. For example, **/BLOCK\_LIMIT=( 500 , " " )** means any job with 500 or more blocks is processed in the queue. You can specify both a lower and upper limit. For example, **/BLOCK\_LIMIT=( 200 , 2000 )** means that jobs with less than 200 blocks or more than 2000 blocks are not processed in the queue.

The **/NOBLOCK\_LIMIT** qualifier cancels the previous block limit setting for that queue.

### **/CHARACTERISTICS= (*characteristic*[,...])**

#### **/NOCHARACTERISTICS**

Specifies one or more characteristics for processing jobs on an execution queue. If a queue does not have all the characteristics that have been specified for a job, the job remains pending. If you specify only one characteristic, you can omit the parentheses. Each time you specify the **/CHARACTERISTICS** qualifier, all previously set characteristics are canceled. Only the characteristics specified with the qualifier are established for the queue.

Queue characteristics are installation specific. The characteristic parameter can be either a value from 0 to 127 or a characteristic name that has been defined by the **DEFINE/CHARACTERISTIC** command.

The **/NOCHARACTERISTICS** qualifier cancels any characteristics settings previously established for that queue.

## **/CLOSE**

Prevents jobs from being entered in the queue through **PRINT** or **SUBMIT** commands or as a result of requeue operations. To allow jobs to be entered, use the **/OPEN** qualifier. Whether a queue accepts or rejects new job entries is independent of the queue's state (such as paused, stopped, or stalled). When a queue is marked closed, jobs executing continue to execute and jobs pending in the queue continue to be candidates for execution.

## **/CPUDEFAULT=time**

Defines the default CPU time limit for jobs in a batch execution queue. You can specify time as delta time, 0, INFINITE, or NONE. You can specify up to 497 days of delta time.

If the queue does not have a defined CPUMAXIMUM time limit and the value established in the user authorization file (UAF) has a specified CPU time limit of NONE, either the value 0 or the keyword INFINITE allows unlimited CPU time. If you specify NONE, the CPU time value defaults to the value specified either in the UAF or by the **SUBMIT** command (if included). CPU time values must be greater than or equal to the number specified by the system parameter PQL\_MCPULM. The time cannot exceed the CPU time limit set by the **/CPUMAXIMUM** qualifier. For information on specifying delta time, see the relevant section in the *VSI OpenVMS User's Manual* [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\\_AND\\_TIME\\_SECT](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT)] or the online help topic Date. For more information on specifying CPU time limits, see the "CPU Time Limit Specifications and Actions" table for the **INITIALIZE/QUEUE** command in the *VSI OpenVMS DCL Dictionary: A-M* [[https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\\_119](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_119)].

## **/CPUMAXIMUM=time**

Defines the maximum CPU time limit for all jobs in a batch execution queue. You can specify time as delta time, 0, INFINITE, or NONE. You can specify up to 497 days of delta time.

The **/CPUMAXIMUM** qualifier overrides the time limit specified in the user authorization file (UAF) for any user submitting a job to the queue. Either the value 0 or the keyword INFINITE allows unlimited CPU time. If you specify NONE, the CPU time value defaults to the value specified either in the UAF or by the **SUBMIT** command (if included). CPU time values must be greater than or equal to the number specified by the system parameter PQL\_MCPULM.

For information on specifying delta time, see the relevant section in the *VSI OpenVMS User's Manual* [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\\_AND\\_TIME\\_SECT](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT)] or the online help topic Date. For more information on specifying CPU time limits, see the "CPU Time Limit Specifications and Actions" table for the **INITIALIZE/QUEUE** command in the *VSI OpenVMS DCL Dictionary: A-M* [[https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\\_119](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_119)].

## **/DEFAULT=(option[,...])**

### **/NODEFAULT**

Establishes defaults for certain options of the **PRINT** command. Defaults are specified by the list of options. If you specify only one option, you can omit the parentheses. After you set an option for the queue with the **/DEFAULT** qualifier, you do not have to specify that option in your **PRINT** commands. If you do specify these options in your **PRINT** command, the values specified with the **PRINT** command override the values established for the queue with the **/DEFAULT** qualifier. Possible options are as follows:

| Option                         | Description                                                                                                                                                                                                                                                                                                                                            |
|--------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| [NO]BURST[= <i>keyword</i> ]   | Controls whether two file flag pages with a burst bar between them are printed preceding output. If you specify the value ALL (default), these flag pages are printed before each file in the job. If you specify the value ONE, these flag pages are printed once before the first file in the job.                                                   |
| [NO]FEED                       | Specifies whether a form feed is inserted automatically at the end of a page.                                                                                                                                                                                                                                                                          |
| [NO]FLAG[= <i>keyword</i> ]    | Controls whether a file flag page is printed preceding output. If you specify the value ALL (default), a file flag page is printed before each file in the job. If you specify the value ONE, a file flag page is printed once before the first file in the job.                                                                                       |
| FORM= <i>type</i>              | Specifies the default form for an output execution queue. If a job is submitted without an explicit form definition, this form is used to process the job. If no form type is explicitly specified with the FORM keyword, the system assigns the form "DEFAULT" to the queue. See also the description of the <a href="#">/FORM MOUNTED</a> qualifier. |
| [NO]TRAILER[= <i>keyword</i> ] | Controls whether a file trailer page is printed following output. If you specify the value ALL (default), a trailer page is printed with each file in the job. If you specify the value ONE, a trailer page is printed once with the last file in the job.                                                                                             |

When you specify the BURST option for a file, the [NO]FLAG option does not add or subtract a flag page from the two flag pages that are printed preceding the file.

For information on establishing mandatory queue attributes, see the description of the [/SEPARATE](#) qualifier. For information on specifying default queue attributes, see the relevant section in the [VSI OpenVMS System Manager's Manual, Volume 1: Essentials](#) [[https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#\\_6017QUEUE\\_MGR](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#_6017QUEUE_MGR)].

**/DESCRIPTION=*string***  
**/NODESCRIPTION**

Specifies a string of up to 255 characters used to provide operator-supplied information about the queue.

Enclose strings containing lowercase letters, blanks, or other non alphanumeric characters (including spaces) in quotation marks (" ").

The **/NODESCRIPTION** qualifier removes any descriptive text that may have been associated with the queue.

**/DISABLE\_SWAPPING**  
**/NODISABLE\_SWAPPING**

Controls whether batch jobs executed from a queue can be swapped in and out of memory.

**/ENABLE\_GENERIC**  
**/NOENABLE\_GENERIC**

Specifies whether files queued to a generic queue that does not specify explicit queue names can be placed in this execution queue for processing.

**/FORM\_MOUNTED=*type***

Specifies the mounted form for an output execution queue.

If no form type is explicitly specified, the system assigns the form "DEFAULT" to the queue.

If the stock of the mounted form does not match the stock of the default form, as indicated by the **/DEFAULT=FORM** qualifier, all jobs submitted to this queue without an explicit form definition enter a pending state and remain pending until the stock of the queue's mounted form is identical to the stock of the form associated with the job.

If a job is submitted with an explicit form and the stock of the explicit form is not identical to the stock of the mounted form, the job enters a pending state and remains pending until the stock of the mounted form of the queue is identical to the stock of the form associated with the job.

To specify the form type, use either a numeric value or a form name that has been defined by the **DEFINE/FORM** command. Form types are installation-specific. You cannot use the **/FORM\_MOUNTED** qualifier with the **/GENERIC** qualifier.

**/JOB\_LIMIT=*n***

Indicates the number of batch jobs that can be executed concurrently from the queue. Specify a number in the range 1 to 65535.

**/NO\_INITIAL\_FF****/NONO\_INITIAL\_FF (default)**

Allows user to set or modify whether a form feed should be sent to a printer device when a queue starts. To suppress the initial form feed, set the queue with **/NO\_INITIAL\_FF** qualifier.

Setting the queue with **/NONO\_INITIAL\_FF** qualifier sends a form feed to the output device before printing begins when the queue restarts.

**/OPEN**

Allows jobs to be entered in the queue through **PRINT** or **SUBMIT** commands or as the result of requeue operations. To prevent jobs from being entered in the queue, use the **/CLOSE** qualifier. Whether a queue accepts or rejects new job entries is independent of the queue's state (such as paused, stopped, or stalled).

**/OWNER\_UIC=*uic***

Requires OPER (operator) privilege or control (C) access to the queue.

Enables you to change the user identification code (UIC) of the queue. Specify the UIC by using the standard format as described in the relevant section in the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC_SECTION) [\[https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC\\_SECTION\]](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC_SECTION).

**/PROTECTION= (*ownership[:access]*,...)**

Requires OPER (operator) privilege to control access to the queue.

Specifies the protection of the queue. The following rules apply:

- Specify the *ownership* parameter as system (S), owner (O), group (G), or world (W).

- Specify the *access* parameter as read (R), submit (S), manage (M), or delete (D). A null access specification means no access.

If you include only one protection code, you can omit the parentheses.

For more information on specifying protection codes, see the relevant section in the *VSI OpenVMS Guide to System Security* [[https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#PROTECT\\_CODE\\_DETAILS](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#PROTECT_CODE_DETAILS)]. For more information on controlling queue operations through UIC-based protection, see the relevant section in the *VSI OpenVMS System Manager's Manual, Volume 1: Essentials* [<https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#SECURITY>].

**/RAD=*n***

**/NORAD**

Specifies the RAD number on which to run batch jobs assigned to the queue. The RAD value is validated as a positive integer between 0 and the value returned by the \$GETSYI item code, SYI\$\_RAD\_MAX\_RADS.

To eliminate the RAD value for a batch queue, use the **/NORAD** qualifier.

Note that when you change the RAD value on a batch queue, the jobs currently in the batch queue are not dynamically updated with the new RAD value. Any executing jobs will complete processing using the original RAD value. Jobs in the pending, holding, or timed execution states will retain the old RAD value on the job; however, when such a job becomes executable, the job is updated with the new RAD value.

RAD is supported on AlphaServer GS series systems and starting from OpenVMS Version 8.4, support is extended to NUMA capable Integrity servers.

**/RECORD\_BLOCKING**

**/NORECORD\_BLOCKING**

Determines whether the symbiont can concatenate (or block together) output records for transmission to the output device. If you specify the **/NORECORD\_BLOCKING** qualifier, the symbiont sends each formatted record in a separate I/O request to the output device. For the standard OpenVMS system print symbiont, record blocking can have a significant performance advantage over single-record mode.

**/RETAIN[=*option*]**

**/NORETAIN**

Holds jobs in the queue in a retained status after they have executed. The **/NORETAIN** qualifier enables you to reset the queue to the default. Possible options are as follows:

| Option | Description                                                |
|--------|------------------------------------------------------------|
| ALL    | Holds all jobs in the queue after execution (default).     |
| ERROR  | Holds in the queue only jobs that complete unsuccessfully. |

**/SCHEDULE=[NO]SIZE**

Specifies whether pending jobs in an output queue are scheduled for printing based on the size of the job. When the **/SCHEDULE=SIZE** qualifier is in effect, shorter jobs print before longer ones.

When the **/SCHEDULE=NOSIZE** qualifier is in effect, jobs are printed in the order they were submitted, regardless of size.

If you enter this command while there are pending jobs in any queue, its effect on future jobs is unpredictable.

**/SEPARATE=(option[,...])**  
**/NOSEPARATE**

Specifies the mandatory queue attributes or job separation options for an output execution queue. Job separation options cannot be overridden by the **PRINT** command.

The job separation options are as follows:

| Option                   | Description                                                                                                                                                                                                                                                                                                                                                                                                                              |
|--------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| [NO]BURST                | Specifies whether two job flag pages with a burst bar between them are printed at the beginning of each job.                                                                                                                                                                                                                                                                                                                             |
| [NO]FLAG                 | Specifies whether a job flag page is printed at the beginning of each job.                                                                                                                                                                                                                                                                                                                                                               |
| [NO]RESET=(module[,...]) | Specifies one or more device control library modules that contain the job reset sequence for the queue. The specified modules from the queue's device control library (by default SYS\$LIBRARY:SYSDEVCTL) are used to reset the device each time a job reset occurs. The RESET sequence occurs after any file trailer and before any job trailer; therefore, all job separation pages are printed when the device is in its RESET state. |
| [NO]TRAILER              | Specifies whether a job trailer page is printed at the end of each job.                                                                                                                                                                                                                                                                                                                                                                  |

When you specify the **/SEPARATE=BURST** qualifier, the [NO]FLAG separation option does not add or subtract a flag page from the two flag pages that are printed preceding the job.

For information on establishing queue attributes that can be overridden, see the description of the **/DEFAULT** qualifier.

For more information on specifying mandatory queue attributes, see the relevant section in the *VSI OpenVMS System Manager's Manual, Volume 1: Essentials* [[https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#CHOOSE\\_OPTIONS](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#CHOOSE_OPTIONS)].

**/WSDEFAULT=n**

Defines for a batch job a working set default, the default number of physical pages that the job can use.

The value set by this qualifier overrides the value defined in the user authorization file (UAF) of any user submitting a job to the queue.

Specify the value of *n* as a number of 512-byte pagelets on Alpha. Note that the OpenVMS system rounds up this value to the nearest CPU-specific page so that actual amount of physical memory allowed may be larger than the specified amount on Alpha.

If you specify the value 0 or NONE, the working set default value defaults to the value specified in the UAF or by the **SUBMIT** command (if included).

For more information about the way a working set default affects batch jobs, see *Table 6, "Working Set Default, Extent, and Quota Decision"*.

### **/WSEXTENT=*n***

Defines for the batch job a working set extent, the maximum amount of physical memory that the job can use. The job uses the maximum amount of physical memory only when the system has excess free pages. The value set by this qualifier overrides the value defined in the user authorization file (UAF) of any user submitting a job to the queue.

Specify the value of *n* as a number of 512-byte pagelets on Alpha. Note that the OpenVMS system rounds up this value to the nearest CPU-specific page so that actual amount of physical memory allowed may be larger than the specified amount on Alpha.

If you specify the value 0 or NONE, the working set extent value defaults to the value specified in the UAF or by the **SUBMIT** command (if included).

For more information about the way a working set extent affects batch jobs, see *Table 6, "Working Set Default, Extent, and Quota Decision"*.

### **/WSQUOTA=*n***

Defines for a batch job the working set quota, the amount of physical memory that is available to the job. The value set by this qualifier overrides the value defined in the user authorization file (UAF) of any user submitting a job to the queue.

Specify the value of *n* as a number of 512-byte pagelets on Alpha systems. Note that the OpenVMS system rounds up this value to the nearest CPU-specific page so that actual amount of physical memory allowed may be larger than the specified amount on Alpha. If you specify the value 0 or NONE, the working set quota value defaults to the value specified in the UAF or by the **SUBMIT** command (if included).

A working set default size and a working set quota (maximum size) are included in each user record in the system user authorization file (UAF). You can specify a working set default and a working set quota for both individual jobs and for all jobs in a given queue. The decision table (*Table 6, "Working Set Default, Extent, and Quota Decision"*) shows the action taken for different combinations of specifications that involve working set size and working set quota values.

**Table 6. Working Set Default, Extent, and Quota Decision**

| Value Specified by the SUBMIT Command? | Value Specified for the Queue? | Action Taken                                                     |
|----------------------------------------|--------------------------------|------------------------------------------------------------------|
| No                                     | No                             | Use the UAF value.                                               |
| No                                     | Yes                            | Use the value for the queue.                                     |
| Yes                                    | Yes                            | Use the smaller of the two values.                               |
| Yes                                    | No                             | Compare the specified value with the UAF value; use the smaller. |

## **Examples**

1. \$ INITIALIZE/QUEUE/DEFAULT=BURST/FORM\_MOUNTED=LETTER/START SYS\$PRINT

```
.  
.  
$ STOP/QUEUE/NEXT SYS$PRINT  
$ SET QUEUE/DEFAULT=BURST/FORM_MOUNTED=MEMO SYS$PRINT
```

In this example, the queue is initialized with the **INITIALIZE/QUEUE** command. The queue has the following attributes: two file flag pages preceding each file in the job and the mounted form LETTER. Later the queue is stopped with the **STOP/QUEUE/NEXT** command so that the current job finishes processing before the queue stops. The **SET QUEUE** command changes the mounted form to MEMO.

2. \$ SET QUEUE/DEFAULT=FORM=LN01\_PORTRAIT LN01\_PRINT

In this example, the **SET QUEUE** command changes the default form to LN01\_PORTRAIT for the LN01\_PRINT queue.

3. \$ SET QUEUE/CLOSE SYS\$BATCH

In this example, the batch queue SYS\$BATCH is modified to prevent jobs from being entered in this queue.

4. \$ SET/QUEUE/RAD=0 BATCHQ1  
\$ SHOW QUEUE/FULL BATCHQ1  
Batch queue BATCHQ1, idle, on QUEBID::  
/BASE\_PRIORITY=4 /JOB\_LIMIT=3 /OWNER=[SYSTEM]  
/PROTECTION=(S:M,O:D,G:R,W:S) /RAD=0

This example modifies the batch queue to run all assigned jobs on RAD 0 of QUEBID. Any new jobs assigned to the queue will run on RAD 0. Jobs already executing on the queue will continue to completion executing on the previous RAD value.

5. \$ SET/QUEUE/NORAD BATCHQ1  
\$ SHOW QUEUE/FULL BATCHQ1  
Batch queue BATCHQ1, idle, on QUEBID::  
/BASE\_PRIORITY=4 /JOB\_LIMIT=3 /OWNER=[SYSTEM]  
/PROTECTION=(S:M,O:D,G:R,W:S)

This example eliminates the RAD value for a batch queue.

## SET RESTART\_VALUE

**SET RESTART\_VALUE** — Assigns a value to the global symbol BATCH\$RESTART. This global symbol defines the location at which a batch job is restarted after its execution has been interrupted. The **SET RESTART\_VALUE** command is meaningful only in command procedures.

### Format

**SET RESTART\_VALUE=string**

### Parameter

*string*

Specifies a string of up to 255 characters, which specifies the label at which the batch job should begin executing when it is restarted.

## Description

Use the **SET RESTART\_VALUE** command in restartable command procedures. (A restartable command procedure is a command procedure that is submitted to run in batch mode with the **SUBMIT/RESTART** command.) **SET RESTART\_VALUE** assigns a value to the global symbol **BATCH\$RESTART**, the location at which the batch job should be restarted after its execution has been interrupted.

When writing a restartable command procedure, begin each possible starting point in the command procedure with a label. After the label, use the **SET RESTART\_VALUE** command to assign the symbol **BATCH\$RESTART** to equal the label. If the batch job is interrupted by a system crash and is then restarted, the command procedure can resume execution at the label pointed to by **BATCH\$RESTART**.

The **SET RESTART\_VALUE** command is used in conjunction with the reserved global symbol **\$RESTART**. **\$RESTART** is a special symbol that is maintained by the system and cannot be deleted. **\$RESTART** has the value **TRUE** if the batch job has been restarted; otherwise, **\$RESTART** has the value **FALSE**.

At the beginning of a restartable command procedure, test the value of the reserved global symbol **\$RESTART**. If **\$RESTART** is true, execute a **GOTO** statement using the symbol **BATCH\$RESTART** as the transfer label. If a **SET RESTART\_VALUE** command was not executed before the batch job was interrupted, the symbol **BATCH\$RESTART** has no definition and the batch job should restart from the beginning.

Most of your process environment is not maintained when the system fails. The only symbols maintained across a system failure are **\$RESTART** and **BATCH\$RESTART**; therefore, you should redefine any symbols or process logical names used in your command procedure after each **SET RESTART\_VALUE** command.

If a command procedure has **SET RESTART\_VALUE** commands in it, but you want the job to restart at the beginning, enter the **SET ENTRY/NOCHECKPOINT** command to delete the global symbol **BATCH\$RESTART**.

## Example

```
$ IF $RESTART THEN GOTO 'BATCH$RESTART'
.
.
.
$ FIRSTPART:
$ SET RESTART_VALUE = FIRSTPART
$ RUN PART1
.
.
.
$ SECONDPART:
$ SET RESTART_VALUE = SECONDPART
$ RUN PART2
.
.
.
```

In this example, the first command states that, if **\$RESTART** is true, the procedure is to jump to the value contained in **BATCH\$RESTART**. (**\$RESTART** is true only if the job has been executed before, that is, the job is being rerun after a crash or after having been queued.)

The first **SET RESTART\_VALUE** command assigns the label `FIRSTPART` to be equal to the symbol `BATCH$RESTART`. The next line contains the command to run `PART1 . EXE`.

The second **SET RESTART\_VALUE** command assigns the label `SECONDPART` to be equal to the symbol `BATCH$RESTART`. The last line shown contains the command to run `PART2 . EXE`.

When the job is first submitted using the **SUBMIT/RESTART** command, the value of `$RESTART` is `FALSE`, so the **IF** expression is ignored. If the job is stopped during the run of `PART1 . EXE`, the value of `BATCH$RESTART` is `FIRSTPART`. When the job is restarted, the value of `$RESTART` is `TRUE`; therefore, the **IF** expression is processed and transfers control to the `FIRSTPART` label in the procedure. `PART1 . EXE` is rerun.

If the job is stopped during the run of `PART2 . EXE`, the value of `BATCH$RESTART` is `SECONDPART`. When the job is restarted, the value of `$RESTART` is `TRUE`. In this instance, the **IF – GOTO** command transfers control to the `SECONDPART` label in the procedure so that `PART2 . EXE` can be run. `PART1 . EXE` is not rerun.

## SET RIGHTS\_LIST

**SET RIGHTS\_LIST** — Allows users to modify the process or system rights list. You must specify either the **/DISABLE** or the **/ENABLE** qualifier with the **SET RIGHTS\_LIST** command.

### Format

```
SET RIGHTS_LIST id-name[,...]
```

### Parameter

*id-name*[,...]

Specifies identifiers to be added to or removed from the process or system rights list. The *id-name* parameter is a string of 1 to 31 alphanumeric characters, underscores (`_`), and dollar signs (`$`); each name must contain at least one nonnumeric character.

### Description

The **SET RIGHTS\_LIST** command modifies identifiers in your current process rights list, the rights list of another process on the system, or the system rights list. Use the following guidelines to determine which privileges are required for each case:

- Adding new identifiers or modifying existing identifiers in your process rights list that do not have the Dynamic attribute requires **CMKRNL** (change mode to kernel) privilege.
- Modifying the rights list of other processes on the system requires **CMKRNL** privilege and either **GROUP** or **WORLD** privilege.
- Modifying the system rights list requires both **CMKRNL** and **SYSNAM** (system logical name) privileges.
- Adding or removing more than ten identifiers using the **/ENABLE** qualifier or the **/DISABLE** qualifier in a single command invocation requires **CMKRNL** privilege. You must specify either the **/DISABLE** or the **/ENABLE** qualifier with the **SET RIGHTS\_LIST** command.

This command can also be used to add attributes to existing identifiers.

## Qualifiers

### **/ATTRIBUTES=(*keyword*[,...])**

Specifies attributes to be associated with the identifiers. Attributes may be added to new or existing identifiers. The following are valid keywords:

| Keyword   | Description                                                                                                                                                                                                                                                                              |
|-----------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DYNAMIC   | Allows unprivileged holders of the identifier to remove and to restore the identifier from the process rights list by using the DCL command <b>SET RIGHTS_LIST</b> .                                                                                                                     |
| NOACCESS  | Makes any access rights of the identifier null and void. If a user is granted an identifier with the No Access attribute, that identifier has no effect on the user's access rights to objects. This attribute is a modifier for an identifier with the Resource or Subsystem attribute. |
| RESOURCE  | Allows holders of an identifier to charge disk space to the identifier. Used only for file objects.                                                                                                                                                                                      |
| SUBSYSTEM | Allows holders of the identifier to create and maintain protected subsystems by assigning the Subsystem ACE to the application images in the subsystem. Used only for file objects.                                                                                                      |

To remove an attribute from the identifier, add a NO prefix to the attribute keyword. For example, to remove the Resource attribute, specify **/ATTRIBUTE=NORESOURCE**.

The default uses the current processes in the rights database. Use the command **SHOW PROCESS/RIGHTS** to see the attributes of the current process.

### **/DISABLE**

Removes the identifiers from the process or system rights list. You cannot use the **/DISABLE** qualifier with the **/ENABLE** qualifier. Note that removing more than ten identifiers in a single command invocation requires CMKRNL privilege.

### **/ENABLE**

Adds the identifiers to the process or system rights list. You cannot use the **/ENABLE** qualifier with the **/DISABLE** qualifier. Note that adding more than ten identifiers in a single command invocation requires CMKRNL privilege.

### **/IDENTIFICATION=*pid***

Specifies the process identification (PID) value of the process whose rights list is to be modified. The PID is assigned by the system when the process is created. When you specify a PID, you can omit the leading zeros.

If you specify the **/IDENTIFICATION** qualifier, you cannot use the **/PROCESS** qualifier. By default, if neither the **/IDENTIFICATION** nor the **/PROCESS** qualifier is specified, the current process is assumed. You cannot use the **/IDENTIFICATION** qualifier with the **/SYSTEM** qualifier.

### **/PROCESS[=*process-name*]**

Specifies the name of the process whose rights list is to be modified. The process name can contain from 1 to 15 alphanumeric characters.

If you specify the **/PROCESS** qualifier, you cannot use the **/IDENTIFICATION** qualifier. By default, if neither the **/PROCESS** nor the **/IDENTIFICATION** qualifier is specified, the current process is assumed.

You cannot use the **/PROCESS** qualifier with the **/SYSTEM** qualifier.

## **/SYSTEM**

Specifies that the desired operation (addition or removal of an identifier) be performed on the system rights list. You cannot use the **/SYSTEM** qualifier with the **/PROCESS** or the **/IDENTIFICATION** qualifier.

## **Examples**

1. `$ SET RIGHTS_LIST/ENABLE/ATTRIBUTES=RESOURCE MARKETING`

The **SET RIGHTS\_LIST** command in this example adds the **MARKETING** identifier to the process rights list of the current process. Specifying the **RESOURCE** attribute allows holders of the **MARKETING** identifier to charge resources to it.

2. `$ SET RIGHTS_LIST/ENABLE/SYSTEM PHYSICS101`  
`%SYSTEM-F-NOPRIV, insufficient privilege or object`  
`protection violation`  
`$ SET PROCESS/PRIVILEGES=(CMKRNL,SYSNAM)`  
`$ SET RIGHTS_LIST/ENABLE/SYSTEM PHYSICS101`

The **SET RIGHTS\_LIST** command in this example adds the **PHYSICS101** identifier to the system rights list. You must have both the **CMKRNL** (change mode to kernel) and **SYSNAM** (system logical name) privileges to modify the system rights list.

## **SET RMS\_DEFAULT**

**SET RMS\_DEFAULT** — Defines default values for multiblock and multibuffer counts, network transfer sizes, prolog level, extend quantity, and the query lock option used by OpenVMS Record Management Services (RMS) for file operations. If you set the default value for either the multiblock count or the multibuffer count at 0, RMS tries to use the process default value or the system default value, in that order. If these are set at 0, RMS uses a default value of 1. Defaults are set for sequential, relative, or indexed file organizations on a process-only basis, unless a systemwide basis is requested.

## **Format**

**SET RMS\_DEFAULT**

## **Parameters**

None.

## **Description**

Multiblocking and multibuffering of file operations can enhance the speed of I/O operations with RMS. The defaults set with the **SET RMS\_DEFAULT** command are applied for all file operations that do not specify explicit multiblock or multibuffer counts.

For more information on multiblock and multibuffer operations, see the [VSI OpenVMS System Services Reference Manual: A-GETUAI](https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-a-getuai/) [https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-a-getuai/].

For indexed files, the **SET RMS\_DEFAULT** command defines default prolog level options.

For sequential files, the **SET RMS\_DEFAULT** command defines default extensions. If a default extension is not specified in your program, the process or system default is used.

For network operations, the **SET RMS\_DEFAULT** command defines network buffer sizes for transfer.

## Qualifiers

### **/BLOCK\_COUNT=count**

Specifies a default multiblock count (0 to 127) for record I/O operations *only*, where *count* is the number of blocks to be allocated for each I/O buffer.

For more information on multiblock count, see the description of the RAB\$B\_MBC in the [VSI OpenVMS Record Management Services Reference Manual](https://docs.vmssoftware.com/vsi-openvms-record-management-services-reference-manual/#_100_RABB_MBCFIELD) [https://docs.vmssoftware.com/vsi-openvms-record-management-services-reference-manual/#\_100\_RABB\_MBCFIELD].

### **/BUFFER\_COUNT=count**

Specifies a default multibuffer count (0 to 255) for local file operations, where *count* is the number of buffers to be allocated. If you use the **/SYSTEM** qualifier to extend the default value systemwide, the maximum default value is 127.

When you use the **/BUFFER\_COUNT** qualifier, you can use the **/DISK**, **/INDEXED**, **/MAGTAPE**, **/RELATIVE**, **/SEQUENTIAL**, and **/UNIT\_RECORD** qualifiers to specify the types of file for which the default is to be applied. If the **/BUFFER\_COUNT** qualifier is specified without any of these qualifiers, the **/SEQUENTIAL** qualifier is assumed. If file type is not specified, the default is applied to sequential files.

For more information on multibuffer count, see the description of the RAB\$B\_MBF field in the [VSI OpenVMS Record Management Services Reference Manual](https://docs.vmssoftware.com/vsi-openvms-record-management-services-reference-manual/#_101_RABB_MBFIELD) [https://docs.vmssoftware.com/vsi-openvms-record-management-services-reference-manual/#\_101\_RABB\_MBFIELD].

### **/CONTENTION\_POLICY=keyword [/SYSTEM]**

Allows you to specify fairness under high contention conditions for write-shared files at the process or system level. Note that selecting this option may noticeably increase locking overhead.

This option is disabled by default.

In a mixed cluster environment with high contention for specific buckets, it is possible for accesses to write-shared files on nodes using read-mode global bucket locking to dominate access to a bucket. Nodes without this support might be denied timely access to the bucket.

Additionally, it is possible to observe comparable behavior on all OpenVMS versions when dealing with accesses to write-shared files without global buffers enabled. A similar fairness issue between lock conversions and new lock requests may be observed in which the new lock requests may remain ungranted for an extended period of time. Use the **/CONTENTION\_POLICY** qualifier to specify fairness under high contention conditions.

The following table lists valid PROCESS keywords (**/SYSTEM** not specified):

| Keyword                     | Description                                                                                                                                    |
|-----------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| NEVER                       | Never use the higher overhead option to improve fairness for any write-shared files accessed by this process; minimal overhead.                |
| SOMETIMES                   | Use this option for fairer bucket access (but higher overhead) to any write-shared files with global buffers enabled accessed by this process. |
| ALWAYS                      | Use this option for fairer bucket access (but higher overhead) to all write-shared files accessed by this process.                             |
| SYSTEM_DEFAULT<br>(default) | Use system setting. Note that this keyword is disallowed with <b>/SYSTEM</b> .                                                                 |

The following table lists valid SYSTEM keywords (**/SYSTEM** also specified):

| Keyword         | Description                                                                                                                                  |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------|
| NEVER (default) | Never use the higher overhead option to improve fairness for any write-shared files accessed on the system; minimal overhead.                |
| SOMETIMES       | Use this option for fairer bucket access (but higher overhead) to any write-shared files with global buffers enabled accessed on the system. |
| ALWAYS          | Use this option for fairer bucket access (but higher overhead) to all write-shared files accessed on the system.                             |

## **/DISK**

Applies the specified defaults to disk file operations. Values applied using the **/SEQUENTIAL** qualifier take precedence over values applied using the **/DISK** qualifier.

## **/EXTEND\_QUANTITY=*n***

Specifies the number of blocks *n* to extend a sequential file where *n* can range from 0 to 65535. If you do not specify the **/EXTEND\_QUANTITY** qualifier, RMS calculates its own extend value. The **/EXTEND\_QUANTITY** qualifier value is used when the program does not specify an extent quantity explicitly.

## **/INDEXED**

Applies the multibuffer default to indexed file operations.

## **/MAGTAPE**

Applies the multibuffer default to magnetic tape operations. Values applied using the **/SEQUENTIAL** qualifier take precedence over values applied using the **/MAGTAPE** qualifier.

## **/NETWORK\_BLOCK\_COUNT=*count***

Specifies a default block count (0 to 127) for network access to remote files, where *count* is the number of blocks to be allocated for each I/O buffer.

For remote file access, the buffer size is negotiated between RMS and the remote system's file access listener (FAL) with the smaller of the two sizes being selected.

Thus, the **/NETWORK\_BLOCK\_COUNT** value places an upper limit on the network buffer size that is used. It also places an upper limit on the largest record that may be transferred to or from

a remote file. The largest record must be less than or equal to 512\*network\_block\_count. (The network\_block\_count is in block units and the record is in byte units.)

If you omit the value or specify a value of 0, RMS uses the systemwide block count value. If this value is also 0, RMS uses a size of one block.

### **/PROLOG=*n***

Specifies a default prolog level for indexed files where acceptable values for *n* are 0, 2, or 3. If 0 (default) is specified, RMS sets an appropriate prolog level.

### **/QUERY\_LOCK=keyword [/SYSTEM]**

Enables or disables query locking at the process and system levels.

The following table lists valid PROCESS keywords (**/SYSTEM** not specified):

| Keyword                     | Description                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|-----------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DISABLE                     | Disable query locking for the duration of any file opens done by images within the process for any read (\$GET or \$FIND) record operations that have both RAB\$V_NLK (no lock) and RAB\$V_RRL (read-regardless) set in the RAB\$L_ROP field of the RAB (Record Access Block). Disabling query locking directs RMS not to make any calls to the lock manager for a read record operation just to find out whether a record is locked by another stream. |
| ENABLE                      | Use RMS's default record locking for images run within this process.                                                                                                                                                                                                                                                                                                                                                                                    |
| SYSTEM_DEFAULT<br>(default) | Use system setting. Note that this keyword is disallowed with <b>/SYSTEM</b> .                                                                                                                                                                                                                                                                                                                                                                          |

The following table lists valid SYSTEM keywords (**/SYSTEM** also specified):

| Keyword          | Description                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DISABLE          | Disable query locking for the duration of any file opens done by images on the system for any read (\$GET or \$FIND) record operations that have both RAB\$V_NLK (no lock) and RAB\$V_RRL (read-regardless) set in the RAB\$L_ROP field of the RAB (Record Access Block). Disabling query locking directs RMS not to make any calls to the lock manager for a read record operation just to find out whether a record is locked by another stream. |
| ENABLE (default) | Use RMS's default record locking for images run within this process.                                                                                                                                                                                                                                                                                                                                                                               |

There is no system parameter associated with the QUERY\_LOCK setting.

### **/RELATIVE**

Applies the multibuffer default to relative file operations.

### **/SEQUENTIAL (default)**

Applies the multibuffer default to sequential file operations. The **/SEQUENTIAL** qualifier overrides values applied using either the **/DISK**, the **/MAGNETIC TAPE**, or the **/UNIT RECORD** qualifier.

The **/SEQUENTIAL** qualifier is the default if you do not specify either the **/RELATIVE** or the **/INDEXED** qualifier.

**/SYSTEM**

Requires CMKRNL (change mode to kernel) privilege.

Applies specified defaults on a systemwide basis to all file operations.

Systemwide settings are implemented as system parameters, with the exception of **/QUERY\_LOCK**. For a systemwide setting to survive a system reboot, it must be written to the system parameter file by using **SYSGEN**.

**/UNIT\_RECORD**

Applies the multibuffer default to file operations on unit record devices. Values applied using the **/SEQUENTIAL** qualifier take precedence over values applied using the **/UNIT\_RECORD** qualifier.

## Examples

1. \$ SET RMS\_DEFAULT/BLOCK\_COUNT=24  
\$ SHOW RMS\_DEFAULT

|         | MULTI-<br>BLOCK<br>COUNT |  | MULTIBUFFER COUNTS |          |            |         |      |        | NETWORK<br>BLOCK<br>COUNT |   |
|---------|--------------------------|--|--------------------|----------|------------|---------|------|--------|---------------------------|---|
|         |                          |  | Indexed            | Relative | Sequential |         |      |        |                           |   |
|         |                          |  |                    |          | Disk       | Magtape | Unit | Record |                           |   |
| Process | 24                       |  | 0                  | 0        | 0          | 0       |      | 0      |                           | 0 |
| System  | 16                       |  | 0                  | 0        | 0          | 0       |      | 0      |                           | 8 |

|         | Prolog | Extend | Quantity | QUERY_LOCK |
|---------|--------|--------|----------|------------|
| Process | 0      |        | 0        | System     |
| System  | 0      |        | 0        | Enabled    |

|         | CONTENTION_POLICY |
|---------|-------------------|
| Process | System            |
| System  | Never             |

The **SET RMS\_DEFAULT** command in this example sets the multiblock count for disk file I/O at 24 for user programs that do not set the multiblock count explicitly. The command applies only to the current process.

2. \$ SET RMS\_DEFAULT/BUFFER\_COUNT=8/MAGTAPE  
\$ SHOW RMS\_DEFAULT

|         | MULTI-<br>BLOCK<br>COUNT |  | MULTIBUFFER COUNTS |          |            |         |      |        | NETWORK<br>BLOCK<br>COUNT |   |
|---------|--------------------------|--|--------------------|----------|------------|---------|------|--------|---------------------------|---|
|         |                          |  | Indexed            | Relative | Sequential |         |      |        |                           |   |
|         |                          |  |                    |          | Disk       | Magtape | Unit | Record |                           |   |
| Process | 0                        |  | 0                  | 0        | 0          | 8       |      | 0      |                           | 0 |
| System  | 16                       |  | 0                  | 0        | 0          | 0       |      | 0      |                           | 8 |

|         | Prolog | Extend | Quantity | QUERY_LOCK |
|---------|--------|--------|----------|------------|
| Process | 0      |        | 0        | System     |
| System  | 0      |        | 0        | Enabled    |

|         | CONTENTION_POLICY |
|---------|-------------------|
| Process | System            |
| System  | Never             |

The **SET RMS\_DEFAULT** command in this example defines the default multibuffer count for I/O magnetic tape operations at 8.

3. \$ SET RMS\_DEFAULT/BUFFER\_COUNT=7/NETWORK\_BLOCK\_COUNT=16/SYSTEM  
\$ SHOW RMS\_DEFAULT

|         | MULTI-<br>BLOCK<br>COUNT |  | MULTIBUFFER COUNTS |          |            |         |      |        |  | NETWORK<br>BLOCK<br>COUNT |
|---------|--------------------------|--|--------------------|----------|------------|---------|------|--------|--|---------------------------|
|         |                          |  | Indexed            | Relative | Sequential |         |      |        |  |                           |
|         |                          |  |                    |          | Disk       | Magtape | Unit | Record |  |                           |
| Process | 0                        |  | 0                  | 0        | 0          | 0       |      | 0      |  | 0                         |
| System  | 16                       |  | 0                  | 0        | 7          | 7       |      | 0      |  | 16                        |

|         | Prolog | Extend | Quantity | QUERY_LOCK |
|---------|--------|--------|----------|------------|
| Process | 0      |        | 0        | System     |
| System  | 0      |        | 0        | Enabled    |

|         | CONTENTION_POLICY |
|---------|-------------------|
| Process | System            |
| System  | Never             |

The **SET RMS\_DEFAULT** command in this example defines the systemwide default multibuffer count at 7 for all sequential file operations on disk, magnetic tape, and unit record devices. The command also sets the network block count at 16.

4. \$ SET RMS\_DEFAULT/EXTEND=50/INDEXED/BUFFER\_COUNT=5  
\$ SHOW RMS\_DEFAULT

|         | MULTI-<br>BLOCK<br>COUNT |  | MULTIBUFFER COUNTS |          |            |         |      |        |  | NETWORK<br>BLOCK<br>COUNT |
|---------|--------------------------|--|--------------------|----------|------------|---------|------|--------|--|---------------------------|
|         |                          |  | Indexed            | Relative | Sequential |         |      |        |  |                           |
|         |                          |  |                    |          | Disk       | Magtape | Unit | Record |  |                           |
| Process | 0                        |  | 5                  | 0        | 0          | 0       |      | 0      |  | 0                         |
| System  | 16                       |  | 0                  | 0        | 0          | 0       |      | 0      |  | 8                         |

|         | Prolog | Extend | Quantity | QUERY_LOCK |
|---------|--------|--------|----------|------------|
| Process | 0      |        | 50       | System     |
| System  | 0      |        | 0        | Enabled    |

|         | CONTENTION_POLICY |
|---------|-------------------|
| Process | System            |
| System  | Never             |

The **SET RMS\_DEFAULT** command in this example sets the default multibuffer count for I/O operations on indexed files at 5. It also defines the default extend quantity for sequential I/O operations at 50 blocks. These defaults apply only to disk operations for user programs that do not set the multiblock count explicitly. These defaults are limited to the current process.

5. \$ SET RMS\_DEFAULT/QUERY\_LOCK=DISABLE  
\$ SHOW RMS\_DEFAULT

|         | MULTI-<br>BLOCK<br>COUNT |  | MULTIBUFFER COUNTS |          |            |         |      |        |  | NETWORK<br>BLOCK<br>COUNT |
|---------|--------------------------|--|--------------------|----------|------------|---------|------|--------|--|---------------------------|
|         |                          |  | Indexed            | Relative | Sequential |         |      |        |  |                           |
|         |                          |  |                    |          | Disk       | Magtape | Unit | Record |  |                           |
| Process | 0                        |  | 0                  | 0        | 0          | 0       |      | 0      |  | 0                         |
| System  | 16                       |  | 0                  | 0        | 0          | 0       |      | 0      |  | 8                         |

|         | Prolog | Extend | Quantity | QUERY_LOCK |
|---------|--------|--------|----------|------------|
| Process | 0      |        | 0        | Disabled   |
| System  | 0      |        | 0        | Enabled    |

|         | CONTENTION_POLICY |
|---------|-------------------|
| Process | System            |

System            Never

The **SET RMS\_DEFAULT** command in this example requests that query locking be disabled for the duration of any file opens done by images within this process for any read (\$GET or \$FIND) record operations that have both RAB\$V\_NLK (no lock) and RAB\$V\_RRL (read-regardless) set in the RAB\$L\_ROP field of the RAB (Record Access Block).

## SET ROOT

SET ROOT — Defines the POSIX root for the system.

### Format

**SET ROOT** *device-name:directory-spec*

### Parameter

*device-name:directory-spec*

Defines the root pathname.

### Description

In POSIX pathname processing mode, RMS and the C Run-Time Library treat the leading slash (/) of a pathname as referring to the defined root. By default, the root is SYS\$SYSDEVICE:[PSX\$ROOT]. The root definition does not persist across a reboot. The **SET ROOT** command requires SYSNAM privilege and has the following qualifier:

### Qualifier

**/LOG** (default)

**/NOLOG**

Controls whether the **SET ROOT** command displays a success indication after the root definition is set.

### Example

```
$ SHOW ROOT
DISK$ALPHASYS:[000000]
$ SET ROOT DISK$ALPHASYS:[PSX$ROOT]
%SET-I_SXROOSET, system POSIX root set to DISK$ALPHASYS:[PSX$ROOT]
$ SHOW ROOT
DISK$ALPHASYS:[PSX$ROOT]
$
```

The **SHOW ROOT** command in this example displays the current root path. The **SET ROOT** command changes these defaults, and the next **SHOW ROOT** command displays the new default root.

## SET SECURITY

SET SECURITY — Modifies the security profile of an object.

## Format

**SET SECURITY** *object-name*

## Parameter

*object-name*

Specifies the name of an object, such as a file or device, whose security profile is to be modified. An object is identified by an object name and a class name. The default class name is FILE.

An object name of the FILE class (explicitly or implicitly specified) can include an asterisk (\*) or a percent sign (%) wildcard character, but wildcard characters are not allowed in any class other than FILE. **SET SECURITY** does not operate on remote files and devices, alias directory entries, or directory names in UIC format (for example, [14,5]).

## Description

The **SET SECURITY** command modifies the security profile of an object. Such a profile contains the following elements:

- An access control list editor (ACL editor).
- A protection code, which defines access to objects based on the categories of system, owner, group, and world.
- An owner. The system uses the owner element to interpret the protection code.

There are three different ways to use the command:

- You can provide new values explicitly with the qualifiers **/ACL**, **/PROTECTION**, and **/OWNER**. (For extensive ACL work, use **/EDIT** to invoke the ACL editor.)
- You can copy from another object's profile with the **/LIKE** qualifier.
- If the object is of the FILE class, you can reset its profile to the default setting with the **/DEFAULT** qualifier.

To modify a security profile, you need control access to the object. An ACL grants control access explicitly whereas a protection code grants it implicitly to anyone belonging to the owner or system categories. If an object profile is modified while the object is being accessed, the existing access is unaffected.

The following table identifies object classes and the access types they support:

| Object Class                    | Access Types                   |
|---------------------------------|--------------------------------|
| COMMON_EVENT_FLAG_CLUSTER       | Associate, Delete              |
| DEVICE                          | Read, Write, Physical, Logical |
| FILE (including directory file) | Read, Write, Execute, Delete   |
| GROUP_GLOBAL_SECTION            | Read, Write, Execute           |
| ICC_ASSOCIATION <sup>1</sup>    | Open, Access                   |

| Object Class          | Access Types                           |
|-----------------------|----------------------------------------|
| LOGICAL_NAME_TABLE    | Read, Write, Create, Delete            |
| QUEUE                 | Read, Submit, Manage, Delete           |
| RESOURCE_DOMAIN       | Read, Write, Lock                      |
| SECURITY_CLASS        | Read, Write, Logical I/O, Physical I/O |
| SYSTEM_GLOBAL_SECTION | Read, Write, Execute                   |
| VOLUME                | Read, Write, Create, Delete            |

<sup>1</sup>The class ICC\_ASSOCIATION has special semantics: there are both permanent and temporary objects for this class. Permanent objects are created using the command procedure SYSSMANAGER:ICC\$CREATE\_SECURITY\_OBJECT.COM. The **SET SECURITY** command applies to both permanent and temporary ICC\_ASSOCIATION security objects.

The *VSI OpenVMS Guide to System Security* [<https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/>] provides a full explanation of protected objects and how to modify them.

Table 7, "*SET SECURITY Qualifier Categories*" shows the qualifier categories for the **SET SECURITY** command. The explanations for the qualifiers following Table 7, "*SET SECURITY Qualifier Categories*" occur in alphabetical order.

**Table 7. SET SECURITY Qualifier Categories**

| General Qualifiers | ACL-Modifying Qualifiers | Security Class Qualifier | File-Specific Qualifiers | Transfer Qualifiers |
|--------------------|--------------------------|--------------------------|--------------------------|---------------------|
| /ACL               | /AFTER                   | /PROFILE                 | /BACKUP                  | /COPY_ATTRIBUTE     |
| /CLASS             | /DELETE                  |                          | /BEFORE                  | /LIKE               |
| /LOG               | /EDIT                    |                          | /BY_OWNER                |                     |
| /OWNER             | /REPLACE                 |                          | /CONFIRM                 |                     |
| /PROTECTION        |                          |                          | /CREATED                 |                     |
|                    |                          |                          | /DEFAULT                 |                     |
|                    |                          |                          | /EXCLUDE                 |                     |
|                    |                          |                          | /EXPIRED                 |                     |
|                    |                          |                          | /MODIFIED                |                     |
|                    |                          |                          | /SINCE                   |                     |
|                    |                          |                          | /STYLE                   |                     |

## Qualifiers

**/ACL[=(ace[,...])]**

Identifies one or more access control list entries (ACEs) to add, replace, or delete. Enclose each ACE in parentheses and separate multiple ACEs by commas (.). The most common type of entry, the Identifier ACE, has the format (IDENTIFIER=identifier, ACCESS=access-type(+...)). By default, **SET SECURITY** adds an ACE to the top of the ACL. This behavior changes when you include one of the positional qualifiers: **/AFTER**, **/DELETE**, or **/REPLACE**. See the discussion of ACL

ordering in the *VSI OpenVMS Guide to System Security* [[https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#ACL\\_DETAILS](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#ACL_DETAILS)].

**/AFTER=*ace***

Positions all ACEs specified with the **/ACL** qualifier after the ACE named with the **/AFTER** qualifier.

**/BACKUP**

Modifies the time value provided with the **/BEFORE** or the **/SINCE** qualifier. The **/BACKUP** qualifier selects files according to the date of their most recent backup (rather than by the creation, expiration, or modification date). By default, **SET SECURITY** selects files according to their creation date.

**/BEFORE[=*time*]**

Selects only those files dated prior to the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: BOOT, LOGIN, TODAY (default), TOMORROW, or YESTERDAY. Specify the **/CREATED** or the **/MODIFIED** qualifier to indicate the time attribute to be used as the basis for selection. The **/CREATED** qualifier is the default.

For complete information on specifying time values, see the relevant section in the *VSI OpenVMS User's Manual* [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\\_AND\\_TIME\\_SECT](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT)] or the online help topic Date.

**/BY\_OWNER[=*uic*]**

Selects files whose owner's UIC matches the UIC specified. The default UIC is that of the current process.

**/CLASS=*class-name***

Specifies the class of the object whose profile is to be modified. By default, the command assumes the object class is FILE.

**/CONFIRM**

Controls whether **SET SECURITY** prompts for verification before performing the operation. Valid responses are YES, NO, TRUE, and FALSE. Answers are not case sensitive and can be abbreviated to one letter. To stop processing the command at any point, type QUIT or press **Ctrl/Z**. To cancel the verification procedure but to proceed with the command, type ALL.

**/COPY\_ATTRIBUTE=(*keyword*[,...])**

Specifies a subset of security elements to transfer from a source object to a target object. Valid keywords include the following:

| Keyword       | Description                  |
|---------------|------------------------------|
| ALL (default) | Copy all security elements   |
| ACL           | Copy the access control list |
| OWNER         | Copy the owner               |
| PROTECTION    | Copy the protection code     |

Use the **/COPY\_ATTRIBUTE** qualifier with the **/LIKE** qualifier. For example, you can create an ACL for an object and then copy its ACL to new objects.

### **/CREATED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/CREATED** qualifier selects files according to the date they were created (rather than by the backup, expiration, or modification date). By default, **SET SECURITY** selects files according to their creation date.

### **/DELETE[=ALL]**

Deletes ACEs according to the following rules:

- The expression **/ACL=aces/DELETE** deletes the named ACEs.
- The expression **/ACL/DELETE** deletes all unprotected ACEs.
- The expression **/ACL/DELETE=ALL** deletes all ACEs including protected ACEs.
- The expression **/ACL=aces/DELETE=ALL** deletes the existing ACL (if any) and create a new ACL with the ACEs specifies on the **/ACL** qualifier.

### **/DEFAULT**

Regenerates the security profile of a file. The default qualifier changes the protection code, the ACL, and the owner elements of a file to what it would be if the file had just been created. The profile is recreated according to the following rules:

- The protection code is propagated from the default protection ACE on the directory (if one exists), or else it is propagated from the process default.
- The ACL is propagated from the parent directory for those ACEs that have the default option.
- The owner is set to the owner of the parent directory.

With subdirectory files, **SET SECURITY** assigns the owner, protection, and ACL elements of the parent directory.

**SET SECURITY** does not copy any ACE on the source object if the ACE holds the nopropagate attribute nor does it change any ACE on the target object if the ACE holds the protected attribute. To apply new elements to all versions of the file, specify **;** in the object name. See the relevant section in the *VSI OpenVMS Guide to System Security* [[https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#ADJUST\\_DEFAULTS](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#ADJUST_DEFAULTS)] for more information on propagation rules.

### **/EDIT**

Invokes the access control list editor (ACL editor) and allows you to modify an ACL interactively. The ACL editor does not allow the asterisk (\*) and the percent sign (%) wildcard characters in an object name. You must specify the object whose ACL you are editing.

The **/EDIT** qualifier must be the first qualifier on the command line; other qualifiers can include **/CLASS** and, if the class is SECURITY\_CLASS, you can include the **/PROFILE** qualifier. Whenever an object does not belong to the FILE class, you also need to specify **/CLASS**.

See the section on the ACL editor in the *VSI OpenVMS System Management Utilities Reference Manual* [[https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-i-a-l/#ACL\\_PART](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-i-a-l/#ACL_PART)] for more information.

**/EXCLUDE=(*filespec*[,...])**

Excludes the specified files from the **SET SECURITY** operation. You can include a directory, but not a device, in the file specification. You cannot use relative version numbers to exclude a specific version.

**/EXPIRED**

Modifies the time specified with the **/BEFORE** or the **/SINCE** qualifier. The **/EXPIRED** qualifier selects files according to their expiration dates rather than by the backup, creation, or modification date. (The expiration date is set with the **SET FILE/EXPIRATION\_DATE** command.) By default, files are selected according to their creation date.

**/LIKE=(NAME=*source-object-name* [,CLASS=*source-object-class*]  
[,PROFILE=TEMPLATE=*template-name*])**

Identifies the object from which **SET SECURITY** should copy security elements. The **/LIKE** qualifier replaces an object's existing elements with those of the source object. Nopropagate ACEs are not transferred and protected ACEs on the target object are not deleted. Use the **/COPY\_ATTRIBUTE** qualifier with the **/LIKE** qualifier to copy an object's elements. See the [VSI OpenVMS Guide to System Security \[https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/\]](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/) for information about the special handling of protected and nopropagate ACEs.

The object class of the source object defaults to the class of the target object. When the **/CLASS** qualifier is omitted, the CLASS keyword defaults to FILE.

The PROFILE keyword applies to security class objects. It identifies which template of the security class you want to copy and modify. See the [/PROFILE](#) qualifier for more information.

**/LOG**

Controls whether the **SET SECURITY** command displays the name of the object that has been modified by the command. The qualifier is invalid with the **/EDIT** qualifier.

**/MODIFIED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/MODIFIED** qualifier selects files according to the dates on which they were last modified, rather than by the backup, creation, or expiration date. By default, files are selected according to their creation date.

**/OWNER=*identifier***

Requires GRPPRV (group privilege) to set the owner to another member of the same group. Requires SYSPRV (system privilege) to set the owner to any user identification code (UIC) outside your group.

Modifies the owner element of an object. Specify the user identification code (UIC) or general identifier in the standard format. Modifying the owner element of a file usually requires privileges. See the relevant section in the [VSI OpenVMS Guide to System Security \[https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC\\_SECTION\]](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC_SECTION) for more information.

**/PROFILE=TEMPLATE[=*template-name*]**

Identifies which template profile of a security class object you want to modify. All object classes except FILE have at least one template profile. These template profiles define the basis of the profile

of new objects. Use the DCL command **SHOW SECURITY/CLASS=SECURITY\_CLASS** to display template names. When no value is given for *template-name*, **SET SECURITY** uses the template named DEFAULT.

Include the **/CLASS=SECURITY\_CLASS** qualifier to identify which profile you want to modify.

**/PROTECTION=(ownership[:access][,...])**

Cannot be used to change the protection on a file by using DECnet software.

Modifies the protection code of an object. The protection code defines the type of access allowed to users, based on their relationship to the object's owner.

Specify the *ownership* parameter as system (S), owner (O), group (G), or world (W).

Access types are class specific and are shown in the Description section. For *access*, use the first letter of the access name. The Examples section provides you with models of protection codes.

**/REPLACE=(ace[,...])**

Eliminates entries listed with the **/ACL** qualifier and adds entries listed with the **/REPLACE** qualifier. **SET SECURITY** inserts the entries listed with **/REPLACE** in the position of the last deleted ACE.

**/SECRECY**

Reserved for use by VSI.

**/SINCE[=*time*]**

Selects only those files dated on or after the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: BOOT, JOB\_LOGIN, LOGIN, TODAY (default), TOMORROW, or YESTERDAY. Specify the **/CREATED** or the **/MODIFIED** qualifier to indicate the time attribute to be used as the basis for selection. The **/CREATED** qualifier is the default.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic Date.

**/STYLE=*keyword***

Specifies the file name format for display purposes.

The valid keywords for this qualifier are CONDENSED and EXPANDED. Descriptions are as follows:

| Keyword             | Description                                                                                                                                                                           |
|---------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CONDENSED (default) | Displays the file name representation of what is generated to fit into a 255-length character string. This file name may contain a DID or FID abbreviation in the file specification. |
| EXPANDED            | Displays the file name representation of what is stored on disk. This file name does not contain any DID or FID abbreviations.                                                        |

The keywords **CONDENSED** and **EXPANDED** are mutually exclusive. This qualifier specifies which file name format is displayed in the output message, along with the confirmation if requested.

File errors are displayed with the **CONDENSED** file specification unless the **EXPANDED** keyword is specified.

See the relevant section in the *VSI OpenVMS User's Manual* [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE\\_ACCESS](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE_ACCESS)] for more information.

### **/SYMLINK=keyword**

The valid keywords for this qualifier are **[NO]WILDCARD** and **[NO]ELLIPSIS**. Descriptions are as follows:

| Keyword           | Description                                                                      |
|-------------------|----------------------------------------------------------------------------------|
| <b>WILDCARD</b>   | Indicates that symlinks are enabled during wildcard searches.                    |
| <b>NOWILDCARD</b> | Indicates that symlinks are disabled during directory wildcard searches.         |
| <b>ELLIPSIS</b>   | Equivalent to <b>WILDCARD</b> (included for command symmetry).                   |
| <b>NOELLIPSIS</b> | Indicates that symlinks are matched for all wildcard fields except for ellipsis. |

If the file named in the **SET SECURITY** command is a symlink, the command operates on the symlink itself.

## Examples

1. (WIDE)\$ SHOW SECURITY LNM\$GROUP /CLASS=LOGICAL\_NAME\_TABLE

```
LNMSGROUP object of class LOGICAL_NAME_TABLE
```

```
Owner: [SYSTEM]
Protection: (System: RWCD, Owner: R, Group: R, World: R)
Access Control List:
    (IDENTIFIER=[USER,VARANESE],ACCESS=CONTROL)
```

```
$ SET SECURITY LNM$GROUP /CLASS=LOGICAL_NAME_TABLE -
_$      /ACL=( (IDENTIFIER=CHEKOV,ACCESS=CONTROL), -
_$              (IDENTIFIER=WU,ACCESS=READ+WRITE)) -
_$      /DELETE=ALL -
_$      /PROTECTION=(S:RWCD, O:RWCD, G:R, W:R)
```

```
$ SHOW SECURITY LNM$GROUP /CLASS=LOGICAL_NAME_TABLE
```

```
LNMSGROUP object of class LOGICAL_NAME_TABLE
```

```
Owner: [SYSTEM]
Protection: (System: RWCD, Owner: RWCD, Group: R, World: R)
Access Control List:
    (IDENTIFIER=[USER,CHEKOV],ACCESS=CONTROL)
    (IDENTIFIER=[USER,WU],ACCESS=READ+WRITE)
```

This example shows how to make a straightforward change to the security elements of an object. The first **SHOW SECURITY** command displays the current settings of the LNM\$GROUP logical name

table. The **SET SECURITY** command resets the ACL to allow control access for user Chekov, and to allow read and write access for user Wu. Note that without the **/DELETE=ALL** qualifier, these ACEs would have been added to the existing ACL rather than superseding it. The protection is also changed to allow read, write, create, and delete access for the owner. The last command displays the results of the changes.

2. \$ SHOW SECURITY LNM\$GROUP /CLASS=LOGICAL\_NAME\_TABLE

LNМ\$GROUP object of class LOGICAL\_NAME\_TABLE

```
Owner: [SYSTEM]
Protection: (System: RWCD, Owner: R, Group: R, World: R)
Access Control List:
    (IDENTIFIER=[USER,FERNANDEZ],ACCESS=CONTROL)
```

\$ SHOW SECURITY LNM\$JOB /CLASS=LOGICAL\_NAME\_TABLE

LNМ\$JOB object of class LOGICAL\_NAME\_TABLE

```
Owner: [USER,WEISS]
Protection: (System: RWCD, Owner: RWCD, Group, World)
Access Control List: <empty>
```

```
$ SET SECURITY LNM$JOB /CLASS=LOGICAL_NAME_TABLE -
_$      /LIKE=(NAME=LNМ$GROUP, CLASS=LOGICAL_NAME_TABLE) -
_$      /COPY_ATTRIBUTES=PROTECTION
$ SET SECURITY LNM$JOB /CLASS=LOGICAL_NAME_TABLE -
_$      /ACL=(IDENTIFIER=FERNANDEZ, ACCESS=READ)
```

\$ SHOW SECURITY LNM\$JOB /CLASS=LOGICAL\_NAME\_TABLE

LNМ\$JOB object of class LOGICAL\_NAME\_TABLE

```
Owner: [USER,WEISS]
Protection: (System: RWCD, Owner: R, Group: R, World: R)
Access Control List:
    (IDENTIFIER=[USER,FERNANDEZ],ACCESS=READ)
```

This example shows how to copy security access information from one object to another and, at the same time, set some elements explicitly. The first **SHOW SECURITY** commands display the current settings for the LNM\$GROUP and LNM\$JOB logical name tables. The **SET SECURITY** command copies the protection code from the LNM\$GROUP logical name table to the LNM\$JOB logical name table and adds an ACE to allow read access to another user. The final **SHOW SECURITY** command shows the effect of the changes.

3. \$ SHOW SECURITY SECURITY\_CLASS /CLASS=SECURITY\_CLASS

SECURITY\_CLASS object of class SECURITY\_CLASS

```
Owner: [SYSTEM]
Protection: (System: RWED, Owner: RWED, Group: R, World: R)
Access Control List: <empty>
```

Template: DEFAULT

```
Owner: [SYSTEM]
```

```
Protection: (System: RWED, Owner: RWED, Group, World: RE)
Access Control List: <empty>

$ SET SECURITY SECURITY_CLASS /CLASS=SECURITY_CLASS -
_$      /PROFILE=TEMPLATE=DEFAULT -
_$      /PROTECTION=(S:RWE, O:RWE, G:RE)

$ SHOW SECURITY SECURITY_CLASS /CLASS=SECURITY_CLASS

SECURITY_CLASS object of class SECURITY_CLASS
  Owner: [SYSTEM]
  Protection: (System: RWED, Owner: RWED, Group: R, World: R)
  Access Control List: <empty>

Template: DEFAULT

  Owner: [SYSTEM]
  Protection: (System: RWE, Owner: RWE, Group: RE, World: RE)
  Access Control List: <empty>
```

This example demonstrates how to change the security elements for the template of a security class object. The first command shows the current settings for the SECURITY\_CLASS object. The second command changes the DEFAULT template of the SECURITY\_CLASS object such that the protection is (S:RWE, O:RWE, G:RE). The change is shown in the display of the last command. The world protection of RE remains unchanged.

#### 4. \$ DIRECTORY/SECURITY

```
Directory DKA200:[DATA]

FILE001.DAT;1          [SYSTEM]          (RWED,RWED,RE, )

Total of 1 file.

$ SET SECURITY/CLASS=FILE/PROTECTION=(WORLD:RE)/LOG FILE001.DAT
%SET-I-MODIFIED, DKA200:[DATA]FILE001.DAT;1 modified

$ DIRECTORY/SECURITY

Directory DKA200:[DATA]

FILE001.DAT;1          [SYSTEM]          (RWED,RWED,RE,RE)

Total of 1 file.
$
```

This example shows how to set UIC-based protection codes on an object. The first **DIRECTORY** command displays the current security settings on the file FILE001.DAT. The **SET SECURITY** command changes the protection codes on the file to allow read and execute access for all users. The last command displays the results of the change.

## SET SERVER ACME\_SERVER (Alpha/Integrity servers Only)

SET SERVER ACME\_SERVER — Controls the ACME server. **Requires SYSPRV privilege.**

## Format

**SET SERVER ACME\_SERVER**

## Description

The **SET SERVER ACME\_SERVER** command provides a system manager with the ability to manage the Authentication and Credential Management Extension (ACME) server process, ACME\_SERVER. Specifying this command allows you to start, stop, and restart the ACME server.

The ACME\_SERVER process is a detached, kernel-threaded server process that services user authentication requests. These requests are received from client processes that use the SYS\$ACM system service. One or more ACME agents assist in processing these requests. An ACME agent is a shareable image that is dynamically activated within the ACME\_SERVER process.

The ACME\_SERVER process is created automatically at system startup with the VMS ACME agent configured and enabled.

By default, the ACME\_SERVER process runs under the SYSTEM account profile ([1,4]) with the following privileges: IMPERSONATE, SYSNAM, PSWAPM, SHARE, TMPMBX, EXQUOTA, AUDIT, CMKRNL, WORLD, and SETPRV.

The ACME\_SERVER process is created with the following quotas:

```
ASTLM      = 200
BIOLM      = 200
BYTLM      = 100000
DIOLM      = 200
ENQLM      = 1000
FILLM      = 64
JTQUOTA    = 4096
```

```
PGFLQUOTA = 200000 (Alpha)
PGFLQUOTA = 300000 (Integrity servers)
```

```
PRCLM      = 4
TQELM      = 64
WSQUOTA    = 2048
WSDEFAULT  = 1024
WSEXTENT   = 4096
```

Default UIC, privileges, and quotas can be overridden when the server is started.

In the event of an abnormal process termination, the server will automatically restart and run the SYS\$MANAGER:ACME\$START.COM command procedure. The executive-mode logical name ACME\$START is used to locate this file.

SYS\$MANAGER:ACME\$START.COM is also run as a result of one of the following commands:

- **SET SERVER ACME/START=AUTO** command is issued.
- **SET SERVER ACME/RESTART** command is issued.

The SYS\$MANAGER:ACME\$START.LOG file contains any information produced during restart in the event of problems.

SY\$MANAGER:ACME\$START.COM file can be modified by the user to define which agents are configured during a restart as well as any other server configuration options. It is not replaced during system upgrades. The SY\$MANAGER:ACME\$START.TEMPLATE file contains the VSI-supplied version of the file.

The ACME\_SERVER process directs SYS\$ERROR output to the SY\$MANAGER:ACME\_SERVER\_ERROR.LOG file. This file exists only if unexpected errors are encountered during operation.

Log file entries generated by the server and ACME agents are written by default to the SY\$MANAGER:ACME\$SERVER.LOG file.

The **SET SERVER ACME** commands are used to perform these operations:

- Start and stop the ACME\_SERVER process.
- Configure (dynamically load) ACME agents.
- Enable and disable ACME agents (after they are configured).
- Suspend and resume requests processing. (ACME agents reenter "initial" state for system management reasons, for example, system backup operations.)
- Control logging and tracing.

The **SHOW SERVER ACME** commands are used to display server and agent information.

The following sequence of commands is used to create the server and enable request processing:

1. **SET SERVER ACME/START**

This command creates the server process.

2. **SET SERVER ACME/CONFIGURE**

This command configures one or more ACME agents.

3. **SET SERVER ACME/ENABLE**

This command enables ACME agent request processing.

For additional information, see the [SHOW SERVER ACME SERVER](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#CONFIGURE_ACME_SERVER_AND_AGENTS) command and see the relevant section in the *VSI OpenVMS Guide to System Security* [[https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#CONFIGURE\\_ACME\\_SERVER\\_AND\\_AGENTS](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#CONFIGURE_ACME_SERVER_AND_AGENTS)].

For information about the SY\$ACM system service, see the relevant section in the *VSI OpenVMS System Services Reference Manual: A-GETUAI* [[https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-a-getuai/#\\_4527acm](https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-a-getuai/#_4527acm)].

## Qualifiers

### **/ABORT**

Forces the ACME\_SERVER process to terminate without graceful shutdown of ACME agents. Pending requests are cancelled.

This command can be used if a malfunctioning ACME agent prevents a graceful shutdown.

### **/CANCEL**

Cancels pending dialogue requests. Pending dialogue requests are outstanding requests to SYS\$ACM callers to supply dialogue response data. Active requests being serviced by the ACME\_SERVER process are allowed to complete normally.

Can be used only if the **/EXIT** or **/DISABLE** qualifier is also specified.

### **/CLUSTER**

Issues the **SET** command to each ACME server in the cluster.

**/CONFIGURE=(NAME=*name*[,CREDENTIALS=*credentials*][,FACILITY=*facility*][,FILE=*file*][,THREAD\_MAX=*n*][,...])**

Dynamically loads an ACME agent. An ACME agent is a shareable image that conforms to the ACME agent plug-in interface specification.

By default, the ACME server looks for an ACME agent file named *prefix\$name\_ACMESHR.EXE*, where the *prefix* is VMS by default and *name* is the case-insensitive string specified by the NAME keyword. The prefix can be overridden by the FACILITY keyword. Otherwise, a complete file specification can be specified with the FILE keyword.

You must specify the CREDENTIALS keyword if the ACME agent is a domain of interpretation (DOI) agent capable of authenticating users and issuing credentials. The CREDENTIALS keyword specifies the name of the persona extension associated with the ACME agent (see the \$PERSONA\_EXTENSION\_LOOKUP system service in the [VSI OpenVMS System Services Reference Manual: GETUTC-Z](https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-getutc-z/#_4527pers_ext_lookup) [[https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-getutc-z/#\\_4527pers\\_ext\\_lookup](https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-getutc-z/#_4527pers_ext_lookup)]). The credentials name must match the name registered by the executive loadable image that implements the persona extension. For credentials other than "VMS", see the documentation provided for the ACME agent and the specific persona extension.

A maximum of eight ACME agents can be configured.

## **THREAD\_MAX Keyword: Usage Considerations**

An ACME server worker thread is the authentication request processing thread of execution. The number of worker threads determines the number of authentication requests the ACME server can process simultaneously.

The ACME server assigns a request slot to each in-progress authentication request. The total number of request slots sets a limit on the maximum number of requests the ACME server can have outstanding.

The ACME server limits the number of unprivileged authentication requests it can accept for processing to half the total number of request slots.

If a process makes a call to \$ACM and no request slots are available, the process remains in resource wait state until a request slot becomes free.

The number of ACME server worker threads can range from 1 to 32. The default of 4 satisfies most operating environments in which authentication processing time is largely spent waiting for I/O. You

may, however, be able to improve throughput by increasing the number of worker threads if, for example, you have a user-written ACME agent that requires more CPU time than most.

You can set the maximum number of ACME server worker threads before you start or restart the server by defining the inner-mode logical name `ACME$THREAD_MAXIMUM` in the systemwide logical name table. For example:

```
$ DEFINE /SYSTEM /EXECUTIVE_MODE ACME$THREAD_MAXIMUM 8
```

You can also use the **/CONFIGURE** qualifier to set the maximum number of server worker threads before you enable the ACME server. For example:

```
$ SET SERVER ACME /CONFIGURE=THREAD_MAX=6
```

The **/CONFIGURE** qualifier overrides the value of the `ACME$THREAD_MAXIMUM` logical, if it is defined.

Because most authentication processing is I/O bound, defining more threads than about one quarter the number of request slots does not gain more throughput.

The ACME server calculates a default number of request slots from the value of `MAXPROCESSCNT` and the number of available CPUs. You can override the calculated value by defining the inner-mode logical name `ACME$REQUEST_MAXIMUM` in the systemwide name table before you start or restart the ACME server. For example:

```
$ DEFINE /SYSTEM /EXECUTIVE_MODE ACME$REQUEST_MAXIMUM 64 $ SET SERVER  
ACME /RESTART
```

## **/DISABLE**

Disables (shuts down) all ACME agents. Additional ACME agents can be configured.

## **/ENABLE[=NAME=(*name*[,...])]**

Enables one or more ACME agents in the specified order. Ordering of ACME agents is significant, as the `ACME_SERVER` processes user authentication requests in the order specified. The *name* variable is a case-insensitive string argument.

If you do not specify the **NAME** keyword, the same list of ACME agents will be enabled that were enabled by a previous **/ENABLE** command. If no previous **/ENABLE** command was issued, all configured ACME agents are enabled.

## **/EXIT**

Requests a graceful shutdown of the ACME agents. The `ACME_SERVER` process will be shut down after pending requests are completed.

## **/LOG**

### **/NOLOG (default)**

Creates and opens a new log file. The log file is named `SY$MANAGER:ACME$SERVER.LOG`. It may be redirected by defining the system logical name `ACME$SERVER`.

## **/NODE=(*node-name*[,...])**

Issues the **SET** command to the ACME server on the specified nodes in the order they are entered. The node names must be located within the current cluster.

**/RESTART**

Requests a graceful shutdown of the ACME agents. The ACME\_SERVER process will be shut down after pending requests are completed.

The ACME\_SERVER is restarted and the SYS\$MANAGER:ACME\$START.COM startup procedure runs.

**/RESUME**

Resumes normal operation following use of the **/SUSPEND** qualifier.

**/START[=AUTO]**

**/START** cannot be used with the **/ABORT**, **/EXIT**, or **/RESTART** qualifiers.

Starts the server process.

The optional keyword, **AUTO**, causes the server to startup and configure itself using the SYS\$MANAGER:ACME\$START.COM procedure. By default, the server starts with only the OpenVMS ACME agent configured. The following options are available:

To change the default privileges:

```
/PRIVILEGES=(privilege[,...])
```

To change the default UIC:

```
/UIC=uic
```

To change the default quotas:

```
/AST_LIMIT=n  
/BUFFER_LIMIT=n  
/ENQUEUE_LIMIT=  
n/EXTENT=n  
/FILE_LIMIT=  
n/IO_BUFFERED=n  
/IO_DIRECT=n  
/JOB_TABLE_QUOTA=n  
/MAXIMUM_WORKING_SET=n  
/PAGE_FILE=n  
/QUEUE_LIMIT=n  
/SUBPROCESS_LIMIT=n  
/WORKING_SET=n
```

You can use the following alternate syntax to specify a list of quotas and their values:

```
/QUOTAS=(quota=n[,...])
```

*quota* is a PQL-style quota name (for example: ASTLM, BIOLM).

See the \$CREPRC system service in the [VSI OpenVMS System Services Reference Manual: A–GETUAI](https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-a-getuai/#JUN_147) [https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-a-getuai/#JUN\_147] for a list of PQL-style quota names and descriptions.

To change the image dump setting:

/DUMP (default)  
/NODUMP

Forces a process dump in the event of an abnormal process termination. The dump is written to SYS\$MANAGER: using the image file name and .DMP extension.

### **/SUSPEND**

Suspends operation after all pending requests are completed.

ACME agents are returned to their initial state (open files are closed, for example). This permits system management functions, such as system backups, to be performed without file-open conflicts.

See also the [/RESUME](#) qualifier.

### **/TRACE= *n*** **/NOTRACE**

Enables trace mode in the ACME\$SERVER log file. Opens the log file if not already opened.

*n* is a bit-mask with the following assigned bits:

|    |                |                                    |
|----|----------------|------------------------------------|
| 0  | agent          | Enable agent tracing               |
| 1  | general        | General (non-specific) tracing     |
| 2  | vm             | VM operations                      |
| 3  | ast            | AST processing                     |
| 4  | wqe            | WQE parameter values               |
| 5  | report         | Agent status/attributes operations |
| 6  | message        | Messaging operations               |
| 7  | dialogue       | Dialogue operations                |
| 8  | resource       | Agent resource operations          |
| 9  | callout        | Agent callout routine              |
| 10 | callout_status | Agent callout return status        |

If you specify **/NOTRACE**, trace mode is disabled and the log file remains open.

### **/WAIT** **/NOWAIT (default)**

Returns to caller once the server returns a status other than ACME\$\_BUSY.

Can only be used with **/EXIT**, **/DISABLE**, and **/SUSPEND** qualifiers.

## **Examples**

1. \$ SET SERVER ACME\_SERVER/START/LOG

This command starts the ACME server and creates and opens a new log file.

2. \$ SET SERVER ACME\_SERVER/DISABLE/WAIT/CANCEL

This command disables all configured ACME agents, cancelling all requests in progress. Control does not return to the DCL command prompt until the ACME server has completed the cancellations.

3. \$ SET SERVER ACME\_SERVER/CONFIGURE=(NAME=VMS,CREDENTIALS=VMS)

This command loads the VMS ACME agent and identifies its credentials as VMS.

## SET SERVER REGISTRY\_SERVER (Alpha/Integrity servers Only)

SET SERVER REGISTRY\_SERVER — Controls the Registry server. **Requires SYSPRV privilege.**

### Format

**SET SERVER REGISTRY\_SERVER**

### Description

The **SET SERVER REGISTRY\_SERVER** command provides a system manager with the ability to start, stop, and restart the Registry server. The Registry server maintains information stored in the Registry database.

The Registry database is used by COM, Advanced Server for OpenVMS, and other applications.

For more information about the Registry database and the \$REGISTRY system service, see the relevant section in the *VSI OpenVMS System Services Reference Manual* [[https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-getutc-z/#\\_4527REGISTRY](https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-getutc-z/#_4527REGISTRY)]. See also the **SHOW SERVER REGISTRY\_SERVER** command.

### Qualifiers

#### /ABORT

Aborts the Registry server on the specified node or nodes in the cluster.

Cannot be used with the **/EXIT**, **/RESTART**, or **/START** qualifiers.

#### /CLUSTER

Issues the **SET** command to each Registry server in the cluster, setting the Registry master server last.

Cannot be used with the **/MASTER** or **/NODE** qualifiers.

#### /EXIT

Stops the Registry server on the specified node or nodes in the cluster.

Cannot be used with the **/ABORT**, **/RESTART**, or **/START** qualifiers.

#### /LOG

#### /NOLOG (default)

Closes the current Registry server log file and creates a new file.

**/MASTER**

Requires SYSLOCK privilege.

Issues the command to the Registry master server only.

Cannot be used with the **/CLUSTER**, **/NODE**, or **/START** qualifiers.

**/NODE=(*node-name*[,...])**

Issues the **SET** command to the Registry servers on the specified nodes in the order they are entered. The node names must be within the current cluster.

Cannot be used with the **/CLUSTER** or **/MASTER** qualifiers.

**/RESTART**

Restarts the Registry server on the specified node or nodes in the cluster.

Cannot be used with the **/ABORT**, **/EXIT**, or **/START** qualifiers.

**/START**

**/START** cannot be used with the **/ABORT**, **/EXIT**, or **/RESTART** qualifiers.

Starts the server process. The following options are available:

To change the default privileges:

```
/PRIVILEGES=(privilege[,...])
```

To change the default UIC:

```
/UIC=uic
```

To change the default quotas:

```
/AST_LIMIT=n  
/BUFFER_LIMIT=n  
/ENQUEUE_LIMIT=n  
/EXTENT=n  
/FILE_LIMIT=n  
/IO_BUFFERED=n  
/IO_DIRECT=n  
/JOB_TABLE_QUOTA=n  
/MAXIMUM_WORKING_SET=n  
/PAGE_FILE=n  
/QUEUE_LIMIT=n  
/SUBPROCESS_LIMIT=n  
/WORKING_SET=n
```

You can use the following alternate syntax to specify a list of quotas and their values:

```
/QUOTAS=(quota=n[,...])
```

The *quota* value is a PQL-style quota name (for example: ASTLM, BIOLM).

See the \$CREPRC system service in the [VSI OpenVMS System Services Reference Manual: A–GETUAI](https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-a-getuai/#JUN_147) [https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-a-getuai/#JUN\_147] for a list of PQL-style quota names and descriptions.

To change the image dump setting:

```
/DUMP  
/NODUMP (default)
```

Forces a process dump in the event of an abnormal process termination. The dump is written to SYS\$MANAGER: using the image file name and .DMP extension.

## Examples

1. \$ SET SERVER REGISTRY\_SERVER/RESTART/MASTER

This command restarts the detached Registry server on the master server.

2. \$ SET SERVER REGISTRY\_SERVER/LOG/CLUSTER

This command closes the current log files and opens new files on all systems across the cluster.

3. \$ SET SERVER REGISTRY\_SERVER/EXIT/NODE=(KAKADU,CAIRNS)

This command stops the detached Registry server process on nodes KAKADU and CAIRNS.

## SET SERVER SECURITY\_SERVER

SET SERVER SECURITY\_SERVER — Controls the Security server. **Requires SYSPRV privilege.**

### Format

**SET SERVER SECURITY\_SERVER**

### Description

The **SET SERVER SECURITY\_SERVER** command provides a system manager with the ability to start, stop, and restart the security server. The security server maintains information stored in the system intrusion and proxy databases.

The system intrusion database is used by **LOGINOUT**, DECnet-Plus, DECwindows, **SHOW INTRUSION**, **DELETE INTRUSION**, and other applications. For more information about the system intrusion database and \$DELETE\_INTRUSION, \$SCAN\_INTRUSION, and \$SHOW\_INTRUSION system services, see the [VSI OpenVMS System Services Reference Manual: A–GETUAI](https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-a-getuai/) [https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-a-getuai/] and [GETUTC-Z](https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-getutc-z/) [https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-getutc-z/]. For further information, see the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/) [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/].

The system proxy database is used by **AUTHORIZE**, DECnet-Plus, DFS, and other applications to access information stored in the network proxy database. Additional information can be found in the [VSI OpenVMS System Management Utilities Reference Manual, Volume 1: A-L](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-i-a-l/) [https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-i-a-l/] and [Volume 2: M-Z](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-m-z/) [https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-m-z/].

[docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/)]. See also the \$ADD\_PROXY, \$DELETE\_PROXY, \$DISPLAY\_PROXY, \$VERIFY\_PROXY system services in the *VSI OpenVMS System Services Reference Manual: A–GETUAI* [<https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-a-getuai/>] and *GETUTC-Z* [<https://docs.vmssoftware.com/vsi-openvms-system-services-reference-manual-getutc-z/>].

## Qualifiers

### /EXIT

Stops the detached security server process.

/EXIT cannot be used with any other qualifier.

### /RESTART

Restarts the detached security server process.

/RESTART cannot be used with any other qualifier.

### /START

Starts the detached security server process.

/START cannot be used with any other qualifier.

## Examples

1. \$ SET SERVER SECURITY\_SERVER/EXIT

This command stops the detached security server process.

2. \$ SET SERVER SECURITY\_SERVER/RESTART

This command restarts the detached security server process.

## SET SHADOW (Alpha/Integrity servers Only)

SET SHADOW — Changes the characteristics of shadow sets created using Volume Shadowing for OpenVMS. For more information about volume shadowing, see the *VSI OpenVMS Volume Shadowing Guide* [<https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/>] manual. **Requires** SYSPRV privilege.

## Format

SET SHADOW [*device-name*[:]]

## Parameter

*device-name*[:]

Specifies the name of a shadow set (DSAn:) or shadow set member (ddcu:), depending on the command qualifiers (see parameter formats specified in some qualifier descriptions).

For most qualifiers that take a shadow set (DSA $n$ ;) as a parameter the **/ALL** qualifier can be used in place of the shadow set name to indicate that the requested action applies to all shadow sets on the system. (Exceptions are noted in the description of **/ALL**.)

## Description

The **SET SHADOW** command and its qualifiers are designed to give the user greater control over the behavior of shadow sets. These commands act upon the shadow set (also known as the virtual unit) or, in some cases, on the individual shadow set member that you specify.

Unless otherwise noted, the qualifier settings typically remain in effect until they are changed using either the **SET SHADOW** or **SET DEVICE** command or until the shadow set or shadow set member is dismounted. If the shadow set is remounted or a shadow set member is returned to the shadow set from which it was dismounted, the settings must be specified again.

Some **SET SHADOW** qualifiers also can be specified using the **SET DEVICE** command, where they have the same effect. However, if your focus is on changing characteristics of shadow sets, the **SET SHADOW** command provides more options.

---

## Note

The following qualifiers are used exclusively to manage host-based minimerge (HBMM) operations and do not apply to other operations:

**/DELETE**  
**/DISABLE**  
**/ENABLE**  
**/NAME**  
**/POLICY**

If you specify any other (non-HBMM) qualifiers in a command that includes HBMM qualifiers, the command will fail.

---

## Qualifiers

**/ABORT\_VIRTUAL\_UNIT DSA $n$ :**  
**/ABORT\_VIRTUAL\_UNIT /ALL**

Aborts mount verification on the specified shadow set or on all shadow sets in mount verification on the system.

Use this qualifier when you know that the unit cannot be recovered. When you use this qualifier, the shadow set must be in mount verification. The shadow set aborts mount verification immediately on the system from which the command is issued. If the shadow set is not in mount verification, this command returns the following error:

```
%SYSTEM-E-UNSUPPORTED, unsupported operation or function.
```

After this command completes, the shadow set still must be dismounted. Use the following command to dismount the shadow set:

```
$ DISMOUNT/ABORT/OVERRIDE=CHECKS DSA $n$ :
```

**/ALL**

Causes the command to operate on all shadow sets that are mounted on the system from which the command is issued.

**/ALL** can be used instead of **DSAn:** in most commands that take a shadow set device specification as a parameter. Exceptions are **/DEMAND\_MERGE**, **/DELETE**, and **/EVALUATE=RESOURCES**. **/ALL** also cannot be specified with **/POLICY** or any qualifier that operates only on individual shadow set members (for example, **/MEMBER\_TIMEOUT** and **/FORCE\_REMOVAL**).

**/CONFIRM****/NOCONFIRM (default)**

Specifies whether a query is made before each merge operation to confirm that the operation should be performed on the designated shadow set.

This qualifier can be used only in conjunction with the **/DEMAND\_MERGE** qualifier.

The following responses are valid in response to the query:

- Affirmative: YES, TRUE, or 1.
- Negative: NO, FALSE, 0 (zero), or pressing the **Return** key.
- End the process: QUIT or **Ctrl/Z**.
- When you enter ALL, the command continues to process, but no further prompts are given.

You can enter word responses in uppercase or lowercase letters, and words can be abbreviated to one or more letters. If you enter an illegal response, DCL redisplay the prompt. (See the **SET SHADOW Examples** section.)

**/COPY\_SOURCE ddcu:****/COPY\_SOURCE DSAn:****/COPY\_SOURCE /ALL**

Specifies which source member of a shadow set to use as the source for read data during full copy operations when a third member is added to a shadow set that contains two full members. This qualifier affects only those copy operations that do not use disk copy data (DCD) commands. The source specified by this qualifier persists until the shadow set is dismounted.

Some storage controllers, such as the HSG80, have a read-ahead cache, which significantly improves a device's read performance. Copy operations normally alternate reads between the two source members, which effectively nullifies the benefits of the read-ahead cache. This qualifier lets you force all reads from a single, specified source member for the duration of a copy operation.

In addition to improving copy performance, **/COPY\_SOURCE** can be used to prevent read operations from a specific shadow set member that is considered unreliable. By specifying only the healthy shadow set member, the copy operations can continue to completion. The unreliable shadow set member can be removed once the copy operation completes successfully.

If a shadow set (**DSAn:**) is specified, all reads for full copy operations are performed from the device that is the current "master" member, regardless of the physical location of that device.

If a shadow set member (**ddcu:**) is specified, that member is used as the read source for all copy operations. This setting allows you to choose any source member. For example, you can choose

a source member that is at the same site as the member being added, rather than using a master member that is not at the same site.

If **/ALL** is specified, all reads for full copy operations on all currently mounted virtual units are performed from the master member.

**/DELETE DSA<sub>n</sub>:**  
**/DELETE /NAME**

Used in conjunction with **/POLICY=HBMM**, **/DELETE** removes a host-based minimerge (HBMM) policy from a specified shadow set, or deletes an HBMM named policy from the entire cluster. For example, the following command removes the policy that is currently associated with shadow set DSA1:

```
$ SET SHADOW /DELETE DSA1 /POLICY=HBMM
```

In contrast, the following command removes COMPANY\_POLICY from the cluster:

```
$ SET SHADOW /DELETE /NAME=COMPANY_POLICY /POLICY=HBMM
```

You cannot delete the NODEFAULT policy.

You cannot specify **/ALL** with **/DELETE**.

**/DEMAND\_MERGE DSA<sub>n</sub>:**

Initiates a merge operation on the specified shadow set. This qualifier is useful if the shadow set was created with the **INITIALIZE/SHADOW** command without the use of the **/ERASE** qualifier. For more information about using **/DEMAND\_MERGE**, see the relevant section in the [VSI OpenVMS Volume Shadowing Guide](https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/#demand_merge_start_merge_oper_sect) [[https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/#demand\\_merge\\_start\\_merge\\_oper\\_sect](https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/#demand_merge_start_merge_oper_sect)].

You cannot specify **/ALL** with **/DEMAND\_MERGE**.

An OPCOM message is displayed for each shadow set indicating that a demand merge has been invoked and recording the process ID (PID) of the process that executed the command. For example:

```
%%%%%%%%%% OPCOM 9-MAR-2004 10:35:23.24 %%%%%%%%%%
Message from user SYSTEM on NODE1
Demand Merge requested for _DSA721:, PID: 2760009A
```

**/DISABLE=HBMM DSA<sub>n</sub>:**  
**/DISABLE=HBMM /ALL**  
**/DISABLE=SPLIT\_READ\_LBNS**

Disables host-based minimerge (HBMM) on the specified shadow set or clusterwide on all shadow sets.

**/DISABLE=SPLIT\_READ\_LBNS** disables the split behavior of logical block numbers and as a result the reads are alternated between the source shadow set members having the same read\_cost and device queue length.

**/ENABLE=HBMM**  
**/ENABLE=SPLIT\_READ\_LBNS**

Enables host-based minimerge (HBMM) on the specified shadow set or across the entire cluster if an applicable HBMM policy exists.

**/ENABLE=SPLIT\_READ\_LBNS** logically divides the shadow set members having the same read cost into equal groups of Logical Block Numbers (LBNS). When a virtual unit performs a read, it does so by reading from the corresponding LBN group. This results in the maximum usage of the controller read-ahead cache.

### **/EVALUATE=RESOURCES**

Forces the system to evaluate whether it should act on most shadow copy and merge operations currently being managed on the system. It cancels most operations and then, based on the value of system parameter **SHADOW\_MAX\_COPY** and the copy/merge priority of each shadow set), it evaluates the order in which the pending copies and merges should be restarted.

**RESOURCES** is the only supported value for **/EVALUATE**, and it must be included.

**/EVALUATE** does not apply to MSCP-based minimerge operations. MSCP-based minimerge operations are not subject to cancellation and restart by **/EVALUATE**.

This command is intended to be used after changing the value of the dynamic system parameter **SHADOW\_MAX\_COPY** or after issuing a **SET SHADOW /PRIORITY=n** command for a shadow set. After a suitable delay, all available **SHADOW\_MAX\_COPY** slots on the system are allocated using the priority list.

### **/FORCE\_REMOVAL ddcu:**

### **/NOFORCE\_REMOVAL ddcu:**

Expels the specified shadow set member from the shadow set. The specified device must be a member of a shadow set that is mounted on the system where the command is issued. You cannot specify **/ALL** with **/FORCE\_REMOVAL**.

If connectivity to a device has been lost and the shadow set is in mount verification, this qualifier causes the member to be expelled from the shadow set immediately.

If the shadow set is not currently in mount verification, no immediate action is taken. If connectivity to a device has been lost but the shadow set is not in mount verification, this qualifier lets you flag the member to be expelled from the shadow set as soon as the shadow set enters mount verification. If no action has been taken on the specified member and you wish to clear the flag, use **/NOFORCE\_REMOVAL**.

If the shadow set is dismounted before the member is expelled, the **FORCE\_REMOVAL** request expires.

### **/LOG**

Instructs the volume shadowing software to display a brief message confirming that the **SET SHADOW** command completed. If **/OUTPUT** is also specified, this information is written to the output file.

### **/MEMBER\_TIMEOUT=n ddcu:**

Specifies the timeout value to be used for a shadow set member. The specified device must be a member of a shadow set that is mounted on the system where the command is issued.

The value supplied by this qualifier overrides the system parameter **SHADOW\_MBR\_TMO** for this specific device. Each member of a shadow set can be assigned a different **MEMBER\_TIMEOUT** value.

The valid range for *n* is 1 through 16777215 seconds.

The timeout value set by **/MEMBER\_TIMEOUT** does not persist after the shadow set is dismounted.

**/MVTIMEOUT=*n* DSA*n*:**  
**/MVTIMEOUT=*n* /ALL**

Specifies the mount verification timeout value to be used for all shadow sets on the cluster or for the shadow set specified by its virtual unit name (DSA*n*:). The specified shadow set must be mounted on the system where the command is issued.

The value supplied by this qualifier overrides the value specified by the system parameter MVTIMEOUT for this specific shadow set.

---

## Note

You cannot change the value of MVTIMEOUT for a system disk. Any attempt to do so results in an error.

---

The valid range for *n* is 1 through 16777215 seconds.

The timeout value set by **/MVTIMEOUT** does not persist after the shadow set is dismounted.

**/NAME=*policy-name***

Used with **/POLICY=HBMM** to define a named host-based minimerge (HBMM) policy or used with **/DELETE** to delete a policy. The policy is defined clusterwide. See detailed descriptions under the [/DELETE](#) and [/POLICY](#) qualifiers.

Policy names are case insensitive and must consist of from 1 to 64 characters. Only letters, numbers, the dollar sign (\$), and the underscore (\_) are allowed.

If you create a default policy, you must assign it the name DEFAULT.

For details about creating and using policy names, see the relevant section in the [VSI OpenVMS Volume Shadowing Guide \[https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/#hbmm\\_policies\\_sect\]](https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/#hbmm_policies_sect).

**/OUTPUT=*file-name***

Outputs any messages to the specified file.

**/POLICY=HBMM[=*policy-name*]**  
**/POLICY=HBMM[=*policy-specification*]**

Creates or deletes a policy for host-based minimerge (HBMM).

HBMM is the only supported value for the **/POLICY** qualifier, and it must be included. You can optionally specify a named policy, including DEFAULT, or you can specify NODEFAULT to indicate that the shadow set to which it is applied is not to use HBMM, including any DEFAULT policy. For details about specifying policies and using the DEFAULT and NODEFAULT policy names, see the relevant section in the [VSI OpenVMS Volume Shadowing Guide \[https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/#hbmm\\_policies\\_sect\]](https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/#hbmm_policies_sect) manual.

When **/POLICY** is specified with **/DELETE**, it removes either a specified HBMM named policy or the HBMM policy for a specific shadow set. You cannot delete the NODEFAULT policy.

When **/POLICY** is specified with **/NAME**, it defines a clusterwide named policy. When no qualifiers other than **/NAME** or **/DELETE** are specified, **/POLICY** defines a policy for a specific shadow set.

Deleting bitmaps with the **DELETE/BITMAP** command causes a bitmap to be deleted. However, the shadowing software recognizes this condition and starts a new bitmap immediately. To disable HBMM bitmaps, you have to use the command **SET SHADOW/DISABLE=HBMM**.

When defining a policy, you use five keywords (**MASTER\_LIST**, **COUNT**, **RESET\_THRESHOLD**, **MULTIUSE**, and **DISMOUNT**) to control the placement and management of HBMM bitmaps. An HBMM policy specification consists of a list of these keywords enclosed within parentheses. Only the **MASTER\_LIST** keyword is required. If **COUNT** and **RESET\_THRESHOLD** are omitted, default values are applied.

The **MULTIUSE** and **DISMOUNT** keywords specify the number of bitmaps to be converted to multiuse bitmaps during the automatic and manual removal of members respectively. If **MULTIUSE** is omitted, then automatic minicopy on volume processing is not enabled. As a result, no HBMM bitmap is converted to multiuse bitmap. If **DISMOUNT** is omitted, only a maximum of 6 HBMM bitmaps can be used as multiuse bitmaps.

- **MASTER\_LIST=*list***

The **MASTER\_LIST** keyword is used to identify a set of systems as candidates for a master bitmap. The *list* value can be a single system name; a parenthesized, comma-separated list of system names; or the wildcard character, as shown in the following examples:

```
MASTER_LIST=NODE1 MASTER_LIST=(NODE1, NODE2, NODE3) MASTER_LIST=*
```

When the system list consists of a single system name or the wildcard character, parentheses are optional.

An HBMM policy must include at least one **MASTER\_LIST**. Multiple master lists are optional. If a policy has multiple master lists, the entire policy must be enclosed with parentheses, and each constituent master list must be separated by a comma as shown in the following example:

```
(MASTER_LIST=(NODE1, NODE2) , MASTER_LIST=(NODE3, NODE4) )
```

There is no significance to the position of a system name in a master list.

- **COUNT=*n***

The **COUNT** keyword specifies how many systems in the master list can have master bitmaps. Therefore, the **COUNT** keyword and its associated **MASTER\_LIST** must be enclosed within a single parenthetical statement.

The **COUNT** value specifies the number of systems on which you want master bitmaps. It does not necessarily mean that the first *n* systems in the list will be chosen.

When the **COUNT** keyword is omitted, the default value is 6 or the number of systems in the master list, whichever is smaller.

You cannot specify more than one **COUNT** keyword per master list.

**Examples:**

```
(MASTER_LIST=(NODE1,NODE2,NODE3), COUNT=2)
```

```
(MASTER_LIST=(NODE1,NODE2,NODE3), COUNT=2),  
(COUNT=2, MASTER_LIST=(NODE4,NODE5,NODE6))
```

- **RESET\_THRESHOLD=*n***

The RESET\_THRESHOLD keyword specifies the number of blocks that can be set before the bitmap is eligible to be cleared. Each set bit in a master bitmap corresponds to a set of blocks to be merged, so this value can affect the merge time.

Bitmaps are eligible to be cleared when the RESET\_THRESHOLD is exceeded. However, the reset is not guaranteed to occur immediately when the threshold is crossed. For more information about choosing a value for this attribute, see the relevant section in the [VSI OpenVMS Volume Shadowing Guide \[https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/#reset\\_threshold\\_value\\_sect\]](https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/#reset_threshold_value_sect) manual.

The reset threshold is associated with a specific HBMM policy, so the RESET\_THRESHOLD keyword can be defined only once in a policy specification. Because its scope is the entire policy, the RESET\_THRESHOLD keyword cannot be specified inside a constituent master list when the policy uses multiple master lists.

When the RESET\_THRESHOLD keyword is omitted, the value of 1,000,000 is used by default. See the following example:

```
(MASTER_LIST=*, COUNT=4, RESET_THRESHOLD=1000000)
```

**Example:**

The command in the following example defines the HBMM named policy POLICY\_2, which has two master lists. Having multiple master lists can be useful in a multiple-site OpenVMS Cluster configuration because a policy can be defined to ensure that at least one surviving system has an HBMM bitmap in the event of an outage at one or more sites.

```
$ SET SHADOW /POLICY=HBMM=( -  
_$(MASTER_LIST=(NODE1,NODE2,NODE3), COUNT=2), -  
_$(MASTER_LIST=(NODE4,NODE5,NODE6), COUNT=2), -  
_$(RESET_THRESHOLD=150000) -  
_$/NAME=POLICY_2
```

In a policy with multiple master lists, a given system name can appear in only one master list.

A shadow set need not be mounted to have an HBMM policy defined for it.

See the **SET SHADOW** [Examples](#) section for several more **/POLICY** examples.

- **MULTIUSE=*n***

The MULTIUSE keyword enables automatic minicopy on volume processing. *n* specifies the number of existing HBMM master bitmaps to be converted to multiuse bitmaps in the event that a shadow set member is removed from the shadow set by the shadowing driver.

During a loss of connectivity to a site or controller, shadowing may remove a member from the shadow set. When the member is added back to the shadow set, a full shadow copy occurs.

By converting a few of the HBMM bitmaps to multiuse, all writes that are performed to the shadow set are recorded. Thus, when the member is added back to the shadow set, the multiuse bitmap can be used for a minicopy operation. This is much faster than a full copy operation.

The value of *n* cannot exceed the implied or explicit value of COUNT. If MULTIUSE is not specified, then bitmaps are not converted to multiuse and a full copy operation is required. Fatal drive errors that remove a shadow set member do not cause a multiuse conversion as the drive has to be replaced and therefore requires a full copy operation.

- **DISMOUNT=*n***

The DISMOUNT keyword allows all the 12 write bitmaps to be used by Shadowing as multiuse bitmaps, thereby reducing the single point of failure of single minicopy master bitmaps. *n* specifies the number of HBMM bitmaps to be converted to multiuse bitmaps every time a member is dismounted from a shadow set with the following command:

```
DISMOUNT/POLICY=MINICOPY
```

**/PRIORITY=*n* DSA*n*:**

Overrides the current default priority setting. Priorities range from 0 (lowest) to 10000 (highest). The default priority is 5000. A shadow set with a priority of 0 is never considered for a merge or a copy on the system.

When a recovery operation (that is, either a merge or a copy) is needed on multiple shadow sets, the shadow sets are recovered in priority order from highest to lowest. The priority setting is system specific; any change in priority made on a single system does not propagate to the entire cluster and does not persist across a system reboot.

Once this qualifier has been applied to a virtual unit that is mounted, the setting persists across any subsequent DISMOUNT and MOUNT commands.

**/READ\_COST=*n* *ddcu*:**

**/READ\_COST=*n* DSA*n*:**

**/READ\_COST=*n* \$*n*\$DGA*n*:**

Enables you to modify the default cost assigned to each shadow set member (*ddcu*:). By modifying the assignments, you can bias the reads in favor of one member of a two-member shadow set or, in the case of three-member shadow sets, in favor of one or two members of the set over the remaining members. The device specified must be a shadow set or member of a shadow set that is mounted on the system where the command is issued.

The valid range for the specified cost is 1 through 65,535 units.

The shadowing driver assigns default READ\_COST values to shadow set members when each member is initially mounted. The default value depends on the device type and its configuration relative to the system mounting it. The following list of device types is ordered by the default READ\_COST assignments, from the lowest cost to the highest cost:

- DECram device
- Directly connected device in the same physical location
- Directly connected device in a remote location
- DECram served device

- Default value for other served devices

The value supplied by the **/READ\_COST** qualifier overrides the default assignment. The shadowing driver adds the value of the current queue depth of the shadow set member to the **READ\_COST** value and then reads from the member with the lowest value.

Different systems in the cluster can assign different costs to each shadow set member.

When this qualifier specifies a shadow set (DSAn:) instead of a shadow set member, the **/READ\_COST** qualifier switches the read cost setting for *all* shadow set members back to the default read cost settings established automatically by the shadowing software. The specified shadow set must be mounted on the system where the command is issued.

You cannot specify a value for **/READ\_COST** when you specify **/ALL**.

If the **/SITE** command qualifier has been specified, the shadowing driver takes site values into account when it assigns default **READ\_COST** values. In order for the shadowing software to determine whether a device is in the category of "directly connected device in a remote location", the **/SITE** command qualifier must have been applied to both the shadow set *and* the shadow set member.

Reads requested for a shadow set from a system at site 1 are performed from a shadow set member that is also at site 1. Reads requested for the same shadow set from site 2 can read from the member located at site 2.

#### **/RECOVERY\_OPTIONS= DELAY\_PER\_SERVED\_MEMBER=*n***

Allows the system manager to adjust the rating assigned to a system based on a delay assessed for each MSCP served shadow set member on that system. The value specified by this qualifier overrides the value established by the **SHADOW\_PSM\_RDLY** system parameter. The default delay for each MSCP served member is 30 seconds and the valid range for the specified delay is 0 through 65,535 seconds.

When a copy or merge operation is needed on a shadow set that is mounted on multiple systems, OpenVMS Volume Shadowing attempts to perform this work on a system that has a local connection to all of the shadow set members. Systems are rated with a penalty (delay time) assessed for each shadow set member that is MSCP served to the system. No delay is added for local members, so a system with all locally accessible shadow set members is likely to perform the work before a system where one or more members is served.

IF **/ALL** is also specified, the specified delay is applied to all currently mounted shadow sets.

See the relevant section in the [VSI OpenVMS Volume Shadowing Guide \[https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/#manage\\_copy\\_merge\\_sect\]](https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/#manage_copy_merge_sect) for more information.

#### **/RESET\_COUNTERS**

Resets the shadowing specific counters that are maintained for each shadow set. These counters can be displayed using the **SHOW SHADOW** command.

The counters that are reset to 0 are the following:

HBMM Reset Count  
Copy Hotblocks  
Copy Collisions  
SCP Merge Repair Cnt

## APP Merge Repair Cnt

The HBMM Reset Count is a running total of the number of times that the HBMM Reset Threshold was exceeded and therefore, the number of times the bitmaps were reset. (The threshold is set by the `RESET_THRESHOLD` keyword in the `/POLICY` qualifier.) For more information, see the relevant section in the [VSI OpenVMS Volume Shadowing Guide \[https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/#manage\\_copy\\_merge\\_sect\]](https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/#manage_copy_merge_sect).

**/SITE=*n* ddcu:**

**/SITE=*n* DSA*n*:**

Indicates to the shadowing driver the site location of the specified shadow set (DSA*n*:) or shadow set member (ddcu:).

The `SHADOW_SITE_ID` system parameter defines the default site location of the shadow set. You can override the default location of the shadow set with the `/SITE` qualifier.

The valid range for the site location, represented by *n*, is 1 through 255.

If `/ALL` is specified, all virtual units are assigned the new value. The shadow set's member site values remain unchanged.

After you apply this qualifier, the setting remains in effect until you change it using a **SET SHADOW/SITE** command.

This qualifier can improve read performance because the member that is physically local to the system will be the preferred disk from which to read, provided that you specify the `/SITE` qualifier for each shadow set member and for the shadow set. (In a Fibre Channel configuration, shadow set members at different sites are directly attached to the system. For the Volume Shadowing and OpenVMS Cluster software, there is no distinction between local and remote in multiple-site Fibre Channel configurations.)

**/STALL=WRITES[=*nnn*]**

**/NOSTALL=WRITES[=*nnn*]**

Using the `/STALL=WRITES[=nnn]` qualifier, you can stall the write operations for *nnn* seconds. *nnn* is the number of seconds for which you can stop write operations. If no value is specified for *nnn*, the lock is released after `SHADOW_MBR_TMO` seconds. The default is `SHADOW_MBR_TMO`.

`/NOSTALL=WRITES[=nnn]` releases the lock after *nnn* seconds so that write operations can continue on the shadow set.

## Examples

1. \$ ! Command sequence used on system 1 at site 1:  
\$ MOUNT/SYSTEM DSA0:/SHADOW=(\$1\$DGA0:,\$1\$DGA1:) TEST  
\$ SET SHADOW/SITE=1 DSA0:  
\$ !  
\$ ! Command sequence used on system 2 at site 2:  
\$ MOUNT/SYSTEM DSA0:/SHADOW=(\$1\$DGA0:,\$1\$DGA1:) TEST  
\$ SET SHADOW/SITE=2 DSA0:  
\$ !  
\$ ! Commands used on both system 1 and system 2:  
\$ SET SHADOW/SITE=1 \$1\$DGA0:  
\$ SET SHADOW/SITE=2 \$1\$DGA1:

In this example, the system at site 1 will perform reads from \$1\$DGA0, which is located at that site, while the system at site 2 will perform reads from \$1\$DGA1, which is located at site 2.

- ```
2. $ SET SHADOW DSA1: /POLICY=HBMM= -
   _$ (MASTER_LIST=(NODE1,NODE2,NODE3), COUNT=2, -
   _$   RESET_THRESHOLD=75000
   )
```

This command defines an HBMM policy for shadow set DSA1:. The policy specifies that no more than two systems of the three systems listed can have an HBMM master bitmap. Once 75000 blocks have been modified on DSA1:, any existing HBMM bitmaps are zeroed.

- ```
3. $ SET SHADOW /POLICY=HBMM=(MASTER_LIST= -
   _$ (NODE1,NODE2,NODE3), RESET_THRESHOLD=75000, COUNT=2) -
   _$ /NAME=HONESTY_IS_BEST
```

This command defines the named policy HONESTY\_IS\_BEST. This policy is available to all cluster members, but is not applied to any specific shadow set.

- ```
4. $ SET SHADOW DSA1: /POLICY=HBMM=HONESTY_IS_BEST
```

This command associates the named policy HONESTY\_IS\_BEST with shadow set DSA1.

- ```
5. $ SET SHADOW /POLICY=HBMM=( -
   _$   (MASTER_LIST=(NODE1,NODE2,NODE3), COUNT=2), -
   _$   (MASTER_LIST=(NODE4,NODE5,NODE6), COUNT=2), -
   _$   RESET_THRESHOLD=150000) -
   _$   /NAME=POLICY_2
```

This command defines the HBMM named policy POLICY\_2, which has two master lists.

- ```
6. $ SET SHADOW DSA2:/POLICY=HBMM=POLICY_2
```

This command associates the named policy POLICY\_2 with shadow set DSA2.

- ```
7. $ SET SHADOW /POLICY=HBMM /DELETE /NAME=POLICY_2
```

This command deletes the named policy POLICY\_2. Note that any shadow set that had acquired the attributes of POLICY\_2 by execution of a **SET SHADOW DSA<sub>n</sub>: /POLICY=HBMM=POLICY\_2** command is *not* affected. Changes made to a named policy are *not* retroactive to a mounted shadow set that was assigned the characteristics of a previous version of that named policy.

- ```
8. $ SET SHADOW DSA1: /POLICY=HBMM /DELETE
```

This command deletes the existing HBMM policy from DSA1:. If this HBMM policy is enabled on DSA1:, you must first execute the following command to disable the policy before you can delete it:

```
$ SET SHADOW DSA1: /DISABLE=HBMM
```

- ```
9. $ SET SHADOW /DEMAND_MERGE/CONFIRM
   Allow merge of _DSA721:? [N]:y
   Allow merge of _DSA850:? [N]: TRUE
   Allow merge of _DSA1010:? [N]:N
   $
```

In this example, a merge operation is initiated on DSA721: and DSA850: but not on DSA1010:.

10. \$ SET SHADOW DSA1/POLICY=HBMM=(MASTER=\*,COUNT=12,MULTIUSE=12,DISMOUNT=1)

In this example, a policy is set in which all 12 bitmaps can be used as multiuse bitmaps. When you execute the command **DISMOUNT/POLICY=MINICOPY**, 1 minimerge bitmap is converted to multiuse bitmap. You can use this multiuse bitmap with the **MINICOPY** command to add the dismounted member back to the shadow set. In other words, it specifies that 12 bitmaps can be used during the automatic and 1 bitmap during the manual removal of the shadow set member.

11. \$ SET SHADOW DSA42 /STALL=WRITES

In this example, the writes are stalled to the shadow set for a period of SHADOW\_MBR\_TMO seconds.

12. \$ SET SHADOW DSA42 /STALL=WRITES=60

In this example, the writes are stalled to the shadow set for a period of 60 seconds.

13. \$ SET SHADOW DSA42 /NOSTALL=WRITES=30

In this example, the writes are allowed to the shadow set after a period of 30 seconds.

## SET SYMBOL

SET SYMBOL — Controls access to local and global symbols in command procedures.

### Format

**SET SYMBOL**

### Description

The **SET SYMBOL** command controls access to local and global symbols in command procedures by treating symbols as undefined. Because all global and local symbols defined in an outer procedure level are accessible to inner procedure levels, it is often necessary to mask these symbols without deleting them.

The **SET SYMBOL** command also controls whether DCL will attempt to translate the verb string (the first token on the command line) as a symbol before processing the line. The default behavior is that the translation is attempted. The advantage to changing this behavior is that a command procedure will not be affected by outer procedure level environments when invoking a command.

The symbol scoping context is different for local and global symbols. Local symbols are procedure level dependent. Local symbols defined in an outer subroutine level can be read at any inner subroutine level, but they cannot be written to. If you assign a value to a symbol that is local to an outer subroutine level, a new symbol is created at the current subroutine level; however, the symbol in the outer procedure level is not modified.

This means that the **SET SYMBOL/SCOPE=NOLOCAL** command causes all local symbols defined at an outer procedure level to be inaccessible to the current procedure level and any inner levels. For example, if **SET SYMBOL/SCOPE=NOLOCAL** was specified at procedure levels 2 and 4, procedure level 2 can read and write to only level 2 local symbols. Level 3 can read (but not write to) level 2 local symbols and can read and write to level 3 local symbols. Level 4 can read and write to only level 4 local symbols.

Global symbols are procedure-level independent. The current global symbol scoping context is applied subsequently to all procedure levels. Specifying the **/SCOPE=NOGLOBAL** qualifier causes all global symbols to become inaccessible for all subsequent commands until either the **/SCOPE=GLOBAL** qualifier is specified or the procedure exits to a previous level at which global symbols were accessible. In addition, specifying the **/SCOPE=NOGLOBAL** qualifier prevents you from creating any new global symbols until the **/SCOPE=GLOBAL** qualifier is specified.

When you exit a procedure level to return to a previous procedure, the symbol scoping context from the previous level is restored for both local and global symbols.

To display the current symbol scoping state, use the lexical function **F\$ENVIRONMENT** ("SYMBOL\_SCOPE").

## Qualifiers

### **/ALL (default)**

Specifies that the values of the **/SCOPE** qualifier pertain both to the translation of the first token on a command line and to general symbol substitution.

The **/ALL** qualifier is incompatible with the **/GENERAL** or the **/VERB** qualifier.

### **/GENERAL**

Specifies that the values of the **/SCOPE** qualifier pertain to the translation of all symbols except the first token on a command line.

The **/GENERAL** qualifier is incompatible with the **/ALL** or the **/VERB** qualifier.

### **/SCOPE=(keyword,...)**

Controls access to local and global symbols. Lets you treat symbols as being undefined. Possible keywords are as follows:

| Keyword  | Description                                                                                                                                             |
|----------|---------------------------------------------------------------------------------------------------------------------------------------------------------|
| NOLOCAL  | Causes all local symbols defined in outer procedure levels to be treated as being undefined by the current procedure and by all inner procedure levels. |
| LOCAL    | Removes any symbol translation limit set by the current procedure level.                                                                                |
| NOGLOBAL | Causes all global symbols to be inaccessible to the current procedure level and to all inner procedure levels unless otherwise changed.                 |
| GLOBAL   | Restores access to all global symbols.                                                                                                                  |

### **/VERB**

Specifies that the values of the **/SCOPE** qualifier pertain to the translation of the first token on a command line as a symbol before processing only. It does not affect general symbol substitution.

---

## Note

Caution must be used if the **SET SYMBOL/VERB/SCOPE** command is used more than once in a command procedure. Because DCL uses the translation behavior when looking for a label or subroutine, execution may be different running in one mode than in another. VSI recommends that

the **SET SYMBOL/VERB/SCOPE** command be used once as part of the command procedure setup and left in that mode for the duration of the procedure.

---

The **/VERB** qualifier is incompatible with the **/ALL** or the **/GENERAL** qualifier.

## Examples

1. `$ SET SYMBOL/SCOPE=NOLOCAL`

In this example, all local symbols defined in outer procedure levels are now undefined for the current procedure level and all inner procedure levels.

2. `$ SET SYMBOL/SCOPE=NOGLOBAL`

In this example, all global symbols are now inaccessible to the current procedure level and all inner procedure levels unless otherwise changed.

3. 

```
$ NOW := SHOW TIME
$ !
$ NOW
      3-NOV-2001 11:48:58
$ !
$ SET SYMBOL /VERB /SCOPE=NOGLOBAL
$ NOW
%DCL-W-IVVERB, unrecognized command verb-check validity and spelling
\NOW\
$ !
$ SHOW SYMBOL NOW
      NOW == "SHOW TIME"
```

This example demonstrates the use of the **/VERB** qualifier.

The symbol `NOW` is assigned to the **SHOW TIME** command. The next line shows the default behavior, where DCL attempts to translate the first string on the command line (`NOW`). Because `NOW` translates to the **SHOW TIME** command, this is used instead of `NOW`.

The **SET SYMBOL** command on the next line changes the behavior so that DCL does not attempt a translation. When `NOW` is subsequently entered, DCL uses the string `NOW` as the command verb and cannot find it in the command table. This results in the error message.

Notice that the scoping of the verb translation has no effect on general symbol translations, as demonstrated by the **SHOW SYMBOL** command in the example.

## SET TERMINAL

**SET TERMINAL** — Sets the characteristics of a terminal. Entering a qualifier changes a characteristic; omitting a qualifier leaves the characteristic unchanged.

### Format

```
SET TERMINAL[device-name[:]]
```

### Parameter

*device-name*[:]

Specifies the device name of the terminal. The default is SYSS\$COMMAND if that device is a terminal. If the device is not a terminal, an error message is displayed.

## Description

The **SET TERMINAL** command modifies specific terminal characteristics for a particular application or overrides system default characteristics. (These defaults are defined at each installation, based on the most common type of terminal in use.) The default characteristics for terminals are listed in *Figure 2, "Default Characteristics for Terminals"*. The table extends across two pages to document a range of terminals.

The terminal characteristics, local or remote, are determined automatically by the terminal driver for terminals that have the modem characteristic enabled. These characteristics are not affected by the **SET TERMINAL** command. For example, when you successfully dial in to an OpenVMS system processor, you establish your terminal as remote. When you hang up, the terminal characteristic is set back to local.

The set of terminals supported by the OpenVMS system includes a set of VT100 family terminals that support special DIGITAL ANSI characteristics and escape sequences. For a description of these special characteristics and escape sequences, see the *VSI OpenVMS I/O User's Reference Manual* [<https://docs.vmssoftware.com/vsi-openvms-io-user-s-reference-manual/>].

Figure 2. Default Characteristics for Terminals

| Name                | Unknown | Foreign | LA12 | LA34<br>LA38<br>LA100<br>LQP02 | LA36 | LA120 | LA210<br>LN03<br>LN01K | VT101 | VT102 |
|---------------------|---------|---------|------|--------------------------------|------|-------|------------------------|-------|-------|
| ADVANCED_VIDEO      | No      | *       | No   | No                             | No   | No    | No                     | No    | Yes   |
| ALTYPEAHD           | No      | *       | *    | *                              | *    | *     | *                      | *     | *     |
| ANSI_CRT            | No      | *       | No   | No                             | No   | No    | No                     | Yes   | Yes   |
| APPLICATION_KEYPAD  | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| /NUMERIC_KEYPAD     |         |         |      |                                |      |       |                        |       |       |
| AUTOAUD             | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| BLOCK_MODE          | No      | *       | No   | No                             | No   | No    | No                     | No    | No    |
| BRDCSTMBX           | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| BROADCAST           | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| CRFILL              | 0       | 0       | 0    | 0                              | 0    | 0     | 0                      | 0     | 0     |
| DEC_CRT             | No      | *       | No   | No                             | No   | No    | No                     | Yes   | Yes   |
| DEC_CRT2            | No      | *       | No   | No                             | No   | No    | No                     | No    | No    |
| DEC_CRT3            | No      | *       | No   | No                             | No   | No    | No                     | No    | No    |
| DEC_CRT4            | No      | *       | No   | No                             | No   | No    | No                     | No    | No    |
| DEC_CRT5            | No      | No      | No   | No                             | No   | No    | No                     | No    | No    |
| DIALUP              | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| DISCONNECT          | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| DMA                 | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| ECHO                | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| EDIT_MODE           | No      | *       | No   | No                             | No   | No    | No                     | No    | Yes   |
| EIGHT_BIT           | *       | *       | No   | No                             | No   | No    | Yes                    | No    | No    |
| ESCAPE              | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| FALLBACK            | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| FORM                | *       | *       | Yes  | Yes                            | No   | Yes   | Yes                    | No    | No    |
| FRAME               | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| FULLDUP/HALFDUP     | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| HANGUP              | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| HARDCOPY/SCOPE      | *       | *       | Hard | Hard                           | Hard | Hard  | Hard                   | Scope | Scope |
| HOSTSYNC            | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| INSERT/OVERSTRIKE   | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| LFFILL              | 0       | 0       | 0    | 0                              | 0    | 0     | 0                      | 0     | 0     |
| LINE_EDITING        | No      | *       | No   | No                             | No   | No    | No                     | *     | *     |
| LOCAL_ECHO          | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| LOWERCASE/UPPERCASE | *       | *       | Low  | Low                            | Low  | Low   | Low                    | Low   | Low   |
| MODEM               | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| PAGE                | *       | *       | 66   | 66                             | 66   | 66    | 66                     | 24    | 24    |
| PARITY              | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| PRINTER_PORT        | No      | *       | No   | No                             | No   | No    | No                     | No    | Yes   |
| READSYNC            | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| REGIS               | No      | *       | No   | No                             | No   | No    | No                     | No    | No    |
| REMOTE              | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| SECURE_SERVER       | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| SET_SPEED           | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| SIXEL_GRAPHICS      | No      | *       | No   | No                             | No   | No    | Yes                    | No    | No    |
| SOFT_CHARACTERS     | No      | *       | No   | No                             | No   | No    | No                     | No    | No    |
| SPEED               | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| SYSPASSWORD         | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| TAB                 | *       | *       | Yes  | No                             | No   | Yes   | No                     | Yes   | Yes   |
| TTSYNC              | *       | *       | Yes  | Yes                            | Yes  | Yes   | Yes                    | Yes   | Yes   |
| TYPE_AHEAD          | *       | *       | *    | *                              | *    | *     | *                      | *     | *     |
| WIDTH               | *       | *       | 80   | 132                            | 132  | 132   | 80                     | 80    | 80    |
| WRAP                | *       | *       | Yes  | Yes                            | Yes  | Yes   | Yes                    | Yes   | Yes   |

\* Indicates that the current setting is not affected by terminal type.

@ Optional terminal feature.

ZK-5170a-AI

| Name                | VT100 | VT125 | VT131 |       | VT200 | VT300 | VT400 | VT500 |
|---------------------|-------|-------|-------|-------|-------|-------|-------|-------|
|                     | VT105 |       | VT132 | VT173 |       |       |       |       |
| ADVANCED_VIDEO      | @     | @     | Yes   | Yes   | Yes   | Yes   | Yes   | Yes   |
| ALTYPEAHD           | *     | *     | *     | *     | *     | *     | *     | *     |
| ANSI_CRT            | Yes   | Yes   | Yes   | Yes   | Yes   | Yes   | Yes   | Yes   |
| APPLICATION_KEYPAD  | *     | *     | *     | *     | *     | *     | *     | *     |
| /NUMERIC_KEYPAD     |       |       |       |       |       |       |       |       |
| AUTOBAUD            | *     | *     | *     | *     | *     | *     | *     | *     |
| BLOCK_MODE          | No    | No    | Yes   | Yes   | No    | No    | No    | No    |
| BRDCSTMBX           | *     | *     | *     | *     | *     | *     | *     | *     |
| BROADCAST           | *     | *     | *     | *     | *     | *     | *     | *     |
| CRFILL              | 0     | 0     | 0     | 0     | 0     | 0     | 0     | 0     |
| DEC_CRT             | Yes   | Yes   | Yes   | No    | Yes   | Yes   | Yes   | Yes   |
| DEC_CRT2            | No    | No    | No    | No    | Yes   | Yes   | Yes   | Yes   |
| DEC_CRT3            | No    | No    | No    | No    | No    | Yes   | Yes   | Yes   |
| DEC_CRT4            | No    | No    | No    | No    | No    | No    | Yes   | Yes   |
| DEC_CRT5            | No    | No    | No    | No    | No    | No    | No    | Yes   |
| DIALUP              | *     | *     | *     | *     | *     | *     | *     | *     |
| DISCONNECT          | *     | *     | *     | *     | *     | *     | *     | *     |
| DMA                 | *     | *     | *     | *     | *     | *     | *     | *     |
| ECHO                | *     | *     | *     | *     | *     | *     | *     | *     |
| EDIT_MODE           | @     | @     | @     | Yes   | Yes   | Yes   | Yes   | Yes   |
| EIGHT_BIT           | No    | No    | No    | No    | Yes   | Yes   | Yes   | Yes   |
| ESCAPE              | *     | *     | *     | *     | *     | *     | *     | *     |
| FALLBACK            | *     | *     | *     | *     | No    | No    | No    | No    |
| FORM                | No    | No    | No    | No    | No    | No    | No    | No    |
| FRAME               | *     | *     | *     | *     | *     | *     | *     | *     |
| FULLDUP/HALFDUP     | *     | *     | *     | *     | *     | *     | *     | *     |
| HANGUP              | *     | *     | *     | *     | *     | *     | *     | *     |
| HARDCOPY/SCOPE      | Scope | Scope | Scope | Scope | Scope | Scope | Scope | Scope |
| HOSTSYNC            | *     | *     | Yes   | Yes   | *     | *     | *     | *     |
| INSERT/OVERSTRIKE   | *     | *     | *     | *     | *     | *     | *     | *     |
| LFFILL              | 0     | 0     | 0     | 0     | 0     | 0     | 0     | 0     |
| LINE_EDITING        | *     | *     | *     | No    | *     | *     | *     | *     |
| LOCAL_ECHO          | *     | *     | *     | *     | *     | *     | *     | *     |
| LOWERCASE/UPPERCASE | Low   | Low   | Low   | Low   | Low   | Low   | Low   | Low   |
| MODEM               | *     | *     | *     | *     | *     | Yes   | Yes   | Yes   |
| PAGE                | 24    | 24    | 24    | 16    | 24    | 24    | 24    | 24    |
| PARITY              | *     | *     | *     | *     | *     | *     | *     | *     |
| PRINTER_PORT        | @     | Yes   | No    | No    | @     | Yes   | Yes   | Yes   |
| READSYNC            | *     | *     | *     | *     | *     | *     | *     | *     |
| REGIS               | No    | Yes   | No    | No    | @     | @     | @     | @     |
| REMOTE              | *     | *     | *     | *     | *     | *     | *     | *     |
| SECURE_SERVER       | *     | *     | *     | *     | *     | *     | *     | *     |
| SET_SPEED           | *     | *     | *     | *     | *     | *     | *     | *     |
| SIXEL_GRAPHICS      | No    | Yes   | No    | No    | @     | @     | @     | @     |
| SOFT_CHARACTERS     | No    | No    | No    | No    | @     | @     | @     | @     |
| SPEED               | *     | *     | *     | *     | *     | *     | *     | *     |
| SYSPASSWORD         | *     | *     | *     | *     | *     | *     | *     | *     |
| TAB                 | Yes   | Yes   | Yes   | Yes   | Yes   | Yes   | Yes   | Yes   |
| TTSYNC              | Yes   | Yes   | Yes   | Yes   | Yes   | Yes   | Yes   | Yes   |
| TYPE_AHEAD          | *     | *     | *     | *     | *     | *     | *     | *     |
| WIDTH               | 80    | 80    | 80    | 80    | 80    | 80    | 80    | 80    |
| WRAP                | Yes   | Yes   | Yes   | Yes   | Yes   | Yes   | Yes   | Yes   |

\* Indicates that the current setting is not affected by terminal type.

@ Optional terminal feature.

ZK-5171a-AI

## Qualifiers

/ADVANCED\_VIDEO

/NOADVANCED\_VIDEO

Controls whether the terminal has advanced video attributes and is capable of 132-column video.

If the terminal width is set to 132 columns and you specify the **/ADVANCED\_VIDEO** qualifier,

the terminal page limit is set to 24 lines. If you specify the **/NOADVANCED\_VIDEO** qualifier, the terminal page limit is set to 14 lines.

### **/ALTYPEAHD**

Causes the terminal driver to create a permanent, alternate type-ahead buffer. The system parameter **TTY\_ALTYPEAHD** determines the size of the type-ahead buffer.

To enable **/ALTYPEAHD**, you must also set the qualifier **/TYPE\_AHEAD**.

You should specify **SET TERMINAL/PERMANENT/ALTYPEAHD** in **SY\$STARTUP:SYSTARTUP\_VMS.COM** for those communication lines that require this capability.

To use this feature interactively, specify **SET TERMINAL/PERMANENT/ALTYPEAHD**. This specification is effective at your next login.

### **/ANSI\_CRT (default)**

#### **/NOANSI\_CRT**

Controls whether the terminal conforms to ANSI CRT programming standards. Because ANSI standards are a proper subset of the **DEC\_CRT** characteristics, the default for all VT100 family terminals is **/ANSI\_CRT**.

### **/APPLICATION\_KEYPAD**

Specifies that the keypad is to be set to application keypad mode, which allows you to enter DCL commands defined with the **DEFINE/KEY** command. By default, the terminal is set to numeric keypad mode.

### **/AUTOBAUD**

#### **/NOAUTOBAUD**

Controls whether the terminal baud rate is set when you log in and sets the default terminal speed to 9600. You must press Return two or more times at intervals of at least 1 second for the baud rate to be determined correctly. If you press a key other than Return, the **/AUTOBAUD** qualifier may detect the wrong baud rate. If this happens, wait for the login procedure to time out before continuing. The **/AUTOBAUD** qualifier must be used with the **/PERMANENT** qualifier.

The valid baud rates are as follows:

|     |      |      |       |        |
|-----|------|------|-------|--------|
| 50  | 150  | 1800 | 4800  | 38400  |
| 75  | 300  | 2000 | 7200  | 57600  |
| 110 | 600  | 2400 | 9600  | 76800  |
| 134 | 1200 | 3600 | 19200 | 115200 |

### **/BACKSPACE=keyword**

Controls how the system responds to the backspace key (**Ctrl/H**) in line editing mode. There are two possible keywords:

- **BACKSPACE** (default) – The terminal driver returns the user to the beginning of the line. (This is the traditional way OpenVMS has always worked.)
- **DELETE** – The terminal driver interprets the backspace key as a delete character instruction.

Note the following exceptions:

- If the terminal is set in **PASSALL** or **PASTHRU** mode, the backspace key is not interpreted as a delete character instruction.
- If the user issues an **IO\$\_READVBLK** with **IO\$\_M\_NOFILTR** or **IO\$\_READPBLK**, the backspace key is not interpreted as a delete character instruction.

You can use **SYSGEN** to make **/BACKSPACE=DELETE** the default for all terminals by setting the system parameter **TTY\_DEFCHAR3** to 16.

If the default is set to **DELETE**, the user can still go to the start of a line by pressing **F12** or by entering the following sequence: **Ctrl/V Ctrl/H Ctrl/H**.

If you use **SET HOST**, both the local node and the remote node must be capable of responding to your definition of the **BACKSPACE** key.

**/BLOCK\_MODE**  
**/NOBLOCK\_MODE**

Controls whether block mode transmission, local editing, and field protection are performed.

**/BRDCSTMBX**  
**/NOBRDCSTMBX**

Controls whether broadcast messages are sent to an associated mailbox if one exists.

**/BROADCAST (default)**  
**/NOBROADCAST**

Controls whether reception of broadcast messages (such as those issued by **MAIL** and **REPLY**) is enabled. Specify the **/NOBROADCAST** qualifier when you are using a terminal as a noninteractive device or when you do not want special output to be interrupted by messages. Use the **SET BROADCAST** command to exclude certain types of messages from being broadcast, rather than eliminating all messages.

**/COLOR**

Sets the **ANSI\_COLOR** terminal characteristic and identifies the terminal as capable of supporting the ANSI color escape sequences.

**/COMMSYNC**  
**/NOCOMMSYNC (default)**

Allows connection of asynchronous printers and other devices to terminal ports, using standard modem control signals as flow control. Transmission to the device stops if either data set ready (DSR) or clear to send (CTS) EIA modem control signals are dropped. Transmission resumes when both signals are present.

The **/COMMSYNC** qualifier and the **/MODEM** qualifier are mutually exclusive.

The **COMMSYNC** feature has the following limitations:

- Cannot be used on **LAT** ports
- Can only be used on ports with full modem control
- Should not be used in conjunction with **Xon/Xoff** flow control (the port may hang)

## Caution

The **/COMMSYNC** qualifier should never be set on a line with a modem that is intended for interactive use. The qualifier disables the modem terminal characteristic that disconnects a user process from the terminal line in case of a modem phone line failure. With the **/COMMSYNC** qualifier enabled, the next call on the terminal line could be attached to the previous user's process. Security administrators should be aware that the characteristic should not be used on interactive terminal ports. In addition, the **/COMMSYNC** qualifier is not supported on a port connected to a LAT line.

### **/CRFILL[=*fill-count*]**

Generates the specified number of null characters after each carriage return before transmitting the next meaningful character (to ensure that the terminal is ready for reception). The value must be an integer in the range 0 to 9. The default is the **/CRFILL=0** qualifier.

### **/DEC\_CRT[= (*value1,value2,value3*)]**

### **/NODEC\_CRT[= (*value1,value2,value3*)]**

Controls whether the terminal conforms to DIGITAL VT100-, VT200-, VT300-, VT400-, or VT500-family standards and supports the minimum standards, including the additional DIGITAL escape sequences.

You can specify one of the following values:

| Value       | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|-------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1 (default) | Requests that the DEC_CRT terminal characteristic be set.                                                                                                                                                                                                                                                                                                                                                                                                         |
| 2           | Requests that the DEC_CRT2 terminal characteristic be set.                                                                                                                                                                                                                                                                                                                                                                                                        |
| 3           | Requests that the DEC_CRT3 terminal characteristic be set. A level 3 terminal supports the following additional features: <ul style="list-style-type: none"> <li>• A status line (line 25, at the bottom of the screen)</li> <li>• The ISO Latin1 character set</li> <li>• Terminal state interrogation (describes what state your terminal is in)</li> </ul>                                                                                                     |
| 4           | Requests that the DEC_CRT4 terminal characteristic be set. A level 4 terminal supports the following additional features: <ul style="list-style-type: none"> <li>• Extended keyboard</li> <li>• Key position mode</li> <li>• Secure reset</li> <li>• Novice mode</li> <li>• Selective erase</li> <li>• On-line transaction processing (OLTP) features: <ul style="list-style-type: none"> <li>• Page memory</li> <li>• Rectangular editing</li> </ul> </li> </ul> |

| Value | Description                                                                                   |
|-------|-----------------------------------------------------------------------------------------------|
|       | <ul style="list-style-type: none"> <li>Text macros</li> <li>Data integrity reports</li> </ul> |

Note that DEC\_CRT2, DEC\_CRT3, and DEC\_CRT4 are supersets of DEC\_CRT. Clearing DEC\_CRT causes DEC\_CRT2, DEC\_CRT3, and DEC\_CRT4 to be cleared. Similarly, setting DEC\_CRT4 causes all subsets of DEC\_CRT4 (including ANSI\_CRT) to be set.

### **/DEVICE\_TYPE=terminal-type**

Informs the system of the terminal type and sets characteristics according to the device type specified. You can specify any of the following terminal types:

|          |       |            |       |       |
|----------|-------|------------|-------|-------|
| UNKNOWN  | LA100 | PRO_SERIES | VT102 | VT200 |
| FT1--FT8 | LA120 | VT05       | VT105 | VT300 |
| LA12     | LA210 | VT52       | VT125 | VT400 |
| LA34     | LN01K | VT55       | VT131 | VT500 |
| LA36     | LN03  | VT100      | VT132 |       |
| LA38     | LQP02 | VT101      | VT173 |       |

The default characteristics for the VT100-, VT102-, and VT125-series terminals are as follows:

|                       |                                 |                     |
|-----------------------|---------------------------------|---------------------|
| <b>/ADVANCEDVIDEO</b> | <b>/NOALTYPEAHD<sup>1</sup></b> | <b>/ANSI_CRT</b>    |
| <b>/NOAUTOBAUD</b>    | <b>/NOBLOCK_MODE</b>            | <b>/NOBRDCSTMBX</b> |
| <b>/BROADCAST</b>     | <b>/CRFILL=0</b>                | <b>/ECHO</b>        |
| <b>/NOEIGHT_BIT</b>   | <b>/NOESCAPE</b>                | <b>/NOFORM</b>      |
| <b>/FULLDUP</b>       | <b>/NOHOSTSYNC</b>              | <b>/LFFILL=0</b>    |
| <b>/LOWERCASE</b>     | <b>/NODMA</b>                   | <b>/PAGE=24</b>     |
| <b>/NOPARITY</b>      | <b>/NOPASTHRU</b>               | <b>/NOREADSYN</b>   |
| <b>/SPEED=9600</b>    | <b>/TAB</b>                     | <b>/TTSYNC</b>      |
| <b>/TYPE_AHEAD</b>    | <b>/WIDTH=80</b>                | <b>/WRAP</b>        |

<sup>1</sup>This is the default characteristic set by the system and is not a valid qualifier for your use.

The terminal types and characteristics that can be set are listed in *Figure 2, "Default Characteristics for Terminals"*.

### **/DIALUP**

#### **/NODIALUP (default)**

Controls whether the terminal is a dialup terminal.

### **/DISCONNECT**

#### **/NODISCONNECT (default)**

Controls whether the process connected to this terminal is disconnected if the line detects a hangup. The **/DISCONNECT** qualifier is valid only when the **/PERMANENT** qualifier is specified.

### **/DISMISS**

#### **/NODISMISS (default)**

Controls whether the terminal driver ignores data that causes a parity error (instead of terminating the currently outstanding I/O with an error status).

**/DMA**  
**/NODMA**

Controls whether direct memory access (DMA) mode is used on a controller that supports this feature.

**/ECHO (default)**  
**/NOECHO**

Controls whether the terminal displays the input it receives. With the **/NOECHO** qualifier, the terminal displays only system or user application output, or both.

**/EDIT\_MODE**  
**/NOEDIT\_MODE**

Controls whether the terminal can perform ANSI-defined advanced editing functions.

**/EIGHT\_BIT**  
**/NOEIGHT\_BIT**

Controls whether the terminal uses the 8-bit ASCII protocol rather than the 7-bit ASCII protocol. You can use the Terminal Fallback Facility (TFF) to set the 8-bit characteristic on terminals. If the terminal you specify has the TFF enabled, the **/EIGHT\_BIT** qualifier has no effect. For more information on terminal fallback, see the *OpenVMS Terminal Fallback Utility Manual*.

**/ESCAPE**  
**/NOESCAPE (default)**

Controls whether escape sequences are validated.

**/FALLBACK**  
**/NOFALLBACK**

Controls whether the 8-bit DEC Multinational character set characters are displayed on the terminal in their 7-bit representation. The default depends on the **/EIGHTBIT** setting of the terminal. If the OpenVMS Terminal Fallback Facility (TFF) is enabled, it activates the default character conversion tables for the named terminal. For more information, see the *OpenVMS Terminal Fallback Utility Manual*. If TFF is not enabled on your system, the **/FALLBACK** qualifier has no effect and no error message is displayed.

**/FORM**  
**/NOFORM**

Controls whether a form feed is transmitted rather than translated into multiple line feeds.

**/FRAME=*n***

Specifies the number of data bits that the terminal driver expects for every character that is input or output. The value of *n* can be from 5 to 8. The default value depends on the settings for the terminal established by the **/PARITY** and **/EIGHTBIT** qualifiers.

**/FULLDUP (default)**  
**/NOFULLDUP**

Controls whether the terminal operates in full-duplex mode. The **/FULLDUP** qualifier is equivalent to the **/NOHALFDUP** qualifier.

**/HALFDUP****/NOHALFDUP (default)**

Controls whether the terminal operates in half-duplex mode. The **/HALFDUP** qualifier is equivalent to the **/NOFULLDUP** qualifier.

**/HANGUP****/NOHANGUP (default)**

May require LOG\_IO (logical I/O) or PHY\_IO (physical I/O) privilege depending on system generation parameter settings.

Controls whether the terminal modem is hung up when you log out.

**/HARDCOPY****/NOHARDCOPY**

Controls whether the device is established as a hardcopy terminal and outputs a backslash (\) when the Delete key is pressed. The **/HARDCOPY** qualifier is equivalent to the **/NOSCOPE** qualifier.

**/HOSTSYNC****/NOHOSTSYNC (default)**

Controls whether system transmission from the terminal is stopped (by generating a **Ctrl/S**) when the input buffer is full and resumed (by generating a **Ctrl/Q**) when the input buffer is empty.

**/INQUIRE**

Sets the device type when the **/INQUIRE** qualifier is specified and the DEC\_CRT characteristic is set. The **SET TERMINAL** command reads the current screen size from the terminal and sets the corresponding page length and page width values appropriately. The default device type is UNKNOWN. Works only on DIGITAL terminals, and not on LA36 or VT05 terminals. Some VT100 family terminals, including the VT101 and VT105, return a VT100 type response. LA38 terminals respond as LA43 terminals.

---

**Note**

The **SET TERMINAL/INQUIRE** command works correctly on DIGITAL supplied VT100 and later terminals. Some personal computer terminal emulators may not work correctly, because they do not correctly emulate all VT100 escape sequences. VSI recommends that users who experience problems with these terminal emulators contact the terminal emulator supplier.

---

You can include the **SET TERMINAL/INQUIRE** command in your LOGIN.COM file to detect the terminal type automatically.

If you specify **/INQUIRE=OLD**, OpenVMS sets the terminal window to 24 lines by 80 columns and ignores the real terminal size. (This is the behavior of the **SET TERMINAL/INQUIRE** command prior to OpenVMS Version 6.2.)

---

**Caution**

This qualifier clears the type-ahead buffer. If the response sequence is unrecognized, no action message or error message is displayed. The **/INQUIRE** qualifier should be used only on DIGITAL terminals; however, the LA36 and VT05 terminals do not support this feature.

---

**/INSERT**

Sets the terminal to insert mode. This feature allows you to insert characters when editing command lines. The default mode is overstrike, which allows you to type over the current character when editing a command line. Press **Ctrl/A** to switch from one mode to the other.

**/LFFILL[=*fill-count*]**

Transmits to the terminal the specified number of null characters after each line feed before transmitting the next meaningful character (to ensure that the terminal is ready for reception). The value must be an integer in the range 0 to 9. The default is installation dependent. See *Figure 2, "Default Characteristics for Terminals"* for a list of default terminal characteristics.

**/LINE\_EDITING****/NOLINE\_EDITING**

Controls whether advanced line-editing features are enabled for editing command lines: pressing **Return** and pressing **Ctrl/Z** are recognized as line terminators, as are escape sequences.

**/LOCAL\_ECHO****/NOLOCAL\_ECHO (default)**

Controls whether the terminal echoes characters locally (rather than the host echoing them) for command level terminal functions. (Do not use the **/LOCAL\_ECHO** qualifier with utilities that require control over echoing, such as line editing or EDT's screen mode.)

---

**Caution**

When logging in to terminals with the **LOCAL\_ECHO** characteristic, the OpenVMS system has no control over the echoing of passwords.

---

**/LOWERCASE****/NOLOWERCASE**

Controls whether lowercase characters are passed to the terminal. The **/NOLOWERCASE** qualifier translates all input to uppercase. The **/LOWERCASE** qualifier is equivalent to the **/NOUPPERCASE** qualifier.

**/MANUAL**

Indicates manual switching of terminal lines to dynamic asynchronous DDCMP lines when your local terminal emulator does not support automatic switching. The **/MANUAL** qualifier should be specified with the **/PROTOCOL=DDCMP** and **/SWITCH=DECNET** qualifiers.

**/MODEM****/NOMODEM**

Specifies whether the terminal is connected to a modem or a cable that supplies standard EIA modem control signals. If your terminal has the **MODEM** characteristic, entering **SET TERMINAL/NOMODEM** automatically logs you out. The **/MODEM** qualifier and the **/COMMSYNC** qualifier are mutually exclusive.

**/NUMERIC\_KEYPAD (default)**

Specifies whether the keys of the numeric keypad are used to type numbers and punctuation marks (**/NUMERIC\_KEYPAD**) or to enter DCL commands defined with the **DEFINE/KEY** command (**/APPLICATION\_KEYPAD**).

**/OVERSTRIKE (default)**

Sets the terminal to overstrike mode. This feature allows you to type over the current character when you are editing a command line. Set your terminal to insert mode if you want to insert characters when editing command lines. Press **Ctrl/A** to switch from one mode to the other.

**/PAGE[=*lines-per-page*]**

Specifies the number of print lines between perforations for hardcopy terminals. (When the terminal reads a form feed, it advances the paper to the next perforation.) The value of the *lines-per-page* parameter can be from 0 to 255 and defaults to 0 (which treats a form feed as a line feed).

**/PARITY[=*option*]****/NOPARITY (default)**

Controls whether the terminal passes data with only odd or even parity, where *option* equals ODD or EVEN. If you specify the **/PARITY** qualifier without an option, the value defaults to EVEN.

**/PASTHRU****/NOPASTHRU (default)**

Controls whether the terminal passes all data (including tabs, carriage returns, line feeds, and control characters) to an application program as binary data. The setting of **/TTSYNC** is allowed.

Make sure that you spell both these qualifiers exactly as they appear in the text.

**/PERMANENT**

Requires LOG\_IO (logical I/O) or PHY\_IO (physical I/O) privilege.

Sets characteristics on a permanent basis, that is, over terminal sessions; however, the characteristics revert to their initial values if the system is halted and restarted. Use in a system startup file to establish characteristics for all terminals on the system.

**/PRINTER\_PORT****/NOPRINTER\_PORT**

Specifies whether the terminal has a printer port (an attribute not set by the **SET TERMINAL/INQUIRE** command). The default is installation dependent. See *Figure 2, "Default Characteristics for Terminals"* for a list of default terminal characteristics.

**/PROTOCOL=DDCMP****/PROTOCOL=NONE (default)**

On VAX, controls whether the terminal port specified is changed into an asynchronous DDCMP line. The **/PROTOCOL=NONE** qualifier changes an asynchronous DDCMP line back into a terminal line. Note that **/PROTOCOL=DDCMP** is a permanent characteristic; therefore, the **/PERMANENT** qualifier is not required.

**/READSYNC****/NOREADSYNC (default)**

Controls whether the terminal uses the **Ctrl/S** and **Ctrl/Q** functions to synchronize data transmitted from the terminal.

## Caution

**SET TERMINAL/READSYNC** should not be used on LAT terminal lines. Setting this characteristic may cause unexpected results.

---

The default is the **/NOREADSYNC** qualifier; the system does not use the **Ctrl/S** and **Ctrl/Q** functions to control reads to the terminal. The **/READSYNC** qualifier is useful for certain classes of terminals that demand synchronization or for special-purpose terminal lines where data synchronization is appropriate.

### **/REGIS** **/NOREGIS**

Specifies whether the terminal understands ReGIS graphic commands.

### **/SCOPE** **/NOSCOPE**

Controls whether the device is established as a video terminal. The **/SCOPE** qualifier is equivalent to the **/NOHARDCOPY** qualifier.

### **/SECURE\_SERVER** **/NOSECURE\_SERVER (default)**

Requires either LOG\_IO (logical I/O) or PHY\_IO (physical I/O) privilege.

Controls whether the Break key on the terminal logs out the current process (except on a virtual terminal). With the **/SECURE\_SERVER** qualifier in effect, pressing the Break key when there is no current process initiates the login sequence. With the **/NOSECURE\_SERVER** qualifier in effect, the break is ignored.

On terminals with the AUTOBAUD and SECURE\_SERVER characteristics, pressing the Break key disconnects the current process, but is not required to start a new login sequence. However, when the NOAUTOBAUD characteristic is set, the SECURE\_SERVER characteristic requires a break to initiate a new login sequence.

### **/SET\_SPEED** **/NOSET\_SPEED**

Requires either LOG\_IO (logical I/O) or PHY\_IO (physical I/O) privilege.

Controls whether the /SPEED qualifier can be used to change the terminal speed.

### **/SIXEL\_GRAPHICS** **/NOSIXEL\_GRAPHICS**

Specifies whether the terminal is capable of displaying graphics using the sixel graphics protocol. The default is device dependent. For a list of default terminal characteristics, see *Figure 2, "Default Characteristics for Terminals"*.

### **/SOFT\_CHARACTERS** **/NOSOFT\_CHARACTERS**

Specifies whether the terminal is capable of loading a user-defined character set. The default is device dependent. See *Figure 2, "Default Characteristics for Terminals"* for a list of default terminal characteristics.

**/SPEED=(input-rate,output-rate)**

Sets the baud rate at which the terminal receives and transmits data. If the input and output rates are the same, specify **/SPEED=rate**.

Not all terminals support different input and output baud rates. For specific information on baud rates for your terminal, consult the manual for that terminal.

The default transmission rates are installation dependent.

The valid values for input and output baud rates are as follows:

|     |      |      |       |        |
|-----|------|------|-------|--------|
| 50  | 150  | 1800 | 4800  | 38400  |
| 75  | 300  | 2000 | 7200  | 57600  |
| 110 | 600  | 2400 | 9600  | 76800  |
| 134 | 1200 | 3600 | 19200 | 115200 |

**/SWITCH=DECNET**

On VAX, causes the terminal lines at each node to be switched to dynamic asynchronous DDCMP lines, when specified with the **/PROTOCOL=DDCMP** qualifier. Note that **/SWITCH=DECNET** is a permanent characteristic; therefore, the **/PERMANENT** qualifier is not required.

**/SYSPASSWORD****/NOSYSPASSWORD (default)**

Requires LOG\_IO (logical I/O) privilege.

Determines whether the terminal requires that a system password be entered before the Username: prompt.

**/TAB****/NOTAB**

Controls whether tab characters are converted to multiple blanks. The **/NOTAB** qualifier expands all tab characters to blanks and assumes tab stops at 8-character intervals. The default is device dependent. For a list of default terminal characteristics, see *Figure 2, "Default Characteristics for Terminals"*.

**/TTSYNC (default)****/NOTTSYNC**

Controls whether transmitting to the terminal is stopped when **Ctrl/S** is pressed and resumes transmission when **Ctrl/Q** is pressed.

**/TYPE\_AHEAD (default)****/NOTYPE\_AHEAD**

Controls whether the terminal accepts unsolicited input to the limit of the type-ahead buffer.

When you specify the **/NOTYPE\_AHEAD** qualifier, the terminal accepts input only when a program or the system issues a read to the terminal, such as for user input at the DCL prompt (\$). When you specify the **/TYPE\_AHEAD** qualifier, the amount of data that can be accepted is governed by the size of the type-ahead buffer. That size is determined by system generation parameters.

**/UNKNOWN**

Specifies a terminal type that is unknown to the system, which then uses the default terminal characteristics for unknown terminals. For a summary of the settings, see *Figure 2, "Default Characteristics for Terminals"*.

**/UPPERCASE****/NOUPPERCASE**

Controls whether lowercase characters are translated to uppercase. The **/UPPERCASE** qualifier is equivalent to the **/NOLOWERCASE** qualifier.

**/WIDTH=characters-per-line**

Specifies the maximum characters per line. This value must be an integer in the range 1 to 511. With the **/WRAP** qualifier, the terminal generates a carriage return and line feed when the width specification is reached.

If the specified width on an ANSI terminal is 132, the screen is set to 132-character mode. If the terminal does not have advanced video option (AVO), the page length limit is set to 14 lines.

**/WRAP (default)****/NOWRAP**

Controls whether a carriage return and line feed are generated when the value of the **/WIDTH** qualifier is reached.

## Examples

1. `$ SET TERMINAL/DEVICE=VT102`

In this example, the **SET TERMINAL** command establishes the current terminal as a VT102 terminal and sets the default characteristics for that terminal type.

2. 

```
$ SET TERMINAL/WIDTH=132/PAGE=60/NOBROADCAST
$ TYPE MEMO.DOC
.
.
.
$ SET TERMINAL/DEVICE=LA36
```

In this example, the first **SET TERMINAL** command indicates that the width of terminal lines is 132 characters and that the size of each page is 60 lines. The **/NOBROADCAST** qualifier disables the reception of broadcast messages while the terminal is printing the file MEMO.DOC. The next **SET TERMINAL** command restores the terminal to its default state.

## SET TIME

**SET TIME** — Resets the system clock, which is used as a timer to record intervals between various internal events and as a source clock for displaying the time of day. **Requires both OPER (operator) and LOG\_IO (logical I/O) privileges.**

## Format

**SET TIME**[=*time*]

## Parameter

### *time*

Specifies a date in the format *day-month-year*, or a time in the format *hour:minute:second.hundredth*, or both. These fields accept the following values:

| Field            | Type    | Values                                                        |
|------------------|---------|---------------------------------------------------------------|
| <i>Day</i>       | Integer | 1 to 31                                                       |
| <i>Month</i>     | String  | JAN, FEB, MAR, APR, MAY, JUN, JUL, AUG, SEP, OCT, NOV, or DEC |
| <i>Year</i>      | Integer | 1858 to 9999                                                  |
| <i>Hour</i>      | Integer | 0 to 23                                                       |
| <i>Minute</i>    | Integer | 0 to 59                                                       |
| <i>Second</i>    | Integer | 0 to 59                                                       |
| <i>Hundredth</i> | Integer | 0 to 99                                                       |

The hyphens (-), colons (:), and period (.) are required delimiters. Separate the date and time, when both are specified, with a colon. The syntax is sometimes specified as follows:

```
[dd-mmm-yyyy[:]] [hh:mm:ss.cc]
```

Alpha systems also allow a 2-digit year format:

```
[dd-mmm-yy[:]] [hh:mm:ss.cc]
```

The century applied to the 2-digit year format is determined by the corresponding year in the supported Alpha date range (1957-2056). A 2-digit year in the range 57-99 is assumed to mean the years 1957-1999; a 2-digit year in the range 00-56 is assumed to mean the years 2000-2056. (To specify years outside the 1957-2056 range, you must enter a 4-digit year.)

If the explicit time value is not specified, the interval system clock is automatically reset according to the time-of-year clock.

For further information about the time-of-year clock, see the hardware documentation for your computer.

---

### Note

Alpha systems maintain system time during power failures and system down time. When a system is booted, if the time is known to be earlier than the time value of the last time modification, or greater than five years in the future, you are prompted to enter the time at the console prompt.

---

## Description

Resets the system clock, which is used as a timer to record intervals between various internal events and as a source clock for displaying the time of day.

---

### Note

The **SET TIME** command will not work if there is a time service available on your system or OpenVMS Cluster.

---

## Qualifier

### /CLUSTER

Requires OPER and LOG\_IO privilege, and in an OpenVMS Cluster environment, SYSLOCK privilege.

Sets the time on all nodes in a cluster to the same system time. The format of the **SET TIME /CLUSTER** command is the following:

```
SET TIME[=time] [/CLUSTER]
```

## Examples

1. \$ SET TIME=14-DEC-2001:19:31:0.0

The **SET TIME** command in this example sets the date and time to December 14, 2001, 7:31 P.M.

2. \$ SET TIME  
\$ SHOW TIME  
14-DEC-2001 03:21:27.53

The **SET TIME** command in this example sets the system time according to the time-of-year clock. The **SHOW TIME** command requests a display of the current time.

3. \$ SET TIME=14-DEC-2001:15:31:0.0/CLUSTER

This example sets the date and time to December 14, 2001, 3:31 P.M. on all nodes in the cluster where the command was entered.

## SET VERIFY

**SET VERIFY** — Controls whether command lines and data lines in command procedures are displayed at the terminal or are printed in a batch job log. The information displayed by the **SET VERIFY** command can help you in debugging command procedures.

## Format

```
SET VERIFY [([NO]PROCEDURE, [NO]IMAGE)]
```

```
SET NOVERIFY
```

## Parameter

```
([NO]PROCEDURE, [NO]IMAGE)
```

Specifies one or both types of verification. Procedure verification causes each DCL command line in a command procedure to be written to the output device. Image verification causes data lines (input data that is included as part of the SYSS\$INPUT input stream) to be written to the output device.

By default, both types of verification are set or cleared with **SET VERIFY** and **SET NOVERIFY**. If you specify only one keyword, the other is not affected. If you specify only one keyword, omit the parentheses.

## Description

By default, the **SET VERIFY** and **SET NOVERIFY** commands set or clear both types of verification. The default setting for command procedures executed interactively is **SET NOVERIFY**. System responses and error messages are, however, always displayed. The default for batch jobs is **SET VERIFY**.

If you use the **SET VERIFY** command to override the default setting, the system displays each command and data line in the command procedure as it reads it. When verification is in effect, the command interpreter displays each command line after it has completed initial scanning and before the command is parsed and executed. You see the results of symbol substitution performed during scanning, but not the results of symbol substitution performed during parsing and evaluation.

When you change the verification setting, the new setting remains in effect for all command procedures that you subsequently execute.

A file must have read (R) access to allow the **SET VERIFY** command to set verification.

## Examples

1. `$ SET VERIFY = PROCEDURE`

In this example, procedure verification is turned on. If image verification was on, it remains on; if image verification was off, it remains off.

2. 

```
$ SET VERIFY
$ INDEX == "$INDEX.EXE"
$ CONTENTS == "$CONTENTS.EXE"
$ TABLE == "$TABLE.EXE"
$ SET NOVERIFY
$ EXIT
```

Procedure and image verification are turned on at the beginning of the command procedure so that the system displays all the command and data lines in the procedure as it reads them. At the end of the procedure, the **SET NOVERIFY** command restores the system default (no procedure or image verification).

3. 

```
$ PROC_VER = F$ENVIRONMENT("VERIFY_PROCEDURE")
$ IMAGE_VER = F$ENVIRONMENT("VERIFY_IMAGE")
$ HOLD_PREFIX = F$ENVIRONMENT("VERIFY_PREFIX")
$ SET PREFIX "(!%T)"
$ SET VERIFY
.
.
.
$ TEMP = F$VERIFY(PROC_VER, IMAGE_VER)
$ SET PREFIX "'HOLD_PREFIX'"
```

This command procedure uses the `F$ENVIRONMENT` lexical function to save the current procedure and image verification setting, as well as the current verification prefix string. The **SET PREFIX** command sets the verification prefix to be used in the current command procedure. It uses an FAO control string to produce the time each command is read by the command interpreter (DCL), surrounded by parentheses. Then the **SET VERIFY** command turns on both procedure and image verification. Subsequently, the `F$VERIFY` lexical function is used to restore the original verification settings. The **SET PREFIX** command returns the verification prefix to its previous setting. Note

how the symbol `HOLD_PREFIX` is used in the **SET PREFIX** command. This preserves casing and special characters in the stored string.

```
4. $ SET VERIFY
   $ @TEST
   $ RUN AVERAGE
   1
   2
   3
   $ EXIT
```

In this example, the **SET VERIFY** command turns procedure and image verification on. When the command procedure `TEST.COM` is executed interactively, the command lines and the data lines for the program `AVERAGE` are displayed on the terminal. The data lines were entered in the command procedure on lines that did not begin with the DCL prompt.

```
5. $ SET VERIFY
   $ COUNT = 1
   $ IF P'COUNT' .NES. "" THEN GOTO &P'COUNT'
       .
       .
       .
   $ EXIT
```

When this command procedure is executed interactively, the **SET VERIFY** command causes the command and data lines to be displayed. Symbols that are substituted during the first phase of symbol substitution (such as `'COUNT'`) are displayed by the **SET VERIFY** command, but other symbols are not. The following lines are displayed when this procedure is executed interactively:

```
$ COUNT = 1
$ IF P1 .NES. "" THEN GOTO &P1
  .
  .
  .
```

Although these values are not displayed, the value for `P1` is substituted during the third phase of symbol substitution, and the value for `&P1` is substituted during the second phase.

## SET VOLUME

**SET VOLUME** — Changes the characteristics of one or more mounted Files-11 volumes. The **SET VOLUME** command affects only the node on which the command is issued, and will not affect any other nodes, even when a volume is mounted on multiple nodes in an OpenVMS Cluster configuration. **If you are not the owner of the volume, requires control access to the volume.**

### Format

```
SET VOLUME device-name[:][,...]
```

### Parameter

```
device-name[:][,...]
```

Specifies the name of one or more mounted Files-11 volumes.

## Qualifiers

### **/ACCESSED[=*n*]**

Requires OPER (operator) privilege.

Specifies the number of directories to be maintained in system space for ready access. You can specify a value *n* in the range of 0 to 255. If you specify the qualifier **/ACCESSED** and omit the number of directories, a default value of 3 is used. If you specify a value greater than the current value, the new value is effective immediately; otherwise, the new value is not effective until the next time the volume is mounted.

### **/CACHE=(*option*[,...])**

Enables or disables XFC caching for the volume. If CLEAR\_DATA option is specified, then contents of the volume already in cache are cleared. (If you do not specify the **/CACHE** qualifier, XFC caching attributes of the volume as well as the contents of the volume already in cache are not affected.) Keywords are as follows:

| Keyword    | Description                                                      |
|------------|------------------------------------------------------------------|
| DATA       | Enables XFC caching for the volume.                              |
| [NO]DATA   | Disables XFC caching for the volume.                             |
| CLEAR_DATA | Clears contents of the volume present in the XFC cache (if any). |

### **/DATA\_CHECK[=(*option*[,...])]**

Defines a default for data check operations following all read and write operations to the specified volume. (If you do not specify the **/DATA\_CHECK** qualifier, no checks are made.) Keywords are as follows:

| Keyword   | Description                                               |
|-----------|-----------------------------------------------------------|
| [NO]READ  | Performs checks following all read operations.            |
| [NO]WRITE | Performs checks following all write operations (default). |

### **/ERASE\_ON\_DELETE**

### **/NOERASE\_ON\_DELETE (default)**

Determines whether the space occupied by a file is overwritten with a system-specified pattern when a file on the volume is deleted.

### **/EXTENSION[=*n*]**

Specifies the number of blocks to be used as a default extension size for all files on the volume. You can specify a value *n* in the range of 0 to 65,535. If you specify the **/EXTENSION** qualifier without specifying a value, a default value of 0 (the OpenVMS RMS default) is used.

For example, during an update operation, the extension default is used when a file increases to a size greater than its initial default allocation.

### **/FILE\_PROTECTION= (*ownership*[:*access*][,...])**

Sets the default protection to be applied to all files on the specified disk volume. Specify the *ownership* parameter as system (S), owner (O), group (G), or world (W) and the *access* parameter as read (R), write (W), execute (E), or delete (D). A null access specification means no access.

---

## Note

This attribute is not used while the volume is in use on an OpenVMS system, but the attribute is provided to control the process use of the volume on RSX-11M systems. The OpenVMS system always uses the default file protection; the protection can be changed with the DCL command **SET PROTECTION/DEFAULT**.

---

### **/HIGHWATER\_MARKING** **/NOHIGHWATER\_MARKING**

Determines whether the file high water mark (FHM) volume attribute is set. The FHM attribute guarantees that a user cannot read data that was not written by the user. Applies to Files-11 On-Disk Structure Level 2 (ODS-2) and 5 (ODS-5) volumes only.

### **/LABEL=*volume-label***

Specifies a 1- to 12-character ANSI name to be encoded on the volume. The specified label remains in effect until it is changed explicitly; dismounting the volume does not affect the label. VSI strongly recommends that a volume label should consist of only alphanumeric characters, dollar signs (\$), underscores (\_), and hyphens (-).

---

## Note

Changing the volume label does not change other structures that used the original volume label. For example, the `DISK$label` logical volume name is not changed nor is the device-lock name that is kept internally by OpenVMS. As a result, if you attempt to access another disk that has the same volume label as the original volume of this device, you may get error messages such as the following: "%MOUNT-F-VOLALRMNT, another volume of same label already mounted".

VSI recommends that, if you change a disk volume label, you also dismount and remount the disk on all nodes in the cluster so that the names and locks are consistent.

---

If you change the volume label on a nonsystem disk and the **PRODUCT INSTALL** command has been used to install software products on that disk, you must update the software product database to reflect this change. To accomplish this, first dismount and remount the disk. Then use the **PRODUCT REGISTER VOLUME** command to replace all occurrences of the old `DISK$label` with the new logical volume name that was created by the **MOUNT** command.

---

## Note

You do not need to take this action when you change the label of the system disk. The POLYCENTER Software Installation Utility continues to use the old logical volume name until the system is rebooted. After reboot (when the system disk is remounted), the utility automatically identifies the system disk using its new logical volume name.

---

### **/LIMIT[=*n*]**

Specifies that the volume is to be enabled for volume expansion. *n* specifies the upper limit of the expansion (in blocks). If no value is specified, the maximum expansion potential is set up.

The maximum expansion size depends on the cluster size defined for the volume using the **INITIALIZE/CLUSTER\_SIZE** command. If the cluster size is 8 or more, the current maximum expansion supported on OpenVMS (2TB) is set up. If the cluster size is less than 8, the expansion

---

limit is set to 65535\*4096\*Cluster-size because the maximum size of the bitmap is 65535 blocks. For more information about volume expansion, see the relevant section in the [VSI OpenVMS Volume Shadowing Guide \[https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/#dynamic\\_vol\\_extention\\_sec\]](https://docs.vmssoftware.com/vsi-openvms-volume-shadowing-guide/#dynamic_vol_extention_sec).

This command must be executed while the disk is mounted privately.

If you add additional physical storage in the future, you can use the **/SIZE** qualifier to increase the volume size.

#### **/LOG**

#### **/NOLOG (default)**

Determines whether the volume specification of each volume is displayed after the modification.

#### **/MOUNT\_VERIFICATION**

#### **/NOMOUNT\_VERIFICATION**

Determines whether mount verification is enabled. Mount verification prevents interruption to user input/output operations and notifies the operator of problems with the disk.

#### **/OWNER\_UIC[=*uic*]**

Sets the owner user identification code (UIC) of the volume to the specified UIC. The default UIC is that of the current process. Brackets ([]) are required around the UIC. Specify the UIC by using standard UIC format as described in the relevant section in the [VSI OpenVMS Guide to System Security \[https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC\\_SECTION\]](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC_SECTION).

#### **/PROTECTION=(*ownership[:access][,...]*)**

Specifies the protection to be applied to the volume. The following rules apply:

- Specify the *ownership* parameter as system (S), owner (O), group (G), or world (W).
- Specify the *access* parameter as read (R), write (W), create (C), or delete (D).

The default protection is all types of access by all categories of user.

#### **/REBUILD[=**FORCE**]**

Recovers caching limits for a volume that was dismounted improperly. If a disk volume was dismounted improperly (such as during a system failure), and was then remounted with the **MOUNT/NOREBUILD** command, you can use **SET VOLUME/REBUILD** to recover the caching that was in effect at the time of the dismount. The **FORCE** option forces the disk to be rebuilt unconditionally, thus updating the free block count in the disk volume's lock value block.

#### **/RETENTION=(*min[,max]*)**

Specifies the minimum and maximum retention times to be used by the file system to determine the expiration date for files on the volume. When a file is created, its expiration date is set to the current time plus the maximum time. Each time the file is accessed, the current time is added to the minimum time. If the sum is greater than the expiration date, a new expiration date is computed.

If you omit the maximum value, a default value that is the smaller of (2 x min) or (min + 7) days is used. For example, **/RETENTION=3-** is the same as **/RETENTION=( 3- , 6- )**, while **/RETENTION=10-** is the same as **/RETENTION=( 10- , 17- )**.

The command **SET VOLUME/RETENTION=0** disables retention times on the volume.

**/SIZE[=*nnn*]**

Specifies the amount of disk space (in blocks) that is usable for the file system. This value must be greater than the current logical volume size and less than or equal to the physical size of the disk or the expansion limit (specified by **/LIMIT**), whichever is smaller.

If the value is omitted, the usable space is increased to the physical size of the disk or the expansion limit, whichever is smaller.

**/STRUCTURE\_LEVEL=*n***

Sets the structure level of the volume. Use the value 5 to set the volume to ODS-5.

When the **/STRUCTURE\_LEVEL** qualifier is used with other qualifiers, the volume structure level is set prior to the other qualifiers being performed.

You cannot use the **SET VOLUME** command to change a volume from ODS-5 to ODS-2. To reset a volume to ODS-2, see the instructions in the *VSI OpenVMS System Manager's Manual, Volume 1: Essentials* [[https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#\\_5TO2](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#_5TO2)].

**/SUBSYSTEM**

**/NOSUBSYSTEM**

Enables the processing of subsystem ACEs. Requires the SECURITY privilege. By default, the disk from which you boot has protected subsystems enabled but other disks do not. For further details on subsystems, see the relevant section in the *VSI OpenVMS Guide to System Security* [[https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#PROTECT\\_SUBSYSTEM](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#PROTECT_SUBSYSTEM)].

**/UNLOAD (default)**

**/NOUNLOAD**

Specifies whether the volume is unloaded (spun down) when the DCL command **DISMOUNT** is entered.

**/USER\_NAME[=*user-name*]**

Specifies a user name of up to 12 alphanumeric characters to be recorded on the volume. The default name is the current process user name.

**/VOLUME\_CHARACTERISTICS= ([**[NO]HARDLINKS,**] [**[NO]ACCESS\_DATES[=*delta-time*]**])**

Enables or disables hard links and automatic updates of access dates on ODS-5 volumes.

To limit the performance impact if a file is accessed frequently, you can suppress update of the access time if the change is small. A delta time is used to determine when a new access time is significant. The default value for *delta-time* is 1 second, chosen to comply with the "seconds since EPOCH" time interface required by POSIX `st_atime`. A site can choose a larger delta time to reduce overhead if 1-second granularity is not required.

To disable access date support on a volume, use the **SET VOLUME/VOLUME\_CHARACTERISTICS=NOACCESS\_DATES** command. This command affects only the node on which the command is issued. Other nodes are not affected by the change until the next time the volume is mounted.

For additional information about ODS-5 volumes, see the [Guide to OpenVMS File Applications](https://docs.vmssoftware.com/guide-to-openvms-file-applications/) [<https://docs.vmssoftware.com/guide-to-openvms-file-applications/>] [<https://docs.vmssoftware.com/guide-to-openvms-file-applications/>].

## **/WINDOWS[=*n*]**

Specifies the number of mapping pointers to be allocated for file windows.

The value of *n* can be from 7 to 80; the default value is 7.

## **/WRITETHROUGH** **/NOWRITETHROUGH**

This qualifier only affects applications such as PATHWORKS that can request deferred writes to file headers. You use it to control whether these applications can use the deferred write feature.

Use **/NOWRITETHROUGH** to allow these applications to use the deferred write feature. When one of these applications explicitly requests a deferred write when updating a file header, control returns to the application when the I/O request has been queued; the application does not have to wait until the data is on disk.

Note that although the **SHOW DEVICES/FULL** command shows the volume status as *write-back caching enabled*, the extended file cache (XFC) will still be in write-through mode.

Use **/WRITETHROUGH** to disable the deferred write feature, so that no applications can use it. The **SHOW DEVICES/FULL** command shows the volume status as *write-through caching enabled*.

The deferred write feature is not available on Files-11 ODS-1 volumes.

## **Examples**

1. \$ SET VOLUME/DATA\_CHECK=(READ,WRITE) DKA5

The **SET VOLUME** command in this example requests that data checks be performed following all read and write operations to DKA5.

2. \$ SET VOLUME/FILE\_PROTECTION=(S:RWED,O:RWED,G:RE,W:RE) DKA5

The **SET VOLUME** command in this example sets the default protection to be applied to all files created on volume DKA5. System (S) and owner (O) are granted all types of access; group (G) and world (W) are permitted only to read and execute files on DKA5.

3. \$ SET VOLUME/LABEL=LICENSES DKA5

The **SET VOLUME** command in this example encodes the label LICENSES on the volume DKA5. Note that if characters in labels are entered in lowercase, they are changed to uppercase by the **/LABEL** qualifier.

4. \$ SET VOLUME/ACCESSED=25/USER\_NAME=MANAGER/LOG DKA0:

The **SET VOLUME** command in this example specifies that 25 directories are to be maintained in system space for ready access for the volume DKA0. The command also assigns the user name MANAGER to the volume and displays the volume specification after the volume is modified.

5. \$ SET VOLUME/REBUILD/LOG NODE\$DKA2:  
%SET-I-MODIFIED, \_NODE\$DKA2: modified

The **SET VOLUME** command in this example causes a rebuild operation to begin on the volume that is mounted on NODE\$DKA2. The **/LOG** qualifier directs the **SET VOLUME** command to display a notification message.

6. \$ DISMOUNT/CLUSTER/NOUNLOAD \$252\$DUA716:  
\$ MOUNT \$252\$DUA716: TST716  
\$ SET VOLUME/LIMIT \$252\$DUA716:  
\$ DISMOUNT/NOUNLOAD \$252\$DUA716:  
\$ MOUNT/CLUSTER \$252\$DUA716: TST716

This example shows how to increase the expansion limit of a volume mounted in a cluster.

7. \$ SET VOLUME SYS\$DISK/VOLUME\_CHARACTERISTICS=NOHARDLINKS

This command disables hard links on SYS\$DISK.

8. \$ SET VOLUME \$DKA100/CACHE=CLEAR\_DATA

This command clears the contents of the volume \$DKA100 present in the XFC cache (if any). The caching mode of the volume \$DKA100 is not altered.

9. \$ SET VOLUME \$DKA100/CACHE=DATA

This command enables XFC caching for the volume \$DKA100. The contents of the volume \$DKA100 already present in the XFC cache is not affected in anyway.

10. \$ SET VOLUME \$DKA100/CACHE= (DATA, CLEAR\_DATA)

This command enables XFC caching for the volume \$DKA100 and clears the contents of the volume \$DKA100 present in the XFC cache (if any).

## SET WORKING\_SET

**SET WORKING\_SET** — Redefines the default working set size for the process, or sets an upper limit to which the working set size can be changed by an image that the process executes. Working set limits cannot be set to exceed those defined in the user authorization file (UAF). Specify the value of *n* as a number of 512-byte pagelets on Alpha. Note that the OpenVMS system rounds up this value to the nearest CPU-specific page so that the actual amount of physical memory allowed may be larger than the specified amount on Alpha.

### Format

**SET WORKING\_SET**

### Parameters

None.

### Description

The **SET WORKING\_SET** command enables the user to change the working set size within the authorized limits. A process's working set is the collection of physical pages to which an executing image can refer. Each user is assigned a default working set size to be associated with the process created

during login. The maximum size to which any process can increase its working set is defined in the user authorization file (UAF).

## Qualifiers

**/ADJUST (default)**

**/NOADJUST**

Controls whether the system can automatically adjust the size of the process working set.

**/EXTENT=*n***

Specifies the maximum number of physical pages that can be resident in the working set during image execution.

The extent value must be greater than the minimum working set defined at system generation, and it must be less than or equal to the authorized extent defined in the UAF.

If you specify a value greater than the authorized extent, the command sets the working set limit at the maximum authorized value.

**/LIMIT=*n***

Specifies the size to which the working set is to be reduced at image exit.

If you specify a value greater than the current quota, the quota value is also increased.

**/LOG**

**/NOLOG (default)**

Determines whether confirmation of the **SET WORKING\_SET** command is displayed.

**/QUOTA=*n***

Specifies the maximum number of physical pages that any image executing in the process context can request. An image can set the working set size for the process by calling the \$ADJWSL (Adjust Working Set Limit) system service.

If you specify a quota value that is greater than the authorized quota, the working set quota is set to the authorized quota value.

## Examples

```
1. $ SHOW WORKING_SET
   Working Set      /Limit=  150  /Quota=  700           /Extent=  700
   Adjustment enabled   Authorized Quota=  700  Authorized Extent=  700
$ SET WORKING_SET/QUOTA=1000
%SET-I-NEWLIMS, new working set: Limit = 150 Quota = 700 Extent = 700
```

The **SHOW WORKING\_SET** command in this example displays the current limit, quota, and extent, as well as the authorized quota and authorized extent. The **SET WORKING\_SET** command attempts to set a quota limiting the maximum number of pages any image can request that is greater than the authorized quota. Note from the response that the quota was not increased.

```
2. $ SHOW WORKING_SET
   Working Set      /Limit=  150  /Quota=  350           /Extent=  350
   Adjustment enabled   Authorized Quota=  350  Authorized Extent=  350
$ SET WORKING_SET/LIMIT=100
```

```
%SET-I-NEWLIMS, new working set: Limit = 100 Quota = 350 Extent = 350
$
SHOW WORKING_SET
Working Set      /Limit= 100 /Quota= 350           /Extent= 350
Adjustment enabled   Authorized Quota= 350   Authorized Extent= 350
```

The **SET WORKING\_SET** command in this example sets the working set size for any image in the process to 100.

## SHOW

**SHOW** — Displays information about the current status of a process, the system, or devices in the system.

### Format

**SHOW** *option*

### Description

The **SHOW** command options are described individually in this manual. *Table 8, "SHOW Command Options"* lists all the **SHOW** command options.

**Table 8. SHOW Command Options**

| Option                                  | Displays                                                                                                                            |
|-----------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------|
| ACCOUNTING                              | Resources the current accounting file is tracking                                                                                   |
| AUDIT                                   | Security auditing characteristics in effect on the system                                                                           |
| BROADCAST                               | Message classes for which broadcast is enabled                                                                                      |
| CLUSTER                                 | OpenVMS Cluster activity and performance                                                                                            |
| CPU                                     | Current state of the attached processor                                                                                             |
| DEFAULT                                 | Current default device and directory                                                                                                |
| DEVICES                                 | Status of devices in the system                                                                                                     |
| DEVICES/SERVED                          | Status of devices served by the MSCP server on an OpenVMS Cluster system                                                            |
| DISPLAY                                 | Node where the output from a DECwindows application running on the current node will be displayed                                   |
| ENTRY                                   | Information about a user's batch and print jobs or about specific job entries                                                       |
| ERROR                                   | Error count for the CPU, memory, and physical devices                                                                               |
| FASTPATH (Alpha/Integrity servers only) | Displays fast path port assignment and usage                                                                                        |
| IMAGE (Alpha/Integrity servers only)    | Displays information about an ELF format image file                                                                                 |
| INTRUSION                               | Contents of the intrusion database                                                                                                  |
| KEY                                     | Key definitions created by the <b>DEFINE/KEY</b> command                                                                            |
| LICENSE                                 | Software product licenses active on the current node as well as list of the names attached to a license (known as the RESERVE list) |

| Option                                         | Displays                                                                                                                     |
|------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------|
| LOGICAL                                        | Current logical name assignments                                                                                             |
| MEMORY                                         | Availability and usage of memory resources                                                                                   |
| NETWORK                                        | Information about network services registered on a node                                                                      |
| PRINTER                                        | Printer characteristics                                                                                                      |
| PROCESS                                        | Attributes of the current process, including privileges, resource quotas, memory usage, priority, and accounting information |
| PROTECTION                                     | Current default protection applied to files                                                                                  |
| QUEUE                                          | Names and types of queues that are available on the system as well as any current jobs belonging to your process             |
| QUEUE/CHARACTERISTICS                          | Characteristic names and numbers that have been defined for system queues                                                    |
| QUEUE/FORM                                     | Form names and numbers that have been defined for system queues                                                              |
| QUEUE/MANAGERS                                 | Information about the queue manager(s) on the system or OpenVMS Cluster                                                      |
| QUOTA                                          | Current disk quota authorized for and used by a specific user on a specific disk                                             |
| RMS_DEFAULT                                    | Current default multiblock and multibuffer counts used by OpenVMS Record Management Services (RMS) for file operations       |
| SECURITY                                       | Name, class, and profile of a security object                                                                                |
| SERVER ACME (Alpha/Integrity servers only)     | Information about the ACME server                                                                                            |
| SERVER REGISTRY (Alpha/Integrity servers only) | Information about the Registry server                                                                                        |
| SHADOW (Alpha/Integrity servers only)          | Status of a specified shadow set on the system.                                                                              |
| STATUS                                         | Status of the current job, including accumulated CPU time, open file count, and count of I/O operations                      |
| SYMBOL                                         | Current symbol definitions                                                                                                   |
| SYSTEM                                         | List of all processes in the system                                                                                          |
| TERMINAL                                       | Device characteristics of a terminal                                                                                         |
| [DAY]TIME                                      | Current date and time                                                                                                        |
| TRANSLATION                                    | Current logical name assignment                                                                                              |
| USERS                                          | Information about users currently on the system                                                                              |
| WORKING_SET                                    | CURRENT working set size limit and quota                                                                                     |
| ZONE                                           | Current state of a VAXft system                                                                                              |

## SHOW ACCOUNTING

SHOW ACCOUNTING — Shows what resources the current accounting file is tracking.

## Format

**SHOW ACCOUNTING**

## Parameters

None.

## Description

Each node on your system has its own current accounting file. You can see what resources this file is tracking using the **SHOW ACCOUNTING** command.

There are two occasions when the resources used by a process are not tracked, despite the output of the **SHOW ACCOUNTING** command:

- When you use the **RUN** (Process) command with the **/NOACCOUNTING** qualifier.
- When you use the \$CREPRC system service with the PRC\$M\_NOACNT status flag.

Similarly, there is one occasion when the resources used by an image are always tracked, despite the output of the **SHOW ACCOUNTING** command:

- When you install an image using the **/ACCOUNTING** qualifier of the Install utility.

The **SHOW ACCOUNTING** command produces a screen display (see the [Example](#)). The keywords in the display (in uppercase) fall into two categories:

- Keywords that show which types of resource are being tracked:

| Keyword       | Type of Resource                                                                                      |
|---------------|-------------------------------------------------------------------------------------------------------|
| IMAGE         | Resources used by an image                                                                            |
| LOGIN_FAILURE | Resources used by an unsuccessful attempt to log in                                                   |
| MESSAGE       | (Unformatted resource record written to the accounting file by a call to the \$SNDJBC system service) |
| PRINT         | Resources used by a print job                                                                         |
| PROCESS       | Resources used by a process                                                                           |

- Keywords that show which types of process are being tracked. When the resources for processes or images are tracked, these keywords show the process type:

| Keyword     | Type of Process                                                                           |
|-------------|-------------------------------------------------------------------------------------------|
| BATCH       | Batch process                                                                             |
| DETACHED    | Detached process                                                                          |
| INTERACTIVE | Interactive process                                                                       |
| NETWORK     | Network process                                                                           |
| SUBPROCESS  | Subprocess (the parent process can be a batch, detached, interactive, or network process) |

## Qualifier

**/OUTPUT[=*filespec*]**

Requires read (R) and write (W) access to the directory in which the specified file is created.

Controls the output destination of the command. By default, the output is the current SYS\$OUTPUT device. To send the output to a file, use the **/OUTPUT** qualifier followed by the file specification.

If the file specification does not include the file name or file type, the defaults SHOW and .LIS are used respectively.

## Example

```
$ SHOW ACCOUNTING
```

Accounting is currently enabled to log the following activities:

|               |                             |
|---------------|-----------------------------|
| PROCESS       | any process termination     |
| IMAGE         | image execution             |
| INTERACTIVE   | interactive job termination |
| LOGIN_FAILURE | login failures              |
| NETWORK       | network job termination     |
| PRINT         | all print jobs              |

The keywords in this example show that the local node is tracking the resources used by each:

- Interactive and network process
- Image running in an interactive or network process
- Login failure
- Print job

## SHOW AUDIT

**SHOW AUDIT** — Displays the security auditing characteristics in effect on the system. **Requires the SECURITY privilege.**

## Format

**SHOW AUDIT**

## Parameters

None.

## Description

The **SHOW AUDIT** command displays the current state of security auditing for the system. The display can include the state of the audit journal, the characteristics of the audit server, and the events for which auditing is enabled. If no auditing has been enabled, the display reports that security alarms and audits are currently disabled.

**SHOW AUDIT** and **SET AUDIT** provide the principal management interface to the security auditing system.

## Qualifiers

### **/ALL**

Displays all available auditing information including the following:

- Location of the system security audit log file
- Security events enabled for auditing
- Location of the security archive file
- Audit server characteristics, such as the action taken if the audit server runs out of memory.

### **/ALARM**

Displays the categories of events that are currently enabled; these events will generate messages on any operator's terminal accepting security class messages.

### **/ARCHIVE**

Displays the name and location of the security archive file (if archiving is enabled).

### **/AUDIT**

Displays the categories of events that are currently enabled to write messages to the system security audit log file.

### **/EXACT**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify a search string that must match the search string exactly and must be enclosed with quotation marks (" ").

If you specify the **/EXACT** qualifier without the **/SEARCH** qualifier, exact search mode is enabled when you set the search string with the Find (E1) key.

### **/HIGHLIGHT[=*keyword*]**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify the type of highlighting you want when a search string is found. When a string is found, the entire line is highlighted. You can use the following keywords: BOLD, BLINK, REVERSE, and UNDERLINE. BOLD is the default highlighting.

### **/JOURNAL**

Displays characteristics of the system audit journal.

### **/OUTPUT[=*filespec*]**

Controls where the output of the command is sent. If you do not enter the **/OUTPUT** qualifier or if you enter it without a file specification, the output is sent to the default output stream or device for the current process, which is identified by the logical name SYSS\$OUTPUT.

If you enter the **/OUTPUT** qualifier with a partial file specification (for example, only a directory name), **SET AUDIT** assigns the file name **SHOW** with the default file type of **.LIS**. The file specification cannot include the asterisk (\*) and the percent sign (%) wildcard characters.

**/PAGE[=keyword]**  
**/NOPAGE (default)**

Controls the display of information on the screen.

You can use the following keywords with the **/PAGE** qualifier:

| Keyword           | Description                                                                               |
|-------------------|-------------------------------------------------------------------------------------------|
| CLEAR_SCREEN      | Clears the screen before each page is displayed.                                          |
| SCROLL            | Displays information one line at a time.                                                  |
| SAVE[= <i>n</i> ] | Enables screen navigation of information, where <i>n</i> is the number of pages to store. |

The **/PAGE=SAVE** qualifier allows you to navigate through screens of information. The **/PAGE=SAVE** qualifier stores up to 5 screens of up to 255 columns of information. When you use the **/PAGE=SAVE** qualifier, you can use the following keys to navigate through the information:

| Key Sequence                                                           | Description                                                 |
|------------------------------------------------------------------------|-------------------------------------------------------------|
| Up arrow key, <b>Ctrl/B</b>                                            | Scroll up one line.                                         |
| Down arrow key                                                         | Scroll down one line.                                       |
| Left arrow key                                                         | Scroll left one column.                                     |
| Right arrow key                                                        | Scroll right one column.                                    |
| Find ( <b>E1</b> )                                                     | Specify a string to find when the information is displayed. |
| Insert Here ( <b>E2</b> )                                              | Scroll right one half screen.                               |
| Remove ( <b>E3</b> )                                                   | Scroll left one half screen.                                |
| Select ( <b>E4</b> )                                                   | Toggle 80/132 column mode.                                  |
| Prev Screen ( <b>E5</b> )                                              | Get the previous page of information.                       |
| Next Screen ( <b>E6</b> ), <b>Return</b> , <b>Enter</b> , <b>Space</b> | Get the next page of information.                           |
| <b>F10</b> , <b>Ctrl/Z</b>                                             | Exit. (Some utilities define these differently.)            |
| Help ( <b>F15</b> )                                                    | Display utility help text.                                  |
| Do ( <b>F16</b> )                                                      | Toggle the display to oldest/newest page.                   |
| <b>Ctrl/W</b>                                                          | Refresh the display.                                        |

The **/PAGE** qualifier is not compatible with the **/OUTPUT** qualifier.

**/SEARCH="string"**

Use with the **/PAGE=SAVE** qualifier to specify a string that you want to find in the information being displayed. Quotation marks are required for the **/SEARCH** qualifier, if you include spaces in the text string.

You can also dynamically change the search string by pressing the Find key (E1) while the information is being displayed. Quotation marks are not required for a dynamic search.

**/SERVER**

Displays audit server characteristics.

**/WRAP****/NOWRAP (default)**

Use with the **/PAGE=SAVE** qualifier to limit the number of columns to the width of the screen and to wrap lines that extend beyond the width of the screen to the next line.

The **/NOWRAP** qualifier extends lines beyond the width of the screen and can be seen when you use the scrolling (left and right) features provided by the **/PAGE=SAVE** qualifier.

## Example

```
$ SHOW AUDIT/ALL
List of audit journals:
Journal name:          SECURITY
Journal owner:         (system audit journal)
Destination:           SYS$COMMON:[SYSMGR]SECURITY.AUDIT$JOURNAL
Monitoring:            enabled
  Warning thresholds,  Block count:    100   Duration:    2 00:00:00.0
  Action thresholds,  Block count:     25   Duration:    0 00:30:00.0

Security auditing server characteristics:
Database version:      4.4
Backlog (total):       100, 200, 300
Backlog (process):     5, 2
Server processing intervals:
  Archive flush:        0 00:01:00:00
  Journal flush:        0 00:05:00:00
  Resource scan:        0 00:05:00:00
Final resource action:  purge oldest audit events

Security archiving information:
Archiving events:      none
Archive destination:

System security alarms currently enabled for:
ACL
Authorization
INSTALL
Time
Audit:                illformed
Breakin:              dialup,local,remote,network,detached
Login:                batch,dialup,local,remote,network,subprocess,detached
Logfailure:           batch,dialup,local,remote,network,subprocess,detached,server

System security audits currently enabled for:
ACL
Mount
Authorization
INSTALL
Time
Audit:                illformed
Breakin:              dialup,local,remote,network,detached
Login:                batch,dialup,local,remote,network,subprocess,detached,server
```

```
Logfailure: batch,dialup,local,remote,network,subprocess,detached,server
Logout:      batch,dialup,local,remote,network,subprocess,detached,server
FILE access:
  Failure:   read,write,execute,delete,control
```

The **SHOW AUDIT** command in this example displays the auditing settings after a system installation. See the [SET AUDIT/ENABLE](#) command for descriptions of the individual audit items.

## SHOW BROADCAST

**SHOW BROADCAST** — Displays the message classes that are currently affected by the **SET BROADCAST** command.

### Format

**SHOW BROADCAST**

### Parameters

None.

### Description

The **SHOW BROADCAST** command tells which classes of messages are being screened from your terminal by the **SET BROADCAST** command. If some messages are enabled by the **SET BROADCAST** command, but these messages will not be displayed because your terminal is set NO BROADCAST, an informational message is displayed.

### Qualifier

**/OUTPUT[=*filespec*]**  
**/NOOUTPUT**

Controls where the output of the command is sent. If you do not enter the qualifier, or if you enter the **/OUTPUT** qualifier without a file specification, the output is sent to the current process default output stream or device, identified by the logical name SYS\$OUTPUT.

If you enter the **/OUTPUT** qualifier with a partial file specification (for example, specifying only a directory), **SHOW** is the default file name and **.LIS** is the default file type. The asterisk (\*) and the percent sign (%) wildcard characters are not allowed.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

### Examples

1. 

```
$ SET BROADCAST=ALL
$ SET TERMINAL/NOBROADCAST
$ SHOW BROADCAST
Broadcasts are enabled for all classes
Terminal is set "No Broadcast", no broadcast messages
```

will be displayed.

The display in this example shows that all message classes are enabled for broadcast, but that these messages will not be received because the terminal is set `NO BROADCAST`.

2. 

```
$ SHOW BROADCAST
```

Broadcasts are currently disabled for:

MAIL

The **SHOW BROADCAST** display in this example indicates that **SET BROADCAST=NOMAIL** is in effect.

3. 

```
$ SET BROADCAST=(NOALL,USER1)
$ SET TERMINAL/NOBROADCAST
$ SHOW BROADCAST
```

Broadcasts are currently disabled for:

GENERAL  
PHONE  
MAIL  
QUEUE  
SHUTDOWN  
URGENT  
DCL  
OPCOM  
USER2  
USER3  
USER4  
USER5  
USER6  
USER7  
USER8  
USER9  
USER10  
USER11  
USER12  
USER13  
USER14  
USER15  
USER16

Terminal is set "No Broadcast", no broadcast messages will be displayed.

This example shows the display you see when messages from `USER1` are enabled, but will not be received, because the terminal is set `NO BROADCAST`.

4. 

```
$ SET BROADCAST=NONE
$ SHOW BROADCAST
```

Broadcasts are disabled for all classes

This example shows the display you see when **SET BROADCAST=NONE** is in effect.

## SHOW CLUSTER

**SHOW CLUSTER** — Invokes the Show Cluster utility to monitor and display cluster activity and performance.

## Format

**SHOW CLUSTER**

## Description

For more information about the Show Cluster utility, see the relevant section in the [VSI OpenVMS System Management Utilities Reference Manual, Volume 2: M-Z](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/#SHCL_PART) [[https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/#SHCL\\_PART](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/#SHCL_PART)] or online help.

## SHOW CPU

**SHOW CPU** — Displays the current state of the processors in an OpenVMS system.

## Format

**SHOW CPU** [*cpu-id*[, ...]]

## Parameter

*cpu-id*[, ...]

Specifies a decimal value representing the identity of a processor in a OpenVMS multiprocessing system. On an Alpha 7000 system, the CPU ID is the backplane slot number of the processor.

## Description

The **SHOW CPU** command displays information about the status, characteristics, and capabilities of the processors active in and available to an OpenVMS multiprocessing or single-CPU system.

You identify the processors to be displayed by using either the **/ACTIVE** qualifier, the **/ALL** qualifier, a CPU ID, or list of CPU IDs. If you specify none of these, the **SHOW CPU** command uses the **/ALL** qualifier by default.

You identify the type of information to be displayed by using the **/BRIEF**, **/FULL**, and **/SUMMARY** qualifiers. If you specify none of these qualifiers, the **SHOW CPU** command assumes the **/BRIEF** qualifier by default; however, if you likewise do not identify a processor or processors as the object of a command, the **SHOW CPU** command assumes a default of **SHOW/ALL/SUMMARY**.

The **SHOW CPU/FULL** command lists the current process on each configured processor without stopping other activity on the system. The current process may change while the data is displayed. As a result, there may be apparent inconsistencies in the display. For example, a process may be listed as the current process on more than one CPU.

## Qualifies

### **/ACTIVE\_SET**

Selects as the subject of the display only those processors that are members of the system's active set.

### **/ALL**

Selects all configured processors, active and inactive, as the subject of the display.

**/BRIEF**

Produces information from the summary display and also lists the current CPU state and current process (if any) for each processor in the configuration.

**/CONFIGURE\_SET (Alpha/Integrity servers only)**

Selects as the subject of the display only those processors that are members of the system's configure set- those that are actively owned and controlled by the current instance.

**/EXACT**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify a search string that must match the search string exactly and must be enclosed with quotation marks (" ").

If you specify the **/EXACT** qualifier without the **/SEARCH** qualifier, exact search mode is enabled when you set the search string with the Find (**E1**) key.

**/FULL**

Produces information from the summary display. The **/FULL** qualifier also lists the current CPU state, the current process (if any), the revision levels, and the capabilities for each configured processor. It indicates which processes can execute only on certain processors in the configuration. In addition, if one or more uniprocessing drivers are present in the system, the **/FULL** qualifier lists them by name.

The **SHOW CPU/FULL** command lists the current process on each configured processor without stopping other activity on the system. The current process may change while the data is displayed. As a result, there may be apparent inconsistencies in the display. For example, a process may be listed as the current process on more than one CPU.

This qualifier also displays whether the CPU is enabled or disabled for use as a Fast Path preferred CPU, then lists the Fast Path ports assigned to it, and shows whether or not the ports are user-assigned.

For more information about using Fast Path features to improve I/O performance, see the relevant section in the *VSI OpenVMS I/O User's Reference Manual* [<https://docs.vmssoftware.com/vsi-openvms-io-user-s-reference-manual/#d0e29396>].

**/HIGHLIGHT[=keyword]**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify the type of highlighting you want when a search string is found. When a string is found, the entire line is highlighted. You can use the following keywords: BOLD, BLINK, REVERSE, and UNDERLINE. BOLD is the default highlighting.

**/OUTPUT[=filespec]****/NOOUTPUT**

Controls where the output of the command is sent. If you do not enter the qualifier, or if you enter the **/OUTPUT** qualifier without a file specification, the output is sent to the current process default output stream or device, identified by the logical name SYS\$OUTPUT.

If you enter the **/OUTPUT** qualifier with a partial file specification (for example, specifying only a directory), SHOW is the default file name and .LIS the default file type. If you enter a file specification, it may not include the asterisk (\*) and the percent sign (%) wildcard characters.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

**/PAGE[=keyword]**  
**/NOPAGE (default)**

Controls the display of device information on the screen.

You can use the following keywords with the **/PAGE** qualifier:

| Keyword           | Description                                                                               |
|-------------------|-------------------------------------------------------------------------------------------|
| CLEAR_SCREEN      | Clears the screen before each page is displayed.                                          |
| SCROLL            | Displays information one line at a time.                                                  |
| SAVE[= <i>n</i> ] | Enables screen navigation of information, where <i>n</i> is the number of pages to store. |

The **/PAGE=SAVE** qualifier allows you to navigate through screens of information. The **/PAGE=SAVE** qualifier stores up to 5 screens of up to 255 columns of information. When you use the **/PAGE=SAVE** qualifier, you can use the following keys to navigate through the information:

| Key Sequence                                                           | Description                                                 |
|------------------------------------------------------------------------|-------------------------------------------------------------|
| Up arrow key, <b>Ctrl/B</b>                                            | Scroll up one line.                                         |
| Down arrow key                                                         | Scroll down one line.                                       |
| Left arrow key                                                         | Scroll left one column.                                     |
| Right arrow key                                                        | Scroll right one column.                                    |
| Find ( <b>E1</b> )                                                     | Specify a string to find when the information is displayed. |
| Insert Here ( <b>E2</b> )                                              | Scroll right one half screen.                               |
| Remove ( <b>E3</b> )                                                   | Scroll left one half screen.                                |
| Select ( <b>E4</b> )                                                   | Toggle 80/132 column mode.                                  |
| Prev Screen ( <b>E5</b> )                                              | Get the previous page of information.                       |
| Next Screen ( <b>E6</b> ), <b>Return</b> , <b>Enter</b> , <b>Space</b> | Get the next page of information.                           |
| <b>F10</b> , <b>Ctrl/Z</b>                                             | Exit. (Some utilities define these differently.)            |
| Help ( <b>F15</b> )                                                    | Display utility help text.                                  |
| Do ( <b>F16</b> )                                                      | Toggle the display to oldest/newest page.                   |
| <b>Ctrl/W</b>                                                          | Refresh the display.                                        |

The **/PAGE** qualifier is not compatible with the **/OUTPUT** qualifier.

**/POTENTIAL\_SET (Alpha/Integrity servers only)**

Selects as the subject of the display only those processors that are members of the system's potential set - those CPUs in the hard partition that meet the current instance's requirements to join its active set.

Inclusion in this set does not imply that the CPU is (or ever will be) owned by the current instance. The potential set only describes those physically existing CPUs that currently meet the instance-specific hardware and software compatibility constraints, should they ever become available.

**/SEARCH="string"**

Use with the **/PAGE=SAVE** qualifier to specify a string that you want to find in the information being displayed. Quotation marks are required for the **/SEARCH** qualifier, if you include spaces in the text string.

You can also dynamically change the search string by pressing the Find key (**F1**) while the information is being displayed. Quotation marks are not required for a dynamic search.

**/STANDBY\_SET (Alpha/Integrity servers only)**

Selects as the subject of the display only those processors that are members of the system's standby set – those CPUs in the hard partition that are not currently owned by soft partitions.

Supported only on AlphaServer systems that support partitioning.

**/SUMMARY**

Produces a display listing the processors in the OpenVMS multiprocessing or single-CPU system, indicating which is the primary processor, which processors are configured, and which processors are active.

The **/SUMMARY** qualifier also indicates the minimum revision levels required for processors in the system, which OpenVMS synchronization image has been loaded into the operating system, and whether multiprocessing is enabled. If the presence of one or more uniprocessing drivers in the system prohibits the enabling of multiprocessing, the **SHOW CPU** command displays a warning message.

**/SYSTEM (Alpha/Integrity servers only)**

Displays platform-specific hardware information relating to the current instance.

**/WRAP****/NOWRAP (default)**

Use with the **/PAGE=SAVE** qualifier to limit the number of columns to the width of the screen and to wrap lines that extend beyond the width of the screen to the next line.

The **/NOWRAP** qualifier extends lines beyond the width of the screen and can be seen when you use the scrolling (left and right) features provided by the **/PAGE=SAVE** qualifier.

## Examples

### 1. \$ SHOW CPU

```
Alpha:
System: LOWFAT, COMPAQ AlphaServer DS20E 666 MHz
Integrity servers:
System: EUROS, HPE rx2600 (900MHz/1.5MB)

CPU ownership sets:
  Active           0,1
  Configure        0,1

CPU state sets:
  Potential        0,1
  Autostart        0,1
  Powered Down     None
```

|               |      |
|---------------|------|
| Not Present   | None |
| Hard Excluded | None |
| Failover      | None |

The **SHOW CPU** command in this example produces a configuration summary of all configured processors in the Alpha (LOWFAT) and Integrity server (EUROS) systems. The primary processor is CPU 01, and all configured processors are active.

## 2. \$ SHOW CPU/BRIEF

```
Alpha:
System: LOWFAT, COMPAQ AlphaServer DS20E 666 MHz
CPU 0      State: RUN                CPUIDB: 81C1A000      Handle: * None
*
      Process: DAVIS                  PID: 20400EB2

CPU 1      State: RUN                CPUIDB: 81D03680      Handle: * None *
```

Integrity servers:

```
System: EUROS, HPE rx2600 (900MHz/1.5MB)
CPU 0      State: RUN                CPUIDB: 8901C000      Handle:
00005D70
      Owner: 000004C8                Current: 000004C8      Partition 0
(EUROS)

CPU 1      State: RUN                CPUIDB: 89163480      Handle: 00005E80
      Owner: 000004C8                Current: 000004C8      Partition 0
(EUROS)
      Process: DAVIS                  PID: 20201192
```

The **SHOW CPU/BRIEF** command in this example produces a configuration summary of the Alpha (LOWFAT) and Integrity server (EUROS) systems. It also indicates that its two processors are in the RUN state. Only CPU 00 has a current process.

## 3. \$ SHOW CPU/FULL

```
System: WFGLXD, AlphaServer GS320 6/731

SMP execlet   = 2 : Enabled : Full checking.
Config tree   = Version 6
Primary CPU    = 0
HWRPB CPUs    = 32
Page Size     = 8192
Revision Code  =
Serial Number  = BUDATEST
Default CPU Capabilities:
      System: QUORUM RUN
Default Process Capabilities:
      System: QUORUM RUN

CPU 0      State: RUN                CPUIDB: 81416000      Handle: 00003200
      Owner: 000006C0                Current: 000006C0      Partition 0
(WFGLXA)
      ChgCnt:          1              State: Present, Primary, Hotswap
      Process: SHADOW_SERVER          PID: 00000434
Capabilities:
      System: PRIMARY QUORUM RUN RAD0
Slot Context: 8F5BA180
CPU        -  State.....: RC, PA, PP, CV, PV, PMV, PL
```

```

Type.....: EV67, Pass 2.3
Speed.....: 730 Mhz
Variation.....: VAX FP, IEEE FP, Primary Eligible
Serial Number...: SM00700054
Revision.....:
Halt Request...: 0
Software Comp...: 8.4
PALCODE - Revision Code...: 1.96-01
Compatibility...: 6
Max Shared CPUs: 32
Memory Space...: Physical = 00000000.00000000 Length =
0
Scratch Space...: Physical = 00000000.00000000 Length =
0
Bindings:
NETACP          PID = 0000041A Reason: PRIMARY Capability
Fastpath:      * None *
Features:
Autostart - Enabled.
Fastpath - Selection enabled as Preferred CPU.

CPU 1      State: RUN          CPUDB: 81456880      Handle: 00003500
          Owner: 000006C0      Current: 000006C0      Partition 0
(WFGLXA)
          ChgCnt:      1          State: Present, Hotswap, Reassignable
          Process: SYSTEM          PID: 00000428
Capabilities:
System: QUORUM RUN RAD0
Slot Context: 8F5BA400
CPU      - State.....: RC, PA, PP, CV, PV, PMV, PL
          Type.....: EV67, Pass 2.3
          Speed.....: 730 Mhz
          Variation.....: VAX FP, IEEE FP, Primary Eligible
          Serial Number...: NI94370773
          Revision.....:
          Halt Request...: 0
          Software Comp...: 8.4
          PALCODE - Revision Code...: 1.96-01
          Compatibility...: 6
          Max Shared CPUs: 32
          Memory Space...: Physical = 00000000.00000000 Length =
0
          Scratch Space...: Physical = 00000000.00000000 Length =
0
          Bindings:      * None *
          Fastpath:      * None *
          Features:
          Autostart - Enabled.
          Fastpath - Selection enabled as Preferred CPU.

```

The **SHOW CPU/FULL** command in this example produces a configuration summary of the AlphaServer GS320 system, WFGLXD. All are in the RUN state and all have a current process.

Note that NETACP can only run on CPU 0, because only CPU 0 has primary capability. Note also that CPUs 0 and 1 have Fast path ports.

#### 4. \$ SHOW CPU 2/BRIEF

System: WFGLXA, AlphaServer GS320 6/731

```
CPU 2      State: RUN                      CPUIDB: 81457680      Handle: 00003800
           Owner: 000006C0                Current: 000006C0    Partition 0
(WFGLXA)
           Process: SHADOW_SERVER          PID: 00000429
```

The **SHOW CPU/BRIEF** command in this example produces a brief configuration summary of CPU 2. CPU 2 is currently running under instance WFGLXA in partition 0.

5. \$ SHOW CPU 11

System: WFGLXA, AlphaServer GS320 6/731

```
CPU 11     State: NOT_CONFIGURED          CPUIDB: 81470E00      Handle: 000125C0
           Owner: 00000440                Current: 00000440    Hard Partition 0
```

This **SHOW CPU** command produces a configuration summary of CPU 11 on instance WFGLXA. CPU 11 is not configured in this instance and is currently assigned to hard partition 0.

6. \$ SHOW CPU 8/FU

System: WFGLXA, AlphaServer GS320 6/731

```
CPU 8      State: POWERED_DOWN            CPUIDB: 81459280      Handle: 00011CC0
           Owner: 000006C0                Current: 000006C0    Partition 0 (WFGLXA)
           ChgCnt:      3                  State: Present, In-Console, Powered
Down,
   Hotswap, Reassignable
           Process: * None *
Capabilities:
           System: QUORUM RAD0
Slot Context: 8F5BB580
           CPU      - State.....: BIP, CV, PV, PMV, PL
Bindings:      * None *
Fastpath:      * None *
Features:
           Autostart - Enabled.
           Fastpath  - Selection enabled as Preferred CPU.
```

This **SHOW CPU** command produces a summary of CPU 8. CPU 8 is currently powered down, but a CPU module is present in the backplane slot.

7. \$ SHO CPU

System: WFGLXA, AlphaServer GS320 6/731

CPU ownership sets:

```
Active      0-3,9,10
Configure   0-3,8-10
Standby     11
Hard Partition 11
```

CPU state sets:

```
Potential   0-7,9-15
Autostart    0-31
Powered Down 8
Not Present  16-31
```

Failover                      None

The **SHOW CPU** command shows the configuration characteristics of the instance.

8. \$ SHOW CPU/SYS

System: WFGLXA, AlphaServer GS320 6/731

```
SMP execlet      = 2 : Enabled : Full checking.
Config tree     = Version 6
Primary CPU      = 0
HWRPB CPUs      = 32
Page Size       = 8192
Revision Code    =
Serial Number    = BUDATEST
Default CPU Capabilities:
    System: QUORUM RUN
Default Process Capabilities:
    System: QUORUM RUN
```

CPU ownership sets:

```
Active           0-3,9,10
Configure        0-3,8-10
Standby          11
    Hard Partition 11
```

CPU state sets:

```
Potential        0-7,9-15
Autostart         0-31
Powered Down     8
Not Present      16-31
Failover         None
```

This **SHOW CPU/SYSTEM** command shows the platform-specific hardware information relating to instance WFGXLA.

9. \$ SET PROCESS /AFFINITY /SET=3 SYSTEM/PERMANENT  
\$ SHOW CPU 3/FULL

System: WFGLXD, AlphaServer GS320 6/731

```
CPU 3      State: RUN                      CPUIDB: 81416000      Handle: 00003200
           Owner: 000006C0                  Current: 000006C0      Partition 0
(WFGLXA)
           ChgCnt:          1                State: Present, Primary, Hotswap
           Process: SHADOW_SERVER            PID: 00000434
Capabilities:
           System: PRIMARY QUORUM RUN RAD0
Slot Context: 8F5BA180
CPU        - State.....: RC, PA, PP, CV, PV, PMV, PL
           Type.....: EV67, Pass 2.3
           Speed.....: 730 Mhz
           Variation.....: VAX FP, IEEE FP, Primary Eligible
           Serial Number...: SM00700054
           Revision.....:
           Halt Request...: 0
           Software Comp...: 8.4
PALCODE    - Revision Code...: 1.96-01
```

```

Compatibility...: 6
Max Shared CPUs: 32
Memory Space...: Physical = 00000000.00000000 Length =
0
Scratch Space...: Physical = 00000000.00000000 Length =
0
Bindings:
  SYSTEM          PID = 00000434 Reason: Affinitized to this CPU
Fastpath:
  PNA0
Features:
  Autostart - Enabled.
  Fastpath - Selection enabled as Preferred CPU.

```

In this example, the SYSTEM process has its affinity set permanently to CPU 3. The **SHOW CPU** command indicates this is the BINDINGS list.

The port PNA0 was assigned to CPU 3 by a user when CPU 3 was enabled as a Fast Path preferred CPU. Subsequent to that operation, CPU 3's bit was cleared in the IO\_PREFER\_CPUS system parameter. This disabled CPU 3 for use as a Fast Path preferred CPU. Normally this is a transient condition, as changing IO\_PREFER\_CPUS results in the FASTPATH\_SERVER process redistributing the Fast Path ports across the set of usable CPUs.

However, if there is no FASTPATH\_SERVER process, PNA0 remains assigned to this CPU until any of the following actions occur:

- a. The user tries to move the port to another CPU by using the **SET DEVICE/PREFERRED\_CPU** command, \$QIO, or the \$IO\_FASTPATH system service.
- b. The CPU is stopped.

#### 10. \$ SHOW CPU/FULL

```

System: LOWFAT, COMPAQ AlphaServer DS20E 666 MHz
SMP execlet   = 3 : Enabled : Streamlined.
Config tree   = None
  Primary CPU   = 0
  HWRPB CPUs    = 2
  Page Size     = 8192
  Revision Code =
  Serial Number = 4033DZ2Z1023
  Default CPU Capabilities:
    System: QUORUM RUN
  Default Process Capabilities:
    System: QUORUM RUN

CPU 0      State: RUN                      CPUDB: 81C1A000      Handle: * None *
          Process: DAVIS                    PID: 20400EB2
  Capabilities:
    System: PRIMARY QUORUM RUN RAD0
    User:  Usr1 Usr2
  Slot Context: 857F6180
    CPU      - State.....: RC, PA, PP, CV, PV, PMV, PL
               Type.....: EV67, Pass 2.2.3 & Pass 2.2.5
               Speed.....: 667 Mhz
               Variation.....: VAX FP, IEEE FP, Primary Eligible
               Serial Number...:
               Revision.....:

```

```

                                Halt Request...: 0
                                Software Comp...: 8.4
PALCODE - Revision Code...: 1.98-01
                                Compatibility...: 79
                                Max Shared CPUs: 2
                                Memory Space...: Physical = 00000000.00000000 Length =
0
                                Scratch Space...: Physical = 00000000.00000000 Length =
0
Bindings:      * None *
Fastpath:
    PKC0
    FGA0
    PEA0
    EWA0
Features:
    Autostart - Enabled.
    Fastpath  - Selection enabled as Preferred CPU.

CPU 1      State: RUN              CPUDB: 81D03680      Handle: * None *
    Process: * None *
Capabilities:
    System: QUORUM RUN RAD0
Slot Context: 857F6400
    CPU      - State.....: RC, PA, PP, CV, PV, PMV, PL
                Type.....: EV67, Pass 2.2.3 & Pass 2.2.5
                Speed.....: 667 Mhz
                Variation.....: VAX FP, IEEE FP, Primary Eligible
                Serial Number...:
                Revision.....:
                Halt Request...: 0
                Software Comp...: 8.4
PALCODE - Revision Code...: 1.98-01
                Compatibility...: 79
                Max Shared CPUs: 2
                Memory Space...: Physical = 00000000.00000000 Length =
0
                Scratch Space...: Physical = 00000000.00000000 Length =
0
Bindings:      * None *
Fastpath:
    PKB0
    PKA0
    FWA0
    BG0
Features:
    Autostart - Enabled.
    Fastpath  - Selection enabled as Preferred CPU.
$

```

The **SHOW CPU/FULL** command in this example produces a configuration summary of the Alpha DS20E 666 MHz system LOWFAT, indicating that only CPU 0, the primary CPU, is active and in the RUN state. It also shows that there is a uniprocessing driver loaded in the system, thus preventing the system from being enabled as a multiprocessor.

# SHOW DEFAULT

SHOW DEFAULT — Displays the current default device and directory.

## Format

**SHOW DEFAULT**

## Description

The **SHOW DEFAULT** command displays the current device and directory names, along with any equivalence strings.

The default disk and directory are established in the user authorization file (UAF). You can change these defaults during a terminal session or in a batch job by using the **SET DEFAULT** command, or by reassigning the logical name SYS\$DISK.

## Examples

```
1. $ SHOW DEFAULT
   DISK1:[ALAMO]
   $ SET DEFAULT DISK5:[SKONETSKI.SOURCES]
   $ SHOW DEFAULT
   DISK5:[SKONETSKI.SOURCES]
```

The **SHOW DEFAULT** command in this example displays the current default device and directory names. The **SET DEFAULT** command changes these defaults, and the next **SHOW DEFAULT** command displays the new default device and directory.

```
2. $ SET DEFAULT NOSUCH:[NOWAY]
   $ SHOW DEFAULT
   NOSUCH:[NOWAY]
   %DCL-I-INVDEF, NOSUCH:[NOWAY] does not exist
```

In this example, the default has been set to a nonexistent device and directory. An error message is displayed.

```
3. $ DEFINE/TRANSLATION_ATTRIBUTES=CONCEALED XYZ WORK:[INVOICES.]
   $ SET DEFAULT XYZ:[HESHELMAN]
   $ SHOW DEFAULT
   XYZ:[HESHELMAN]
```

In this example, a logical name, XYZ, is defined to represent WORK:[INVOICES]. The **/TRANSLATION\_ATTRIBUTES=CONCEALED** qualifier tells the system not to display the translation of XYZ in file specifications. Thus, the **SHOW DEFAULT** command displays the logical name XYZ and not its translation.

```
4. $ SET DEFAULT WRK:[SCHENKENBERGER]
   $ SHOW DEFAULT
   WRK:[SCHENKENBERGER]
   $ DEFINE KUDOS WRK:[SCHENKENBERGER.TEMP1],WRK:[SCHENKENBERGER.TEMP2]
   $ SET DEFAULT KUDOS
   $ SHOW DEFAULT
   KUDOS:[SCHENKENBERGER]
   =    WRK:[SCHENKENBERGER.TEMP1]
```

```
= WRK:[SCHENKENBERGER.TEMP2]
```

In this example, the logical name KUDOS is defined as a search list containing the directories [SCHENKENBERGER.TEMP1] and [SCHENKENBERGER.TEMP2] on device WRK. The **SET DEFAULT** command equates this search list logical name with the logical name SYS\$DISK. The subsequent **SHOW DEFAULT** command displays the search list logical name along with its equivalence strings.

Because the directory field has not been explicitly specified, the original [SCHENKENBERGER] directory remains in effect as the current default directory; however, unless the current default directory syntax ([ ]) is explicitly used, all file references are to those directories contained in the search list.

## SHOW DEVICES

**SHOW DEVICES** — Displays the status of a device on the system. **See the qualifier descriptions for restrictions.**

### Format

```
SHOW DEVICES [device-name[:]]
```

### Parameter

*device-name*[:]

Specifies the name of a device for which information is to be displayed. The device name displayed by the system uses the format *ddcu* where *dd* is the device code, *c* is the controller designation, and *u* is the unit number. If the system is part of an OpenVMS Cluster that is running with HSC controllers, the device name must include the node name using the format *node\$ddcu* (where *node* is the node name).

You can specify a complete device name or only a portion of a device name. The **SHOW DEVICES** command provides defaults for nonspecified portions of device names, as follows:

- If you truncate a device name (for example, if you specify D), the command lists information about all devices whose device names begin with what you entered (in this case, D). However, if you specify a device in an OpenVMS Cluster that is running with HSC controllers, you must include the entire *node* portion of the device name.
- If you omit a controller designation, the **SHOW DEVICES** command lists all devices on all controllers with the specified unit number.
- If you omit a unit number, the **SHOW DEVICES** command lists all devices on the specified controller.

Note that the **/FILES** qualifier does not support defaults for nonspecified portions of device names; you must supply a complete device specification.

### Description

When you enter the **SHOW DEVICES** command without specifying a device or using any qualifier, information about all devices on the system is displayed. If you specify a device name, the **SHOW DEVICES** command displays information about that device. If you use certain qualifiers with the

**SHOW DEVICES** command, information is displayed about those devices that currently have volumes mounted or that have been allocated to processes, or both.

The device name displayed by the system uses the format *ddcu*, where *dd* is the device code, *c* is the controller designation, and *u* is the unit number. If the system is part of an OpenVMS Cluster that is running with HSC controllers, the device name must include the node name using the format *node\$ddcu* (where *node* is the node name).

If you enter the **SHOW DEVICES** command and do not specify a device name parameter or a qualifier, the command provides a brief listing of characteristics of all devices on the system, with the exception of pseudodevices with the mailbox characteristic, such as MBA3:, NLA0:, NET9:, and so on. To display such a device, you must specify all or part of the device name.

---

## Note

If a field width is too narrow to display a particular numeric field, asterisks are displayed in place of the data. Therefore, if asterisks appear in the Free Space field while displaying a particular device, use the **/UNITS** or **/SIZE** qualifier to display the free space in bytes.

---

## Qualifiers

### **/ALLOCATED**

Displays all devices currently allocated to processes.

If you specify a device name, the characteristics of only that device are displayed. If the device is not currently allocated, the command displays a message indicating that there is no such device. If you specify a generic device name, the characteristics of all allocated devices of that type are displayed.

### **/BRIEF (default)**

Displays brief information about the specified devices.

### **/BITMAP *ddcu*:**

Displays information regarding minicopy or HBMM (Host-Based Minimerge) bitmaps for the given shadow set.

Note that the **SHOW DEVICES /FULL *ddcu*:** display also displays status to indicate that bitmaps are active on the device.

### **/EXACT**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify a search string that must match the search string exactly and must be enclosed with quotation marks (" ").

If you specify the **/EXACT** qualifier without the **/SEARCH** qualifier, exact search mode is enabled when you set the search string with the Find (**E1**) key.

### **/FILES**

Requires SYSPRV (system privilege) or BYPASS privileges to list read-protected files.

Displays a list of the names of all files open on a volume and their associated process name and process identification (PID). The specified device must be a mounted Files-11 volume. If the specified volume is a multivolume set, the files on each volume in the set are listed.

## Note

The **SHOW DEVICES/FILES** command does not support defaults for nonspecified portions of device names. You must supply a complete device specification when using the **/FILES** qualifier.

---

If the **/SYSTEM** qualifier is also specified, only the names of installed files and files opened by the system are displayed. Files opened by the system are those that have been opened without the use of an ancillary control process (ACP), such as INDEXF.SYS and QUOTA.SYS, as well as system files such as JBCSYSQUE.EXE and SYSMMSG.EXE.

If the **/NOSYSTEM** qualifier is specified, only those files opened by processes are displayed. To list files opened by a process in your group, your process must have at least GROUP privilege. If the process is not in your group, you need WORLD privilege.

If neither the **/SYSTEM** nor the **/NOSYSTEM** qualifier is specified, the names of all files currently opened on the system are displayed.

If a file is read-protected from your user identification code (UIC), the "No privilege" message is displayed instead of the file name. You must have SYSPRV (system privilege) privilege or BYPASS privilege to display the file name.

A space in place of a file name represents a work file (such as a temporary edit file) not entered in any directory. To display temporary file names, you must have BYPASS privilege in addition to GROUP or WORLD privilege.

Do not use the **/FILES** qualifier with the **/ALLOCATED**, **/BRIEF**, **/FULL**, or **/MOUNTED** qualifier. The functions of the **/FILES** qualifier and these qualifiers are mutually exclusive.

## **/FULL**

Displays a complete list of information about the devices, as appropriate, except for rebuild status. You must use the **/REBUILD\_STATUS** qualifier to get that information.

The display will be in blocks or bytes, depending on the current system default setting. You can use **SHOW PROCESS/UNITS** to display the current default. To change the default, execute the DCL command **SET PROCESS/UNITS=BYTES** or **SET PROCESS/UNITS=BLOCKS**.

For more information about fields related to Dissimilar Device Shadowing (DDS) or Dynamic Volume Expansion (DVE) in the display, see the discussion of these topics in the [VSI OpenVMS System Manager's Manual, Volume 1: Essentials](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#d0e28741) [https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#d0e28741].

## **/HIGHLIGHT[=keyword]**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify the type of highlighting you want when a search string is found. When a string is found, the entire line is highlighted. You can use the following keywords: BOLD, BLINK, REVERSE, and UNDERLINE. BOLD is the default highlighting.

## **/MOUNTED**

Displays all devices that currently have volumes mounted on them.

If you specify a device name, only the characteristics of that device are displayed; however, if the device is not currently mounted, the command issues a message indicating there is no such device. If

you specify a generic device name, the characteristics of all such devices that currently have volumes mounted are displayed.

## **/MULTIPATH**

Displays all devices that are currently multipath sets.

If you specify a device name, only the characteristics of that device are displayed; however, if the device is not a multipath set, the command issues a message indicating there is no such device. If you specify a generic device name, the characteristics of all such devices that are currently multipath sets are displayed.

## **/OUTPUT[=*filespec*]**

## **/NOOUTPUT**

Controls where the output of the command is sent. If you do not enter the qualifier, or if you enter the **/OUTPUT** qualifier without a file specification, the output is sent to the current process default output stream or device, identified by the logical name SYS\$OUTPUT.

If you enter the **/OUTPUT** qualifier with a partial file specification (for example, specifying only a directory), **SHOW** is the default file name and **.LIS** the default file type. If you enter a file specification, it may not include the asterisk (\*) and the percent sign (%) wildcard characters.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

## **/PAGE[=*keyword*]**

## **/NOPAGE (default)**

Controls the display of device information on the screen.

You can use the following keywords with the **/PAGE** qualifier:

| Keyword                | Description                                                                               |
|------------------------|-------------------------------------------------------------------------------------------|
| <b>CLEAR_SCREEN</b>    | Clears the screen before each page is displayed.                                          |
| <b>SCROLL</b>          | Displays information one line at a time.                                                  |
| <b>SAVE[=<i>n</i>]</b> | Enables screen navigation of information, where <i>n</i> is the number of pages to store. |

The **/PAGE=SAVE** qualifier allows you to navigate through screens of information. The **/PAGE=SAVE** qualifier stores up to 5 screens of up to 255 columns of information. When you use the **/PAGE=SAVE** qualifier, you can use the following keys to navigate through the information:

| Key Sequence                       | Description                                                 |
|------------------------------------|-------------------------------------------------------------|
| <b>Up</b> arrow key, <b>Ctrl/B</b> | Scroll up one line.                                         |
| <b>Down</b> arrow key              | Scroll down one line.                                       |
| <b>Left</b> arrow key              | Scroll left one column.                                     |
| <b>Right</b> arrow key             | Scroll right one column.                                    |
| <b>Find (E1)</b>                   | Specify a string to find when the information is displayed. |
| <b>Insert Here (E2)</b>            | Scroll right one half screen.                               |
| <b>Remove (E3)</b>                 | Scroll left one half screen.                                |
| <b>Select (E4)</b>                 | Toggle 80/132 column mode.                                  |

| Key Sequence                                                           | Description                                      |
|------------------------------------------------------------------------|--------------------------------------------------|
| Prev Screen ( <b>E5</b> )                                              | Get the previous page of information.            |
| Next Screen ( <b>E6</b> ), <b>Return</b> , <b>Enter</b> , <b>Space</b> | Get the next page of information.                |
| <b>F10</b> , <b>Ctrl/Z</b>                                             | Exit. (Some utilities define these differently.) |
| Help ( <b>F15</b> )                                                    | Display utility help text.                       |
| Do ( <b>F16</b> )                                                      | Toggle the display to oldest/newest page.        |
| <b>Ctrl/W</b>                                                          | Refresh the display.                             |

The **/PAGE** qualifier is not compatible with the **/OUTPUT** qualifier.

### **/REBUILD\_STATUS**

Tells you whether volumes need rebuilding.

You may need to rebuild a volume if the volume was improperly dismounted. Volumes are improperly dismounted when, for example, the system crashes.

For each volume, **SHOW DEVICES/REBUILD\_STATUS** returns one of these values:

| Value                   | Meaning                                                                                                                                         |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------|
| Yes                     | Rebuild needed.                                                                                                                                 |
| No                      | Rebuild not needed.                                                                                                                             |
| Not applicable          | You cannot rebuild this volume. This value is returned if, for example, the volume is not a disk, or the volume is write-locked.                |
| Information unavailable | Rebuild information is unavailable. This value is returned when, for example, the volume is not mounted, or mount verification is taking place. |

To rebuild a volume, either:

- Use **SET VOLUME/REBUILD**
- Dismount the volume, then mount the volume again using **MOUNT/REBUILD**

You cannot use the **/REBUILD\_STATUS** qualifier with any other **SHOW DEVICES** qualifiers, except **/OUTPUT**.

### **/SEARCH="string"**

Use with the **/PAGE=SAVE** qualifier to specify a string that you want to find in the information being displayed. Quotation marks are required for the **/SEARCH** qualifier, if you include spaces in the text string.

You can also dynamically change the search string by pressing the Find key (**E1**) while the information is being displayed. Quotation marks are not required for a dynamic search.

### **/SIZE=keyword**

Allows you to override the current default specified by **SET PROCESS/UNITS** so that you can display disk free space in your choice of blocks or bytes. (**/SIZE** is functionally equivalent to **/UNITS**.)

The following keywords are valid with the **/SIZE** qualifier: BLOCKS, BYTES.

If you specify **/SIZE** with no keyword, the default value is not changed.

#### **/SYSTEM**

#### **/NOSYSTEM**

Controls whether the names of installed files and files opened by the system are displayed. Files opened by the system are those that have been opened without the use of an ancillary control process (ACP), such as INDEXF.SYS and QUOTA.SYS.

If you specify the **/NOSYSTEM** qualifier with the **/FILES** qualifier, only files opened by processes are displayed. If you omit both the **/SYSTEM** and **/NOSYSTEM** qualifiers and specify the **/FILES** qualifier, the names of all files currently open on the system are displayed.

You can use this qualifier only with the **/FILES** qualifier. See the description of the [/FILES](#) qualifier for more details.

#### **/UNITS=keyword**

Allows you to override the current default specified by **SET PROCESS/UNITS** so that you can display disk free space in your choice of blocks or bytes. (**/UNITS** is functionally equivalent to **/SIZE**.)

The following keywords are valid with the **/UNITS** qualifier: BLOCKS, BYTES.

If you specify **/UNITS** with no keyword, the default value is not changed.

#### **/WINDOWS**

Displays the window count and total size of all windows for files open on a volume. The file name and related process name and process identification (PID) are also displayed. The letter C in a display indicates that the file is open with "cathedral windows" (segmented windows).

#### **/WRAP**

#### **/NOWRAP (default)**

Use with the **/PAGE=SAVE** qualifier to limit the number of columns to the width of the screen and to wrap lines that extend beyond the width of the screen to the next line.

The **/NOWRAP** qualifier extends lines beyond the width of the screen and can be seen when you use the scrolling (left and right) features provided by the **/PAGE=SAVE** qualifier.

## Examples

### 1. \$ SHOW DEVICES

| Device<br>Name | Device<br>Status | Err.<br>Count | Volume<br>Label | Free<br>Blocks | Trans<br>Count | Mount<br>Count |
|----------------|------------------|---------------|-----------------|----------------|----------------|----------------|
| DKA0:          | Online mnt       | 0             | VMS             | 47088          | 115            | 1              |
| DKA1:          | Online mnt       | 0             | USERPACK1       | 45216          | 2              | 1              |
| DKA2:          | Online mnt       | 3             | DOCUMENT        | 8068           | 20             | 1              |
| DKA5:          | Online mnt       | 0             | MASTERP         | 28668          | 1              | 1              |
| DKA6:          | Online           | 0             |                 |                |                |                |
| DKA7:          | Online mnt       | 0             | PROJECT         | 110547         | 1              | 1              |
| DMA0:          | Online           | 0             |                 |                |                |                |
| DLA0:          | Online           | 0             |                 |                |                |                |

```

DYA0:      Online      0
DYA1:      Online      0
DRA3:      Online mnt   0  RES26APR      29317      1      1

```

In this example, the **SHOW DEVICES** command displays the following information for each device on the system:

- Device name
- Device status and characteristics (status indicates whether the device is on line; characteristics indicate whether the device is allocated, is spooled, has a volume mounted on it, or has a foreign volume mounted on it)
- Error count
- Volume label (for disk and tape volumes only)
- Number of free blocks on the volume
- Transaction count
- Number of mount requests issued for the volume (disk devices only)

2. \$ SHOW DEVICES /FULL \$1\$dga30

```

Disk $1$DGA100: (EUROS), device type HPE MSA VOLUME, is online, mounted,
file-
oriented device, shareable, available to cluster, error logging is
enabled.

```

```

Error count      0      Operations completed
17299
Owner process    ""      Owner UIC
[SYSTEM]
Owner process ID 00000000  Dev Prot
S:RWPL,O:RWPL,G:R,W
Reference count   3      Default buffer size
512
Current preferred CPU Id 0      Fastpath
1
Total blocks      488327805  Sectors per track
96
Total cylinders   52987      Tracks per cylinder
96
Logical Volume Size 488327805  Expansion Size Limit
941752320
Host name         "EUROS"      Host type, avail HPE rx2600
(900MHz/1.5MB), yes
Allocation class   1
Volume label      "DEBUG-DISK1"  Relative volume number
0
Cluster size      480      Transaction count
2
Free blocks       16558560  Maximum files allowed
507617
Extend quantity   5      Mount count
2

```

```

Mount status          System    Cache name          "_
$7$DKD100:XQPCACHE"
  Extent cache size      64      Maximum blocks in extent cache
1655856
  File ID cache size     64      Blocks in extent cache
581760
  Quota cache size       0      Maximum buffers in FCP cache
3514
  Volume owner UIC       [SYSTEM]  Vol Prot
S:RWCD,O:RWCD,G:RWCD,W:RWCD

Volume Status:  ODS-2, subject to mount verification, file high-water
marking,
  write-back caching enabled.
Volume is also mounted on EUROS.

```

In this example, the **SHOW DEVICES** command requests a full listing of the status of the multipath device \$1\$DGA30. This device has four local Fibre Channel paths and one remote (MSCP-served) path.

3. \$ SHOW DEVICE/FULL DKB0:

Disk \$DKB0:, device type RZ56, is online, mounted, file-oriented device, shareable, error logging is enabled.

```

Error count           0  Operations completed           392750
Owner process         ""  Owner UIC                     [1,4]
Owner process ID      00000000  Dev Prot           S:RWPL,O:RWPL,G:R,W
Reference count       317  Default buffer size           512
Total blocks          1299174  Sectors per track           54
Total cylinders       1604  Tracks per cylinder          15

Volume label "SYSTEM_DISK"  Relative volume number           0
Cluster size         3  Transaction count             278
Free blocks          367632  Maximum files allowed        162396
Extend quantity       5  Mount count                   1
Mount status         System  Cache name          "$DKB0:XQPCACHE"
Extent cache size     64  Maximum blocks in extent cache  36763
File ID cache size    64  Blocks currently in extent cache 36258
Quota cache size      0  Maximum buffers in FCP cache   210
Volume owner UIC      [1,1]  Vol Prot    S:RWCD,O:RWCD,G:RWCD,W:RWCD

```

Volume status: ODS-2, subject to mount verification, protected subsystems enabled, file high-water marking, write-through XQP caching enabled, write-through XFC caching enabled.

In this example, the **SHOW DEVICES** command requests a full listing of the status of the RZ56 device DKB0.

4. \$ SHOW DEVICES/REBUILD\_STATUS

```

Device Name          Rebuild needed?

ADU15$DKA300:        Information unavailable
EDIV$DKA300:          Information unavailable
EMUL$DKB200:          No
EMUL$DKB300:          No
EMUL$DKB500:          Yes
FTA0:                 Not applicable

```

OPA0: Not applicable

In this example, the volume mounted on device EMUL\$DKB500 needs rebuilding.

5. \$ SHOW DEVICES/FULL NODE2\$

```
Disk NODE2$DUA0:, device type RA81, is online, mounted,
error logging enabled
  Error count          0  Operations completed          24195
  Owner process name    Owner UIC          [11,177]
  Owner process ID      20200000  Dev Prot   S:RWPL,O:RWPL,G:RWPL,W:RWPL
  Reference count       16  Default buffer size          512
  Volume label          VMSDOCLIB  Relative volume no.          0
  Cluster size          3  Transaction count          17
  Free blocks           525447  Maximum files allowed        111384
  Extend quantity       5  Mount count                  1
  Volume status         System  ACP process name
  Caching disabled
Volume is subject to mount verification, file high-water marking
```

```
Disk NODE2$DUA1:, device type RA81, is online, error logging enabled
  Error count          0  Operations completed          0
  Owner UIC            [0,0]  Owner process name
  Owner process ID      20200000  Dev Prot   S:RWED,O:RWED,G:RWED,W:RWED
  Reference count       0  Default buffer size          512
.
.
.
```

In this example, the user requested a full display of information about each device on NODE2 in the OpenVMS Cluster. Information is shown here only for the first two devices: a mounted device and a device that is not mounted.

6. \$ SHOW DEVICES MUA1/FULL

```
Magtape $4$MUA1: (HSC70), device type TA79, is online, device is
equipped with a stacker/loader, file-oriented device, available
to cluster, error logging is enabled.
```

```
  Error count          0  Operations completed          0
  Owner process        ""  Owner UIC          [SYSTEM]
  Owner process ID      00000000  Dev Prot   S:RWPL,O:RWPL,G:R,W
  Reference count       0  Default buffer size          2048
  Density              1600  Format          Normal-11
  Host name             "HSC70"  Host type, avail    HS70, yes
  Allocation class      4
```

Volume status: no-unload on dismount, odd parity.

In this example, the user requested a full display of the tape device MUA1.

7. \$ SHOW DEVICE/FULL \$1\$DKA221

```
Disk $1$DKA221: (HSC952), device type RZ29, is online, mounted,
file-oriented device, shareable, available to cluster, error
logging is enabled.
```

```
  Error count          0  Operations completed          6509
```

```

Owner process      "" Owner UIC [SYSTEM]
Owner process ID   00000000 Dev Prot S:RWPL,O:RWPL,G:R,W
Reference count    108 Default buffer size 512
Current preferred CPU Id 1 FastPath 1
Total blocks       8380080 Sectors per track 4
Total cylinders    65470 Tracks per cylinder 32
Host name          "HSC952" Host type, avail HS95, yes
Allocation class   1

Volume label "GALAXY_X6L5" Relative volume number 0
Cluster size    4 Transaction count 302
Free blocks     4691760 Maximum files allowed 838008
Extend quantity 5 Mount count 2
Mount status    System Cache name "_$1$DKA221:XQPCACHE"
Extent cache size 64 Maximum blocks in extent cache 469176
File ID cache size 64 Blocks currently in extent cache 237504
Quota cache size 0 Maximum buffers in FCP cache 1734
Volume owner UIC [1,1] Vol Prot S:RWCD,O:RWCD,G:RWCD,W:RWCD

```

Volume Status: ODS-2, subject to mount verification, protected  
subsystems enabled, file high-water marking, write-through  
XQP caching enabled, write-through XFC caching enabled.  
Volume is also mounted on MEAD.

This disk is a device that performs its I/O through the Fast Path port PNA0. Fast Path is enabled for this disk, and its I/O will be processed on the preferred CPU, CPU 1, which is associated with its Fast Path port PNA0.

The **/FULL** qualifier also displays additional information about Fast Path devices. A Fast Path device may be either a class device or a port device. An example of a class device is an HSC disk, and an example of a port device is the CI. For both Fast Path class devices and ports, the display indicates that Fast Path is enabled and lists the current CPU ID to which that device is assigned. Additionally, for a Fast Path port, the display indicates the port's user-established CPU preference (if any).

The current preferred CPU and the User Preferred CPU can be set by using the DCL command, **SET DEVICE/PREFERRED\_CPU**, or by issuing a \$QIO.

For more information about using Fast Path features to improve I/O performance, see the relevant section in the *VSI OpenVMS I/O User's Reference Manual* [<https://docs.vmssoftware.com/vsi-openvms-io-user-s-reference-manual/#d0e29396>].

#### 8. \$ SHOW DEVICE/FULL PNA0

Device PNA0:, device type CIXCD, is online, shareable, error logging is enabled.

```

Error count      0 Operations completed 0
Owner process    "" Owner UIC [SYSTEM]
Owner process ID 00000000 Dev Prot S:RWPL,O:RWPL,G,W
Reference count   0 Default buffer size 0
Current preferred CPU Id 1 FastPath 1

```

The above display shows that port PNA0 is assigned to CPU 1 and that Fast Path is enabled.

#### 9. \$ SHOW DEVICE/FULL PNA0

Device PNA0:, device type CIXCD, is online, shareable, error logging is enabled.

|                          |          |                      |                   |
|--------------------------|----------|----------------------|-------------------|
| Error count              | 0        | Operations completed | 0                 |
| Owner process            | " "      | Owner UIC            | [SYSTEM]          |
| Owner process ID         | 00000000 | Dev Prot             | S:RWPL,O:RWPL,G,W |
| Reference count          | 0        | Default buffer size  | 0                 |
| Current preferred CPU Id | 1        | FastPath             | 1                 |
| User preferred CPU Id    | 2        |                      |                   |

This example shows a Fast Path assignment made by a user.

Normally, the User Preferred CPU ID matches the current preferred CPU ID. The reason for the mismatch in the above display is because CPU 2 was stopped. The port was previously assigned to CPU 2. But when CPU 2 was stopped, the operating system moved the port assignment from CPU 2 to CPU 1.

If CPU 2 were started, the operating system would assign the device to the User Preferred CPU.

#### 10. \$ SHOW DEVICE/FULL DSA0

Disk DSA0:, device type RAM Disk, is online, mounted, file-oriented device, shareable, available to cluster, error logging is enabled, device supports bitmaps (no bitmaps active).

|                    |          |                                  |                             |
|--------------------|----------|----------------------------------|-----------------------------|
| Error count        | 0        | Operations completed             | 47                          |
| Owner process      | " "      | Owner UIC                        | [SYSTEM]                    |
| Owner process ID   | 00000000 | Dev Prot                         | S:RWPL,O:RWPL,G:R,W         |
| Reference count    | 2        | Default buffer size              | 512                         |
| Total blocks       | 1000     | Sectors per track                | 64                          |
| Total cylinders    | 1        | Tracks per cylinder              | 32                          |
| Volume label       | "TST0"   | Relative volume number           | 0                           |
| Cluster size       | 1        | Transaction count                | 1                           |
| Free blocks        | 969      | Maximum files allowed            | 250                         |
| Extend quantity    | 5        | Mount count                      | 1                           |
| Mount status       | System   | Cache name                       | "_\$252\$DUA721:XQPCACHE"   |
| Extent cache size  | 64       | Maximum blocks in extent cache   | 96                          |
| File ID cache size | 64       | Blocks currently in extent cache | 0                           |
| Quota cache size   | 0        | Maximum buffers in FCP cache     | 404                         |
| Volume owner UIC   | [SYSTEM] | Vol Prot                         | S:RWCD,O:RWCD,G:RWCD,W:RWCD |

Volume Status: ODS-2, subject to mount verification, file high-water marking, write-back XQP caching enabled, write-through XFC caching enabled.

Disk \$252\$MDA0:, device type RAM Disk, is online, member of shadow set DSA0:.

|                  |     |                               |     |
|------------------|-----|-------------------------------|-----|
| Error count      | 0   | Shadow member operation count | 128 |
| Allocation class | 252 |                               |     |

Disk \$252\$MDA1:, device type RAM Disk, is online, member of shadow set DSA0:.

|                  |     |                               |     |
|------------------|-----|-------------------------------|-----|
| Error count      | 0   | Shadow member operation count | 157 |
| Allocation class | 252 |                               |     |

This example shows that a write bitmap exists for a shadow set, and that no write bitmap is active. If a shadow set supports write bitmaps, "device supports bitmaps" is displayed along with either "bitmaps active" or "no bitmaps active". If the device does not support write bitmaps, no message pertaining to write bitmaps is displayed.

11. \$ SHOW DEVICE/BITMAP DSA13

| Device | BitMap   | Size    | Percent   | Type of   | Master |
|--------|----------|---------|-----------|-----------|--------|
| Active |          |         |           |           |        |
| Name   | ID       | (Bytes) | Populated | Bitmap    | Node   |
| DSA13: | 00010007 | 8248    | 0.01%     | Minimerge | IPA    |
| Yes    |          |         |           |           |        |

This example shows a **SHOW DEVICE/BITMAP** display. In this example, the bitmap is an HBMM bitmap that is active on node IPA.

The **/BITMAP** qualifier is similar to the **/REBUILD** qualifier in that neither can be combined with most other **SHOW DEVICE** qualifiers. The **SHOW DEVICE/BITMAP** display can be brief or full; brief is the default. Use the **/FULL** qualifier to view the entire display.

If no bitmap is active (or the device is not mounted), no bitmap file ID is displayed. The phrase "no bitmaps active" is displayed.

12. \$ SHOW DEVICE/FULL EWA0

Device EWA0:, device type DEGXA, is online, network device, error logging is enabled, device is a template only.

|                          |          |                      |
|--------------------------|----------|----------------------|
| Error count              | 1        | Operations completed |
| 0                        |          |                      |
| Owner process            | " "      | Owner UIC            |
| [SYSTEM]                 |          |                      |
| Ownerprocess ID          | 00000000 | Dev Prot             |
| S:RWPL,O:RWPL,G,W        |          |                      |
| Reference count          | 0        | Default buffer size  |
| 512                      |          |                      |
| Current preferred CPU ID | 0        | Fastpath             |
| 1                        |          |                      |
| Current Interrupt CPU ID | 0        |                      |

Operating characteristics: Link up, Full duplex, Autonegotiation, Jumbo frames.

|                   |                   |                  |                   |
|-------------------|-------------------|------------------|-------------------|
| Speed (Mbits/sec) | 1000              |                  |                   |
| Def. MAC addr     | 00-D0-59-61-6A-B2 | Current MAC addr | 00-D0-59-61-6A-B2 |

This example shows information regarding the LAN template device EWA0. Only the template device displays the state of the link. In this example, the link is up.

13. SHOW DEVICE/FULL EIA4

Device EIA4:, device type i82559, is online, network device, error logging is enabled.

|             |   |                      |
|-------------|---|----------------------|
| Error count | 0 | Operations completed |
| 375225      |   |                      |

```
      Owner process          "NETACP"      Owner UIC
[SYSTEM]
      Owner process ID       39800425      Dev Prot
S:RWPL,O:RWPL,G,W
      Reference count        2             Default buffer size
1498

Operating characteristics: Full duplex, Autonegotiation.
      Speed (Mbits/sec)      100
      Def. MAC addr 00-08-02-AF-EC-D4      Current MAC addr
AA-00-04-00-CD-4D
      Protocol name          DECNET        Protocol type
60-03
```

This example show information regarding the LAN device EIA4. As this device is specific to a particular LAN protocol, information regarding that protocol is displayed; this information is not displayed for the template device in the previous example, as there is no protocol associated with the template service.

## SHOW DEVICES/SERVED

**SHOW DEVICES/SERVED** — Displays information on devices served by the mass storage control protocol (MSCP) server on this node. The **/SERVED** qualifier is required.

### Format

**SHOW DEVICES/SERVED**

### Description

The **SHOW DEVICES/SERVED** command displays information about the MSCP server and the devices it serves. This information is used mostly by system managers. The following message displays when the user issues a **SHOW DEVICE/SERVED** command when the tape server is not loaded:

```
%SHOW-E-TMSCPNOTLD, TMSCP-Server code not loaded
```

### Qualifiers

**/ALL**

This qualifier displays the information displayed by all of the qualifiers listed below except the **/OUTPUT** qualifier.

**/COUNT**

Displays the number of transfer operations completed, sorted by the size of the transfers, and the number of MSCP operations that have taken place since the MSCP server was started.

**/EXACT**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify a search string that must match the search string exactly and must be enclosed with quotation marks (" ").

If you specify the **/EXACT** qualifier without the **/SEARCH** qualifier, exact search mode is enabled when you set the search string with the Find (**E1**) key.

**/HIGHLIGHT[=*keyword*]**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify the type of highlighting you want when a search string is found. When a string is found, the entire line is highlighted. You can use the following keywords: BOLD, BLINK, REVERSE, and UNDERLINE. BOLD is the default highlighting.

**/HOST**

Displays the names of the processors that have MSCP served devices on line. The System Generation utility (SYSGEN) command MSCP/HOST determines how many hosts in the OpenVMS Cluster can connect to the MSCP server at one time.

**/OUTPUT=[*filespec*]**

Redirects output from your terminal to the specified file. If you do not specify a file, or if you do not use this qualifier, output is sent to SYS\$OUTPUT.

**/PAGE[=*keyword*]****/NOPAGE (default)**

Controls the display of device information on the screen.

You can use the following keywords with the **/PAGE** qualifier:

| Keyword           | Description                                                                               |
|-------------------|-------------------------------------------------------------------------------------------|
| CLEAR_SCREEN      | Clears the screen before each page is displayed.                                          |
| SCROLL            | Displays information one line at a time.                                                  |
| SAVE[= <i>n</i> ] | Enables screen navigation of information, where <i>n</i> is the number of pages to store. |

The **/PAGE=SAVE** qualifier allows you to navigate through screens of information. The **/PAGE=SAVE** qualifier stores up to 5 screens of up to 255 columns of information. When you use the **/PAGE=SAVE** qualifier, you can use the following keys to navigate through the information:

| Key Sequence                                                           | Description                                                 |
|------------------------------------------------------------------------|-------------------------------------------------------------|
| Up arrow key, <b>Ctrl/B</b>                                            | Scroll up one line.                                         |
| Down arrow key                                                         | Scroll down one line.                                       |
| Left arrow key                                                         | Scroll left one column.                                     |
| Right arrow key                                                        | Scroll right one column.                                    |
| Find ( <b>E1</b> )                                                     | Specify a string to find when the information is displayed. |
| Insert Here ( <b>E2</b> )                                              | Scroll right one half screen.                               |
| Remove ( <b>E3</b> )                                                   | Scroll left one half screen.                                |
| Select ( <b>E4</b> )                                                   | Toggle 80/132 column mode.                                  |
| Prev Screen ( <b>E5</b> )                                              | Get the previous page of information.                       |
| Next Screen ( <b>E6</b> ), <b>Return</b> , <b>Enter</b> , <b>Space</b> | Get the next page of information.                           |
| <b>F10</b> , <b>Ctrl/Z</b>                                             | Exit. (Some utilities define these differently.)            |
| Help ( <b>F15</b> )                                                    | Display utility help text.                                  |

| Key Sequence | Description                               |
|--------------|-------------------------------------------|
| Do (F16)     | Toggle the display to oldest/newest page. |
| Ctrl/W       | Refresh the display.                      |

The **/PAGE** qualifier is not compatible with the **/OUTPUT** qualifier.

## /RESOURCE

Displays information about the resources available to the MSCP server for use in processing I/O requests for the devices it serves.

You make these resources available by using the following system parameters: MSCP\_BUFFER, MSCP\_CREDITS, MSCP\_LOAD, and MSCP\_SERVE\_ALL.

See the *VSI OpenVMS Cluster Systems Manual* [<https://docs.vmssoftware.com/vsi-openvms-cluster-systems/>] or SYSGEN online help for more information.

## /SEARCH="string"

Use with the **/PAGE=SAVE** qualifier to specify a string that you want to find in the information being displayed. Quotation marks are required for the **/SEARCH** qualifier, if you include spaces in the text string.

You can also dynamically change the search string by pressing the Find key (E1) while the information is being displayed. Quotation marks are not required for a dynamic search.

## Examples

### 1. \$ SHOW DEVICES/SERVED

MSCP-Served Devices on BIAK 28-MAY-2001 13:48:01.32

| Device:     | Status | Total Size | Queue Requests |     | Hosts |
|-------------|--------|------------|----------------|-----|-------|
|             |        |            | Current        | Max |       |
| \$11\$DUA8  | Online | 2376153    | 0              | 2   | 6     |
| \$11\$DUA9  | Avail  | 2376153    | 0              | 0   | 0     |
| \$11\$DUA10 | Online | 2376153    | 0              | 2   | 8     |
| \$11\$DUA11 | Online | 2376153    | 0              | 2   | 7     |
| \$11\$DUA13 | Online | 2376153    | 0              | 2   | 7     |
| \$11\$DUA14 | Avail  | 2376153    | 0              | 0   | 0     |
| \$11\$DUA16 | Avail  | 2376153    | 0              | 0   | 0     |
| \$11\$DUA17 | Avail  | 2376153    | 0              | 0   | 0     |
| \$11\$DUA18 | Online | 2376153    | 0              | 1   | 4     |
| \$11\$DUA19 | Online | 2376153    | 0              | 4   | 7     |
| \$11\$DUA20 | Online | 2376153    | 0              | 1   | 7     |
| \$11\$DUA21 | Online | 2376153    | 0              | 17  | 12    |

This example shows the output generated by the command **SHOW DEVICES/SERVED**. The first column in the display shows the names of the devices that are served by the MSCP server. The second column shows the status of the devices. The third column shows the size, in blocks, of the device.

The Queue Requests columns show the number of I/O requests currently awaiting processing by that device and the maximum number of I/O requests that have ever been concurrently awaiting processing by that device. The last column in the display shows the number of hosts that have the device on line.

## 2. \$ SHOW DEVICES/SERVED/COUNT

MSCP-Served Devices on BIAK 28-MAY-2001 13:49:52.41

```

.
.
.
Request Count:
  0-7:    951154      32-39:    2168      88-103:    1618
  8-15:   197224      40-55:    2543      104-127:    189
 16-23:   137707      56-71:    8343
 24-31:     982      72-87:    141

Operations Count:
ABORT          0    ERASE          22772    READ          1042206
ACCESS         0    FLUSH           0    REPLACE         0
AVAILABLE     611    GET COM STS      0    SET CTL CHR     176
CMP CTL DAT    0    GET UNT STS  4026024    SET UNT CHR     3630
CMP HST DAT    0    ONLINE          427    WRITE          259953
Total          5355799

```

This example shows the information displayed by the **SHOW DEVICES/SERVED/COUNT** command. The numbers to the left of the colon (:), separated by a hyphen (-), are the size, in pages, of the requests. The numbers to the right of the colon are the number of requests of that size that have been processed by the MSCP server.

The section of the display headed by the label Operations Count shows the number of times the MSCP server has performed the MSCP operations listed. In the example, this MSCP server has performed 176 set-controller-characteristics (SET CTL CHR) operations, and has performed 3630 set-unit-characteristics (SET UNT CHR) operations.

## 3. \$ SHOW DEVICES/SERVED/RESOURCE

MSCP-Served Devices on BIAK 28-MAY-2001 13:51:32.01

```

.
.
.
Resources:      Total      Free      In Use
  Buffer Area:   400      400         0
  I/O Packets:   0        0
.
.
.
          Current      Maximum
  Buffer Wait:    0        0

```

This example shows the information displayed by the **SHOW DEVICES/SERVED/RESOURCE** command. The Total column shows the total number of pages in the buffer area and in the number of I/O-request packets set aside for use by the MSCP server. The Free column shows the number of pages in the buffer and the number of I/O-request packets that are available for use.

The In Use column shows the number of pages within the buffer area that are in use.

The line labeled Buffer Wait shows the number of I/O requests that are currently waiting for buffer space to become available for their use, and the maximum number of I/O requests that have waited concurrently to obtain a buffer.

## 4. (wide)\$ SHOW DEVICES/SERVED/HOST

MSCP-Served Devices on BIAK 28-NOV-2001 13:54:41.99

```

.

```

```

.
.
Host:                               Queue Requests
                                Current    Max    Devices
IPL31      25-MAY-2001 21:44:06.44      0      1      0
DELAND     25-MAY-2001 21:44:09.98      0      1      0
HEAVEN     25-MAY-2001 22:03:15.67      0      7     10
VIVA       26-MAY-2001 09:44:11.96      0      1      0
.
.
.

```

This example shows the information displayed by the **SHOW DEVICES/SERVED/HOST** command. The first column contains the names of the hosts that have class drivers connected to the MSCP server. The next column contains the times at which these connections were made.

The columns under the heading Queue Requests show the number of requests the MSCP server currently has outstanding for I/O activity on the devices it serves, the maximum number of such requests that have been outstanding at one time, and the number of MSCP server devices that the listed hosts have on line.

#### 5. \$ SHOW DEVICES/SERVED

```

      MSCP-Served Devices on HEN  3-DEC-2001 09:09:08.49
                                Queue Requests
Device:      Status    Total Size    Current    Max    Hosts
254$DJB1     Avail          0          0      0      0
254$DUA2     Online    1216665          0      0      1
254$DUA4006  Avail          0          0      0      0

      TMSCP-Served Devices on HEN  3-DEC-2001 09:09:08.74
                                Queue Requests
Device:      Status    Position     Current    Max    Hosts
90$MUA7      Avail          0          0      0      0
90$MUA8      Avail          0          0      0      0
90$MUA50     Online    3804          0      0      0

```

This example displays the output of the **SHOW DEVICES/SERVED** command from a node that has both MSCP server and TMSCP server devices. In the display, the third column for MSCP server disk devices shows the size of the disk device. The same column for TMSCP server device shows the location where each tape is currently positioned.

## SHOW DISPLAY

**SHOW DISPLAY** — Indicates the node where output from a DECwindows application will be displayed.

### Format

**SHOW DISPLAY** [*display-device*]

### Parameter

*display-device*

Refers to the display-device parameter specified with the **SET DISPLAY** command. If you are directing application output to multiple workstations in the same session, you can use logical names to point to each workstation. Using the **SHOW DISPLAY** command, you can specify this logical name as the display-device parameter to see where application output will be displayed.

If you do not specify a display-device string, the logical name DECW\$DISPLAY is used.

## Description

DECwindows gives you the ability to run applications across a network. The **SET DISPLAY** command enables you to direct the output of client applications across the network to an alternate workstation (X display server) for viewing. For example, the **SET DISPLAY** command allows you to:

- Redirect the output from local client applications to a remote workstation for display.
- Redirect the output from remote client applications to your local workstation for display. Although the application runs on another processor, it looks the same as any other application running locally on your workstation.

By running applications on a remote processor for local display on your workstation, you can take advantage of larger computers that might be better suited to a specific computing task. By default, applications running on your workstation are displayed on your workstation.

You use the **SET DISPLAY** command to direct the output from applications to other workstations. The **SHOW DISPLAY** command lets you see where the output from these applications will be displayed.

Sample output from the **SHOW DISPLAY** command looks like the following:

```
Device:      WSA2:   [super]
Node:        0
Transport:   LOCAL
Server:      0
Screen:      0
```

The description of each item follows:

- Device is your workstation device. A new WSA $n$  device is created each time you use the **SET DISPLAY/CREATE** command.
- Node is the network system on which the output from applications is displayed. When you are running and displaying applications on your node, Node is 0, which is the standard shorthand notation for representing your node.
- Transport refers to the mechanism, for example, DECNET or LOCAL, that passes information between the application, the client, and the server. The server sends input from the user to the application and output from the application to the display.
- Server is 0.
- Screen is 0.

On DECwindows workstations, the Session Manager creates a default workstation device for use by DECwindows processes (like DECterm). When you use the **SET HOST** command to connect to a remote node, no workstation device is created for that process and DECW\$DISPLAY is not defined. You must specifically create new display devices with the **SET DISPLAY/CREATE** command.

If no definition for `DECW$DISPLAY` exists, entering the **SHOW DISPLAY** command returns an error.

Qualifiers to the **SHOW DISPLAY** command enable you to display properties related to the display device and extract authorization information, as described in the following sections.

## Displaying Named Properties (Alpha/Integrity servers Only)

Named property values are designed to store configuration information associated with the display device, such as the network address of a session manager. By using the **/ALL** and **/SYMBOLS** qualifiers, you can display all the named properties related to the display device and use them to define one or more global symbols.

See the description of the [SET DISPLAY](#) command for more information.

## Extracting Authorization Information (Alpha/Integrity servers Only)

If the display device is connected to a workstation that is using either Magic Cookie or Kerberos access control, you can use the **/EXTRACT** qualifier to obtain authorization information related to the display device from the current X authority file.

See the description of the [SET DISPLAY](#) command for more information.

## Qualifiers

### **/ALL (Alpha/Integrity servers only)**

Displays all named properties and their values related to the current display device.

### **/EXTRACT (Alpha/Integrity servers only)**

Obtains the authorization data for the display device and writes that data to `SYSS$OUTPUT`. The authorization data is obtained from the current X authority file and is in the format expected by the X Authority utility (`xauth`).

Note that when using an LBX proxy server, the extracted authorization information references the address of the proxy server and not the X display server.

Do not use the **/EXTRACT** qualifier with any other **SHOW DISPLAY** qualifier.

See the description of the [SET DISPLAY](#) command for more information.

### **/QUOTA (Alpha/Integrity servers only)**

Displays the current name count and data space quota values for the display device. This display includes the set limit and the amount of space currently available for use.

### **/SYMBOLS (Alpha/Integrity servers only)**

Defines one or more global DCL symbols for each property displayed by the **SHOW DISPLAY** command. You can then use these property symbols in DCL command procedures.

Each global symbol name follows the form:

`DECW$DISPLAY_name`

The following are the symbols for predefined properties:

- DECW\$DISPLAY\_NODE
- DECW\$DISPLAY\_TRANSPORT
- DECW\$DISPLAY\_SCREEN
- DECW\$DISPLAY\_SERVER
- DECW\$DISPLAY\_XAUTH

Note that symbols for user-defined properties have a double underscore in the name. For example, the user-defined symbol for the value DISK\$USER:[JONES] would be defined as follows:

```
$ SHOW SYMBOL DECW$DISPLAY*

DECW$DISPLAY_NODE == "101.124.99.119"
DECW$DISPLAY_SCREEN == "0"
DECW$DISPLAY_SERVER == "0"
DECW$DISPLAY_TRANSPORT == "TCPIP"
DECW$DISPLAY_XAUTH == "DISK$USER:[SMITH]SERVER1.DECW$XAUTH"
DECW$DISPLAY__JONES == "DISK$USER:[JONES]"
```

If a symbol name or value exceeds or violates any DCL limits or naming conventions, the symbol is not set and an error message is displayed.

If the display device uses a proxy server, the symbols DECW\$DISPLAY\_NODE, DECW\$DISPLAY\_TRANSPORT, and DECW\$DISPLAY\_SERVER reflect values associated with the proxy server and not the X display server.

### **/VALUES=(*property-name*[,...]) (Alpha/Integrity servers only)**

Displays the value for the specified property. If the value consists of one or more items, they are displayed as a comma-delimited list.

## **Examples**

```
1. $ SHOW DISPLAY
   Device:      WSA1:  [super]
   Node:        0
   Transport:   LOCAL
   Server:      0
   Screen:      0

$ SET DISPLAY/CREATE/NODE=ZEPHYR
$ SHOW DISPLAY
   Device:      WSA2:  [super]
   Node:        ZEPHYR
   Transport:   DECNET
   Server:      0
   Screen:      0
$ SPAWN/NOWAIT/INPUT=NL: RUN SYS$SYSTEM:DECW$CLOCK
```

In this example, you are logged in to your workstation, here referred to as node 0 (0 is the standard shorthand notation for representing your node.) You want to run the DECwindows Clock on your workstation and display it on another node, ZEPHYR.

Assuming you are authorized to display applications on ZEPHYR, you redirect the application's output to ZEPHYR with the **SET DISPLAY** command and enter the **SHOW DISPLAY** command to verify the location of the redirected display. You then run Clock. Note that a new workstation display device, WSA2, is created when you enter the **SET DISPLAY/CREATE** command.

```
2. $ SET DISPLAY/CREATE/VALUE=(NAME=DECW$SESSION_MANAGER,-
   _$ SET="tcpip/zephyr:9510")
   $ SHOW DISPLAY/SYMBOLS/ALL
      Device:      WSA23:  [super]
      Node:        0
      Transport:   DECNET
      Server:      0
      Screen:      0
      User-defined values:
        "DECW$SESSION_MANAGER" = "tcpip/zephyr:9510"
   $ SHOW SYMBOL DECW$DISPLAY__DECW$SESSION_MANAGER
      DECW$DISPLAY__DECW$SESSION_MANAGER == "tcpip/zephyr:9510"
```

In this example, you create a display device, and set the DECW\$SESSION\_MANAGER property to the network address of a session manager on remote node ZEPHYR using port number 9510. The **SHOW DISPLAY/SYMBOLS** command then defines a DCL symbol for the port value.

## SHOW ENTRY

**SHOW ENTRY** — Displays information about a user's batch and print jobs or about specific job entries. Requires read (R) access to the queue.

### Format

**SHOW ENTRY** [*entry-number*[, ...]], [*job-name*[, ...]]

### Parameters

*entry-number*[, ...]

Specifies the entry number of the job you want displayed. If no entry number or job name is specified, all your own jobs (or those owned by the user specified with the **/USER\_NAME** qualifier) are displayed.

*job-name*[, ...]

Specifies the name of the jobs you want displayed. The asterisk (\*) and the percent sign (%) wildcard characters are allowed. If no job name or entry number is specified, all your own jobs (or those owned by the user specified with the **/USER\_NAME** qualifier) are displayed.

### Description

The **SHOW ENTRY** command displays information about a user's batch and print jobs or about specific job entries.

The information displayed includes the entry number, the job name, the owner, job size in blocks (for print jobs), and the job status. The name, status, and queue type of the queue in which the job is located are also displayed.

If you are only interested in information about your own batch and print jobs, the **SHOW ENTRY** command produces a better display than the **SHOW QUEUE** command. Because the **SHOW QUEUE** command displays queue information regardless of whether your jobs are in these queues, you must scan the display to locate your jobs. By contrast, the **SHOW ENTRY** command displays only information relevant to your jobs (or those owned by the user you specify with the **/USER\_NAME** qualifier.) If the **/USER\_NAME** qualifier is not specified, information about your own jobs is displayed.

## Qualifiers

### **/BATCH**

Selects batch jobs for display.

### **/BRIEF (default)**

Displays the following information for each job: entry number, job name, user name, job size in blocks (for print jobs), job status, queue name, queue status, and queue type. The **/FULL** and **/FILES** qualifiers override the **/BRIEF** qualifier.

Specify the **/FULL** qualifier to obtain more job information.

### **/BY\_JOB\_STATUS[=(keyword,...)]**

Selects for display only those jobs with the specified status. Specify the status with one or more of the following keywords:

| Keyword       | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |                                  |
|---------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------|
| EXECUTING     | Requests the display of jobs in any of the following states:                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |                                  |
|               | ABORTING<br>EXECUTING<br>PRINTING<br>PROCESSING                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    | STALLED<br>STARTING<br>SUSPENDED |
|               | ABORTING means that the job is halting prior to normal completion and will not continue processing. A SUSPENDED state means that the job stopped during processing, but should continue when the cause of the SUSPENDED state is resolved. A STALLED or SUSPENDED state means that the job stopped during processing, but should continue when the cause of the STALLED or SUSPENDED state is resolved. PROCESSING is the executing state for server queues. PRINTING is the executing state for printer and terminal queues. STARTING means the job is beginning to be processed. |                                  |
| HOLDING       | Requests the display of jobs on hold. Holding status indicates that the job is being held in the queue indefinitely.                                                                                                                                                                                                                                                                                                                                                                                                                                                               |                                  |
| PENDING       | Requests the display of jobs with pending status. Pending status indicates that the job is waiting its turn to execute.                                                                                                                                                                                                                                                                                                                                                                                                                                                            |                                  |
| RETAINED      | Requests the display of jobs retained in the queue after execution. Retained status indicates that the job has completed but remains in the queue.                                                                                                                                                                                                                                                                                                                                                                                                                                 |                                  |
| TIMED_RELEASE | Requests the display of jobs on hold until a specified time. Timed-release status indicates that the job is being held in the queue for execution at a specified time.                                                                                                                                                                                                                                                                                                                                                                                                             |                                  |

If no keyword is specified, the **/BY\_JOB\_STATUS** qualifier displays the status of all jobs.

**/DEVICE[=(keyword,...)]**

Selects for display only those print jobs in the queue types specified. Specify the queue type with one or more of the following keywords:

| Keyword  | Description                                      |
|----------|--------------------------------------------------|
| PRINTER  | Requests the display of jobs in print queues.    |
| SERVER   | Requests the display of jobs in server queues.   |
| TERMINAL | Requests the display of jobs in terminal queues. |

If no keyword is specified, the **/DEVICE** qualifier displays all jobs in printer, terminal, or server queues.

**/EXACT**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify a search string that must match the search string exactly and must be enclosed with quotation marks (" ").

If you specify the **/EXACT** qualifier without the **/SEARCH** qualifier, exact search mode is enabled when you set the search string with the Find (**F1**) key.

**/FILES**

Adds to the default display the list of full file specifications for each file in each job. The **/FILES** qualifier overrides the default **/BRIEF** qualifier.

**/FULL**

Displays the following information for each job: entry number, job name, user name, job status, full file specification associated with each job, date and time of submission, settings specified for the job, queue name, queue status, and queue type.

The **/FULL** qualifier overrides the default **/BRIEF** qualifier.

**/GENERIC**

Selects for display only those jobs contained in generic queues. A generic queue holds jobs of a particular type (for example, batch or line printer jobs) and directs them to execution queues for processing.

**/HIGHLIGHT[=keyword]**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify the type of highlighting you want when a search string is found. When a string is found, the entire line is highlighted. You can use the following keywords: BOLD, BLINK, REVERSE, and UNDERLINE. BOLD is the default highlighting.

**/OUTPUT[=filespec]****/NOOUTPUT**

Controls where the output of the **SHOW ENTRY** command is sent. By default, the output is sent to the current SYS\$OUTPUT device (usually your terminal). To send the output to a file, use the **/OUTPUT** qualifier followed by a file specification.

The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification. If you enter a partial file specification (for example, specifying only a directory), **SHOW** is the default file name and **.LIS** is the default file type.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

**/PAGE[=keyword]**  
**/NOPAGE (default)**

Controls the display of information on the screen.

You can use the following keywords with the **/PAGE** qualifier:

| Keyword             | Description                                                                               |
|---------------------|-------------------------------------------------------------------------------------------|
| <b>CLEAR_SCREEN</b> | Clears the screen before each page is displayed.                                          |
| <b>SCROLL</b>       | Displays information one line at a time.                                                  |
| <b>SAVE[= n]</b>    | Enables screen navigation of information, where <i>n</i> is the number of pages to store. |

The **/PAGE=SAVE** qualifier allows you to navigate through screens of information. The **/PAGE=SAVE** qualifier stores up to 5 screens of up to 255 columns of information. When you use the **/PAGE=SAVE** qualifier, you can use the following keys to navigate through the information:

| Key Sequence                                  | Description                                                 |
|-----------------------------------------------|-------------------------------------------------------------|
| <b>Up</b> arrow key, <b>Ctrl/B</b>            | Scroll up one line.                                         |
| <b>Down</b> arrow key                         | Scroll down one line.                                       |
| <b>Left</b> arrow key                         | Scroll left one column.                                     |
| <b>Right</b> arrow key                        | Scroll right one column.                                    |
| <b>Find (E1)</b>                              | Specify a string to find when the information is displayed. |
| <b>Insert Here (E2)</b>                       | Scroll right one half screen.                               |
| <b>Remove (E3)</b>                            | Scroll left one half screen.                                |
| <b>Select (E4)</b>                            | Toggle 80/132 column mode.                                  |
| <b>Prev Screen (E5)</b>                       | Get the previous page of information.                       |
| <b>Next Screen (E6), Return, Enter, Space</b> | Get the next page of information.                           |
| <b>F10, Ctrl/Z</b>                            | Exit. (Some utilities define these differently.)            |
| <b>Help (F15)</b>                             | Display utility help text.                                  |
| <b>Do (F16)</b>                               | Toggle the display to oldest/newest page.                   |
| <b>Ctrl/W</b>                                 | Refresh the display.                                        |

The **/PAGE** qualifier is not compatible with the **/OUTPUT** qualifier.

**/SEARCH="string"**

Use with the **/PAGE=SAVE** qualifier to specify a string that you want to find in the information being displayed. Quotation marks are required for the **/SEARCH** qualifier, if you include spaces in the text string.

You can also dynamically change the search string by pressing the Find key (**F1**) while the information is being displayed. Quotation marks are not required for a dynamic search.

### **/USER\_NAME=username**

Selects for display those jobs owned by the specified user. If the **/USER\_NAME** qualifier is not specified, information about your own jobs is displayed. The name must be 1 to 12 alphanumeric characters.

### **/WRAP**

#### **/NOWRAP (default)**

Use with the **/PAGE=SAVE** qualifier to limit the number of columns to the width of the screen and to wrap lines that extend beyond the width of the screen to the next line.

The **/NOWRAP** qualifier extends lines beyond the width of the screen and can be seen when you use the scrolling (left and right) features provided by the **/PAGE=SAVE** qualifier.

## Examples

1. \$ SHOW ENTRY/BY\_JOB\_STATUS=RETAINED

| Entry | Jobname                                         | Username | Blocks | Status                 |
|-------|-------------------------------------------------|----------|--------|------------------------|
| 422   | FORECAST                                        | JONES    |        | Retained on completion |
|       | On stopped generic batch queue CLUSTER_BATCH    |          |        |                        |
|       | Completed 21-DEC-2001 16:18 on queue NODE_BATCH |          |        |                        |

In this example, the **SHOW ENTRY** command displays a job entry that was retained on completion.

2. (wide)

\$ SHOW ENTRY/FULL S\*

| Entry | Jobname                                                 | Username | Blocks | Status                  |
|-------|---------------------------------------------------------|----------|--------|-------------------------|
| 625   | STAFF                                                   | ESTES    | 112    | Pending (queue stopped) |
|       | On stopped printer queue LN01\$PRINT                    |          |        |                         |
|       | Submitted 19-DEC-2001 12:14 /FORM=LN01\$PORTRAIT        |          |        |                         |
|       | (stock=DEFAULT) /NOTIFY /PRIORITY=100                   |          |        |                         |
|       | File: _DKA1:[ESTES]STAFF.DIS;3                          |          |        |                         |
| 629   | SEARCH                                                  | ESTES    | 94     | Printing                |
|       | On printer queue LINE\$PRINT                            |          |        |                         |
|       | Submitted 19-DEC-2001 12:16 /FORM=DEFAULT /NOTIFY       |          |        |                         |
|       | /PRIORITY=100 /COPIES=2 /NOFEED /PASSALL                |          |        |                         |
|       | File: _DKA1:[ESTES.DAILY]SEARCH.TXT;2 (printing copy 2) |          |        |                         |

In this example, the **SHOW ENTRY** command displays the current job name entries beginning with the letter "S" owned by ESTES on all queues. The **/FULL** qualifier lists the submission information, the full file specification, and the current settings for the job.

Note that entry 629 specified the **/COPIES**, **/NOFEED**, and **/PASSALL** qualifiers to the **PRINT** command. The **/NOFEED** qualifier suppresses automatic form feeds. The **/PASSALL** qualifier suppresses formatting (including form feeds and carriage return characters) performed by the print symbiont.

3. \$ SUBMIT ASSIGNMENTS.COM

```
Job ASSIGNMENTS.COM (queue SYS$BATCH, entry 199) pending
.
.
.
$
SHOW ENTRY 199/FULL
Entry      Jobname      Username      Status
-----
199      ASSIGNMENTS      JONES      Executing
Submitted 19-DEC-2001 08:36 /KEEP /NOLOG/ NOPRINT
/PRIORITY=100
File: DUA2:[JONES]ASSIGNMENTS.COM;34
```

In this example, JONES submits ASSIGNMENTS.COM for batch processing. Because JONES does not specify a specific queue, the job is entered into the generic SYS\$BATCH queue to await processing. After performing other tasks, JONES checks the job status and sees that the file is now executing. Note that the job entry migrated from a generic to an execution batch queue and that JONES was able to check the job status without knowing the specific batch queue name. If the user did not specify an entry number, all jobs would have been displayed.

## SHOW ENTROPY (x86-64 only)

SHOW ENTROPY (x86-64 only) — Displays information about derived entropy sources and the status of hardware entropy sources.

### Syntax

**SHOW ENTROPY**

### Description

The **SHOW ENTROPY** command displays information about derived entropy sources and the status of hardware entropy sources.

---

### Note

Not all listed sources of entropy may be implemented. In particular, hardware sources of entropy may vary by host hardware and hypervisor.

---

### Qualifiers

**/OUTPUT[=*filespec*]**  
**/NOOUTPUT**

Controls where the output of the **SHOW ENTROPY** command is sent. By default, the output is sent to the current SYS\$OUTPUT device (usually your terminal). To send the output to a file, use the **/OUTPUT** qualifier followed by a file specification.

The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification. If you enter a partial file specification (for example, specifying only a directory), SHOW is the default file name and .LIS is the default file type.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

## /SYMBOLS

### /NOSYMBOLS (default)

Define symbols to hold information about the availability of hardware sources of entropy. The symbol names are as follows:

|                          |                                                                                                                                                                                                                                                                                                                            |
|--------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| SHOW\$RDRAND_IN_HARDWARE | TRUE if the host hardware supports the RDRAND instruction as determined by the results of the CPUID instruction. Otherwise the symbol will be set to FALSE.                                                                                                                                                                |
| SHOW\$RDRAND_AVAILABLE   | TRUE if the host hardware supports the RDRAND instruction, and an attempt to execute the instruction returned success. Otherwise the symbol will be set to FALSE. Not all hypervisor configurations support the RDRAND instruction even if the host does. Consult the documentation for your hypervisor regarding support. |

## Example

```
$ SHOW ENTROPY/SYMBOLS
RANDOM_SOURCES:      FFFFFFFF
Enabled Sources:    000007FF
Disabled Sources:   FFFFF800
```

Sources enabled by RANDOM\_SOURCES:

```
Bit   Description
---   -
0     Cached Random Data
1     Device Attachment
2     Per-CPU counters
3     Lock Manager
4     Cluster events
5     Tunnel sources
6     Ethernet Packets
7     Device Interrupts
8     Software Interrupts
9     File System
10    Pool Packet Deallocation
16    RDRAND Instruction (disabled)
17    VIRTIO Random Device (disabled)
```

System hardware supports the RDRAND instruction.  
The hypervisor does not support the RDRAND instruction.

```
$ SHOW SYMBOL SHOW*
SHOW$RDRAND_AVAILABLE = "FALSE"
SHOW$RDRAND_IN_HARDWARE = "TRUE"
```

## SHOW ERROR

**SHOW ERROR** — Displays the error count for all devices with error counts greater than zero.

## Format

**SHOW ERROR**

## Parameters

None.

## Qualifiers

### **/EXACT**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify a search string that must match the search string exactly and must be enclosed with quotation marks (" ").

If you specify the **/EXACT** qualifier without the **/SEARCH** qualifier, exact search mode is enabled when you set the search string with the Find (**E1**) key.

### **/FULL**

Displays the error count for all devices, including those with no errors (The error count is either zero or a number greater than zero).

### **/HIGHLIGHT[=*keyword*]**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify the type of highlighting you want when a search string is found. When a string is found, the entire line is highlighted. You can use the following keywords: BOLD, BLINK, REVERSE, and UNDERLINE. BOLD is the default highlighting.

### **/OUTPUT[=*filespec*]**

#### **/OUTPUT=SYS\$OUTPUT (default)**

Specifies the file to which the display is written. By default, the display is written to the current SYS\$OUTPUT device.

If you enter the **/OUTPUT** qualifier with a partial file specification (for example, specifying only a directory), SHOW is the default file name and .LIS the default file type. The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

### **/PAGE[=*keyword*]**

#### **/NOPAGE (default)**

Controls the display of error information on the screen.

You can use the following keywords with the **/PAGE** qualifier:

| Keyword      | Description                                      |
|--------------|--------------------------------------------------|
| CLEAR_SCREEN | Clears the screen before each page is displayed. |
| SCROLL       | Displays information one line at a time.         |

| Keyword           | Description                                                                               |
|-------------------|-------------------------------------------------------------------------------------------|
| SAVE[= <i>n</i> ] | Enables screen navigation of information, where <i>n</i> is the number of pages to store. |

The **/PAGE=SAVE** qualifier allows you to navigate through screens of information. The **/PAGE=SAVE** qualifier stores up to 5 screens of up to 255 columns of information. When you use the **/PAGE=SAVE** qualifier, you can use the following keys to navigate through the information:

| Key Sequence                                                           | Description                                                 |
|------------------------------------------------------------------------|-------------------------------------------------------------|
| <b>Up</b> arrow key, <b>Ctrl/B</b>                                     | Scroll up one line.                                         |
| <b>Down</b> arrow key                                                  | Scroll down one line.                                       |
| <b>Left</b> arrow key                                                  | Scroll left one column.                                     |
| <b>Right</b> arrow key                                                 | Scroll right one column.                                    |
| Find ( <b>E1</b> )                                                     | Specify a string to find when the information is displayed. |
| Insert Here ( <b>E2</b> )                                              | Scroll right one half screen.                               |
| Remove ( <b>E3</b> )                                                   | Scroll left one half screen.                                |
| Select ( <b>E4</b> )                                                   | Toggle 80/132 column mode.                                  |
| Prev Screen ( <b>E5</b> )                                              | Get the previous page of information.                       |
| Next Screen ( <b>E6</b> ), <b>Return</b> , <b>Enter</b> , <b>Space</b> | Get the next page of information.                           |
| <b>F10</b> , <b>Ctrl/Z</b>                                             | Exit. (Some utilities define these differently.)            |
| Help ( <b>F15</b> )                                                    | Display utility help text.                                  |
| Do ( <b>F16</b> )                                                      | Toggle the display to oldest/newest page.                   |
| <b>Ctrl/W</b>                                                          | Refresh the display.                                        |

The **/PAGE** qualifier is not compatible with the **/OUTPUT** qualifier.

### **/SEARCH="string"**

Use with the **/PAGE=SAVE** qualifier to specify a string that you want to find in the information being displayed. Quotation marks are required for the **/SEARCH** qualifier, if you include spaces in the text string.

You can also dynamically change the search string by pressing the Find key (**E1**) while the information is being displayed. Quotation marks are not required for a dynamic search.

### **/WRAP**

#### **/NOWRAP (default)**

Use with the **/PAGE=SAVE** qualifier to limit the number of columns to the width of the screen and to wrap lines that extend beyond the width of the screen to the next line.

The **/NOWRAP** qualifier extends lines beyond the width of the screen and can be seen when you use the scrolling (left and right) features provided by the **/PAGE=SAVE** qualifier.

## Example

```
$ SHOW ERROR
```

| Device                          | Error Count |
|---------------------------------|-------------|
| PNA0:                           | 2           |
| \$1\$DGA22: (AJAM PGA, ALPHAB)  | 1           |
| \$11\$DUA1915: (HSJ018, HSJ019) | 14          |

The **SHOW ERROR** command displays the error count for all devices with error counts greater than zero.

## SHOW FASTPATH (Alpha/Integrity servers Only)

**SHOW FASTPATH** — Displays fast path port assignment and usage. **SHOW FASTPATH** is useful for evaluating the distribution of interrupts among the various CPUs in complex configurations.

### Format

**SHOW FASTPATH**

### Qualifiers

**/CPU=*n*[,...]**

Requests fast path information for one or more specific CPUs. By default, information is displayed for all CPUs.

**/OUTPUT[=*filename*]**

**/NOOUTPUT**

Controls where output from the command is sent. If you omit the **/OUTPUT** qualifier or omit the file specification with the qualifier, the display is written to the current SYSS\$OUTPUT device by default. If you enter the **/NOOUTPUT** qualifier, output is suppressed.

### Examples

1. \$ SHOW FASTPATH

```
Fast Path preferred CPUs on NODE1 23-MAY-2004 16:47:58.10
HPE rx2600 (900MHz/1.5MB) with 2 CPUs
```

| Device: | Fastpath CPU: |
|---------|---------------|
| PKA0    | 1             |
| PEA0    | 0             |
| PKB0    | 0             |
| EIA0    | 0             |
| EWA0    | 1             |

OpenVMS TCP/IP is currently running on CPU 1

This example shows all the devices on NODE1 and the CPUs to which they are assigned.

2. \$ SHOW FASTPATH/CPU=(5,7,9)

```
Fast Path preferred CPUs on NODE2 23-MAY-2004 09:50:55.85
HPE AlphaServer GS140 6/525 with 6 CPUs
```

| Device: | Fastpath CPU: |
|---------|---------------|
| PKB0    | 7             |
| PKD0    | 5             |
| EBA0    | 7             |
| EWB0    | 7             |
| EWD0    | 5             |
| PGA0    | 9             |

OpenVMS Lock Manager is currently running on CPU 5

This example shows all the devices on NODE2 that are assigned to CPUs 5, 7, and 9.

## SHOW IMAGE (Alpha/Integrity servers Only)

**SHOW IMAGE** — Displays information about the specified Integrity servers image file. This command can be executed on an Alpha or Integrity server system, but it is designed only to display attributes of Integrity images. These attributes can be modified using the **SET IMAGE** command.

### Format

**SHOW IMAGE** *image-filespec*

### Parameter

*image-filespec*

Specifies the name of an OpenVMS Integrity servers image file whose attributes you want to display. The asterisk (\*) and percent sign (%) wildcard characters are allowed in the file specification. If you omit the file type extension, the default file type .EXE is applied.

### Description

Displays information about an Integrity servers image file. The information displayed includes the image identification, the linker identification, and information indicating whether the image has been modified since the original link.

### Qualifier

**/OUTPUT**[=*file-spec*]

Writes the **SHOW IMAGE** output to a specified file rather than to the current SYS\$OUTPUT device. If you specify the **/OUTPUT** qualifier without a file specification, the output is directed to SYS\$OUTPUT. If you omit the file type in the file specification, the default file type is .LIS. If you specify a file type and omit the file name, the default file name is SHOW. No wildcard characters are allowed in the file specification.

**/PAGE**[=*keyword*]

**/NOPAGE** (default)

Controls the display of **SHOW IMAGE** information on the screen.

You can use the following keywords with the **/PAGE** qualifier:

| Keyword           | Description                                                                               |
|-------------------|-------------------------------------------------------------------------------------------|
| CLEAR_SCREEN      | Clears the screen before each page is displayed.                                          |
| SCROLL            | Displays information one line at a time.                                                  |
| SAVE[= <i>n</i> ] | Enables screen navigation of information, where <i>n</i> is the number of pages to store. |

The **/PAGE** qualifier is not compatible with the **/OUTPUT** qualifier.

The **/PAGE=SAVE** qualifier allows you to navigate through screens of information. The **/PAGE=SAVE** qualifier can store up to 5 screens of up to 255 columns of information. When you use the **/PAGE=SAVE** qualifier, you can use the following keys to navigate through the output:

| Key Sequence                                         | Description                                                 |
|------------------------------------------------------|-------------------------------------------------------------|
| Up arrow key, <b>Ctrl/B</b>                          | Scroll up one line.                                         |
| Down arrow key                                       | Scroll down one line.                                       |
| Left arrow key                                       | Scroll left one column.                                     |
| Right arrow key                                      | Scroll right one column.                                    |
| Find ( <b>E1</b> )                                   | Specify a string to find when the information is displayed. |
| Insert Here ( <b>E2</b> )                            | Scroll right one half screen.                               |
| Remove ( <b>E3</b> )                                 | Scroll left one half screen.                                |
| Select ( <b>E4</b> )                                 | Toggle 80/132 column mode.                                  |
| Prev Screen ( <b>E5</b> )                            | Get the previous page of information.                       |
| Next Screen ( <b>E6</b> ),                           | Get the next page of information.                           |
| Return, Enter, Space, <b>F10</b> , and <b>Ctrl/Z</b> | Exit. (Some utilities define these differently.)            |
| Help ( <b>F15</b> )                                  | Display utility help text.                                  |
| Do ( <b>F16</b> )                                    | Toggle the display to oldest/newest page.                   |
| <b>Ctrl/W</b>                                        | Refresh the display.                                        |

## Examples

- ```
$ SHOW IMAGE PATCH
Show Image Version 1.2                      29-SEP-2004 07:52:08.41
WORK1:[SWEENEY.CLIUTL]PATCH.EXE;65
This is an OpenVMS IA64 (Elf format) executable image file

Image Identification Information

Image name: PATCH
Global Symbol Table name: PATCH
Image file identification: X-6
Image build identification: <unavailable>
Link identification: Linker T02-14
Link Date/Time: 28-SEP-2004 07:49:17.57
Patch Date/Time: Never
Manipulation Date/Time: 29-SEP-2004 07:51:58.73
Image Dynamic Data Version: 1.1
```

Image Completion Code Value: SUCCESS State: Original

Image Link Flags state: Manipulated

Current Image Flags -----	Original Link Flags -----
IMGSTA	CALL_DEBUG
MAIN	IMGSTA
TBK_IN_IMG	MAIN
DBG_IN_IMG	TBK_IN_IMG
DBG_IN_IMG	
Image Link Flag -----	Description -----
CALL_DEBUG	: Call debugger
IMGSTA	: Call SYS\$IMGSTA
MAIN	: Image has main transfer
TBK_IN_IMG	: Traceback records in image file
DBG_IN_IMG	: Debug records in image file

In this example, the **SHOW IMAGE** command displays the attributes of the file `PATCH.EXE` located in the current working directory. The image was modified from the original attributes on 29-SEP-2004.

The image link flags output indicates the image was changed to not call the debugger at image startup. The output also shows that the traceback symbols and the debugger symbols are present in the image file.

The first line of output displays the version of **SHOW IMAGE** installed on the system. The line titled "Image Dynamic Data Version" shows the version of **SHOW IMAGE** that was available when the image was linked. Future updates to the Integrity servers ELF image format might cause the image dynamic data version to increase. When the image version does not match the **SHOW IMAGE** version, a new version of **SHOW IMAGE** might be required to display the new ELF format data.

2. \$ SHOW IMAGE SYS\$LIBRARY:DCLTABLES  
 Show Image Version 1.2 29-SEP-2004 07:59:48.07  
 SYS\$COMMON:[SYSLIB]DCLTABLES.EXE;928  
 This is an OpenVMS IA64 (Elf format) executable image file

Image Identification Information

```
Image name: DCLTABLES
  Global Symbol Table name: DCLTABLES
  Image file identification: 0-0
  Image build identification: XAAU-BL1-0000
    Link identification: Linker T02-02
      Link Date/Time: 12-MAY-2004 14:39:38.30
      Patch Date/Time: Never
      Manipulation Date/Time: Never
  Image Dynamic Data Version: <unavailable>
  Image Completion Code Value: SUCCESS State: Original
  Image Link Flags state: <unavailable>
```

This example lists the image information for the `DCLTABLES.EXE` file in `SYS$LIBRARY`. The `<unavailable>` string in the image dynamic data version line indicates that this image cannot be manipulated with the **SET IMAGE** command.

# SHOW INTRUSION

**SHOW INTRUSION** — Displays the contents of the intrusion database. **Requires SECURITY privilege.**

## Format

**SHOW INTRUSION**

## Description

The OpenVMS system stores information in the intrusion database about login failures that originate from a specific source and that result from any number of failure types (invalid password, account expired, unknown user name). A security manager can identify possible break-in attempts by using the **SHOW INTRUSION** command to display the contents of the intrusion database.

The entries in the intrusion database have the following format:

```
Intrusion      Type      Count      Expiration      Source
```

The information provided in the fields in each entry is as follows:

Field	Description
Intrusion	Class of intrusion. The type of evasive action that the OpenVMS system takes depends on the class of intrusion.
Type	Severity of intrusion as defined by the threshold count for login failures.
Count	Number of login failures associated with a particular source.
Expiration	Absolute time at which a login failure is no longer counted by OpenVMS. The system parameter LGI_BRK_TMO controls how long the OpenVMS system keeps track of a login failure.
Source	Origin of the login failure. The information provided in this field depends on the class of intrusion.

In the intrusion database, the operating system classifies login failures according to their source. The four classes of system intrusion are as follows:

Intrusion Class	Description
NETWORK	Login failure originating from a remote node, using a valid user name.
TERMINAL	Login failure originating from one terminal.
TERM_USER	Login failure originating from one terminal, using a valid user name.
USERNAME	Login failure attempting to create a detached process.

The class of intrusion determines the type of information presented in the source field of the entry. Information appears in the source field in one of the following formats:

Intrusion Class	Format of Source Field
NETWORK	node::user name
TERMINAL	terminal:
TERM_USER	terminal:user name

Intrusion Class	Format of Source Field
USERNAME	user name

The type of evasive action that a security manager can take is based on the type of information provided. For details on how to use this information, see the relevant section in the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#d0e11646) [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#d0e11646].

The intrusion database contains two levels of intrusion entries: suspect and intruder. The severity level of an entry is displayed in the type field of the entry. When a login failure associated with a particular source occurs, the OpenVMS system classifies the login failure as suspect. Each succeeding login failure from the same source is counted. The login failure count is displayed in the count field of the entry. The absolute time at which the login failure ceases to be counted is displayed in the expiration field of the entry. When the number of login failures exceeds the number specified by the system parameter LGI\_BRK\_LIM, the entry is classified as an intruder. However, if the parameter LGI\_BRK\_LIM is set to zero, the first login failure is not classified as an intruder; the result is the same as if the parameter LGI\_BRK\_LIM were set to one.

When an entry is promoted to intruder, the OpenVMS system takes evasive action by blocking all login attempts from that particular source.

The duration of the evasive action is determined by the system parameter LGI\_HID\_TIM. The absolute time at which the evasive action ends is displayed in the expiration field of the entry.

For information on intrusion detection, prevention, and evasive actions, see the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/) [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/].

If you determine that an entry in the intrusion database resulted from a user error and not a break-in attempt, you can remove an entry from the intrusion database with the **DELETE/INTRUSION\_RECORD** command. See the [DELETE/INTRUSION\\_RECORD](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_66) [https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\_66] command for more details.

## Qualifiers

**/NODE**[(*node-name*[,...])]

The **/NODE** qualifier displays each intrusion record with the supporting node information.

If you specify individual nodes, the supporting node information is displayed only for the nodes listed.

**/OUTPUT**[(*filespec*)]

Directs the output from the **SHOW INTRUSION** command to the file specified with the qualifier. By default, output from the command is displayed to SYS\$OUTPUT.

**/TYPE**=*keyword*

Selects the type of information from the intrusion database that is displayed. The valid keywords are as follows:

Keyword	Description
ALL	All entries. By default, all entries are displayed.
SUSPECT	Entries for login failures that have occurred but have not yet passed the threshold necessary to be identified as intruders.

Keyword	Description
INTRUDER	Entries for which the login failure rate was high enough to warrant evasive action.

## Examples

1. `$ SHOW INTRUSION/OUTPUT=INTRUDER.LIS`

The **SHOW INTRUSION** command in this example writes all the entries currently in the intrusion database to the file `INTRUDER.LIS`.

2. `$ SHOW INTRUSION/TYPE=INTRUDER`

Intrusion	Type	Count	Expiration	Source
TERMINAL	INTRUDER	9	10:29:39.16	AV34C2/LC-1-15:
NETWORK	INTRUDER	7	10:47:53.12	NODE22::RONNING

In this example, the **SHOW INTRUSION** command displays all intruder entries currently in the intrusion database.

3. `$ SHOW INTRUSION/NODE`  

NETWORK	SUSPECT	5	26-JUL-2001 08:51:25.66	POPEYE::WONG
Node: TSAVO	Count:	2		
Node: FROGGY	Count:	2		
Node: KITTY	Count:	1		

This command displays each intrusion record for all nodes.

4. `$ SHOW INTRUSION/NODE=(FROGGY,KITTY)`  

NETWORK	SUSPECT	5	26-JUL-2001 08:51:25.66	POPEYE::HAMMER
Node: FROGGY	Count:	2		
Node: KITTY	Count:	2		

This command displays intrusion record information for nodes FROGGY and KITTY.

5. `$ SHOW INTRUSION/NODE=EVMSA`  
`$`

This command shows that there are no intrusion records for node EVMSA.

## SHOW KEY

**SHOW KEY** — Displays the key definitions created with the **DEFINE/KEY** command.

### Format

**SHOW KEY** [*key-name*]

### Parameter

*key-name*

Specifies the name of the key whose definition you want displayed. For a list of valid key names, see the **DEFINE/KEY** command in the [VSI OpenVMS DCL Dictionary: A–M](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_60) [https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\_60].

## Description

After you have defined keypad keys by using the **DEFINE/KEY** command, you can use the **SHOW KEY** command to refresh your memory about a key definition. You can also use the **SHOW KEY** command with the **/DIRECTORY** qualifier to list the names of all the states in which you have created key definitions. Use the **SET KEY** command to change key states.

## Qualifiers

### **/ALL**

Displays all key definitions in the current state (or the state specified with the **/STATE** qualifier.) If you use the **/ALL** qualifier, do not specify a key name.

### **/BRIEF (default)**

### **/NOBRIEF**

Displays only the key definition and state. The **/BRIEF** and **/NOFULL** qualifiers are equivalent.

### **/DIRECTORY**

Displays the names of all states for which keys have been defined. If you have not specified a state with a key definition, the **SHOW KEY/DIRECTORY** command displays **DEFAULT** for the state.

You cannot use the **/DIRECTORY** qualifier with any of the other **SHOW KEY** qualifiers.

### **/FULL**

### **/NOFULL (default)**

Displays all qualifiers associated with a definition. By default, only the state of the definition and the definition itself are displayed. The **/FULL** and **/NOBRIEF** qualifiers are equivalent.

### **/STATE=(state-name[,...])**

### **/NOSTATE**

Displays the key definitions for the specified state. If you specify only one state name, you can omit the parentheses. State names can be any appropriate alphanumeric string. State names are created with the **DEFINE/KEY** command.

If you omit the **/STATE** qualifier or use the **/NOSTATE** qualifier, key definitions in the current state are displayed.

## Example

```
$ DEFINE/KEY/TERMINATE PF1 "ATTACH BOB"
%DCL-I-DEFKEY, DEFAULT key PF1 has been defined
$ SHOW KEY PF1
DEFAULT keypad definitions:
  PF1 = "ATTACH BOB"
$ SHOW KEY/FULL PF1
DEFAULT keypad definitions:
  PF1 = "ATTACH BOB"  (noecho,terminate,noerase,nolock)
```

The **SHOW KEY** command in this example displays both the definition and the state for the **PF1** key. This is the default display. The **SHOW KEY/FULL** command displays all qualifiers associated with the key definition.

# SHOW LICENSE

**SHOW LICENSE** — Displays software product licenses active on the current node and lists the names attached to a license (known as the RESERVE list). The **SHOW LICENSE** command displays the license database information currently in your system's memory. Use the License Management utility command, **LICENSE LIST**, when you want to view the license database information that is on disk.

## Format

```
SHOW LICENSE [product-name [, ...]]
```

## Parameter

### *product-name*

Specifies the name or names of activated software product licenses to display. The asterisk (\*) and the percent sign (%) wildcard characters are allowed. If you do not specify a product name, information is displayed about all active product name licenses. The *product-name* parameter is incompatible with the **/UNIT\_REQUIREMENTS** qualifier.

## Description

The DCL command **SHOW LICENSE** displays software product licenses active on the current node. An active license is one that has been registered in the **LICENSE** database *and* has been loaded into system memory. To register and activate software product licenses, use the License Management utility (**LICENSE**) or **VMSLICENSE.COM**. Some licenses are registered automatically during product installation.

For a complete description of this utility, see the [VSI OpenVMS License Management Utility Guide](https://docs.vmssoftware.com/vsi-openvms-license-management-utility-guide/) [https://docs.vmssoftware.com/vsi-openvms-license-management-utility-guide/].

To display licenses registered in the **LICENSE** database, use the **LICENSE LIST** command.

## Qualifiers

### **/BEFORE**

Use with **/TERMINATION\_DATE** and **/RELEASE\_DATE** qualifiers. Selects only those licenses whose times are before the time specified with the other qualifiers.

The **/BEFORE** qualifier cannot be used with the **/SINCE** qualifier.

### **/BRIEF (default)**

Displays a summary of information about the specified active product licenses. Use the **/FULL** qualifier to obtain a complete product license listing.

### **/CHARGE\_TABLE**

Synonym for the **/UNIT\_REQUIREMENTS** qualifier.

### **/CLUSTER**

Use with the **/UNIT\_REQUIREMENTS** qualifier to display the license unit requirements for every node in an OpenVMS Cluster.

**/EXACT**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify a search string that must match the search string exactly and must be enclosed with quotation marks (" ").

If you specify the **/EXACT** qualifier without the **/SEARCH** qualifier, exact search mode is enabled when you set the search string with the Find (**F1**) key.

**/FULL**

Displays a summary of information about the specified active product licenses, including Product Authorization Key (PAK) options and the reserve list (if any). On Integrity server systems, lists the products included in the operating environment currently active on the system.

**/HIERARCHY (Integrity servers only)**

Displays the hierarchy of licenses for operating environments active on the current node.

**/HIGHLIGHT[=keyword]**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify the type of highlighting you want when a search string is found. When a string is found, the entire line is highlighted. You can use the following keywords: BOLD, BLINK, REVERSE, and UNDERLINE. BOLD is the default highlighting.

**/OE[=OE-name] (Integrity servers only)**

When *OE-name* is specified, displays the settings for the named operating environment currently active on the node. Valid *OE-names* are FOE, BOE, EOE, MCOE, and HAOE. When no *OE-name* is specified, displays the operating environment currently active on the node.

**/OUTPUT[=filespec]****/NOOUTPUT**

Controls where the output of the **SHOW LICENSE** command is sent. By default, the output of the **SHOW LICENSE** command is sent to the current SYS\$OUTPUT device (usually your terminal). To send the output to a file, use the **/OUTPUT** qualifier followed by a file specification.

The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification. If you enter a partial file specification (for example, specifying only a directory), SHOW is the default file name and .LIS is the default file type.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

**/PAGE[=keyword]****/NOPAGE (default)**

Controls the display of license information on the screen.

You can use the following keywords with the **/PAGE** qualifier:

Keyword	Description
CLEAR_SCREEN	Clears the screen before each page is displayed.
SCROLL	Displays information one line at a time.
SAVE[=n]	Enables screen navigation of information, where <i>n</i> is the number of pages to store.

The **/PAGE=SAVE** qualifier allows you to navigate through screens of information. The **/PAGE=SAVE** qualifier stores up to 5 screens of up to 255 columns of information. When you use the **/PAGE=SAVE** qualifier, you can use the following keys to navigate through the information:

Key Sequence	Description
<b>Up</b> arrow key, <b>Ctrl/B</b>	Scroll up one line.
<b>Down</b> arrow key	Scroll down one line.
<b>Left</b> arrow key	Scroll left one column.
<b>Right</b> arrow key	Scroll right one column.
Find ( <b>E1</b> )	Specify a string to find when the information is displayed.
Insert Here ( <b>E2</b> )	Scroll right one half screen.
Remove ( <b>E3</b> )	Scroll left one half screen.
Select ( <b>E4</b> )	Toggle 80/132 column mode.
Prev Screen ( <b>E5</b> )	Get the previous page of information.
Next Screen ( <b>E6</b> ), <b>Return</b> , <b>Enter</b> , <b>Space</b>	Get the next page of information.
<b>F10</b> , <b>Ctrl/Z</b>	Exit. (Some utilities define these differently.)
Help ( <b>F15</b> )	Display utility help text.
Do ( <b>F16</b> )	Toggle the display to oldest/newest page.
<b>Ctrl/W</b>	Refresh the display.

The **/PAGE** qualifier is not compatible with the **/OUTPUT** qualifier.

#### **/PRODUCER=producer-name**

Displays software product licenses active on the current node and supplied by the specified producer. The asterisk (\*) and the percent sign (%) wildcard characters are allowed for the *producer-name* parameter. You cannot use the **/PRODUCER** qualifier with the **/UNIT\_REQUIREMENTS** qualifier.

#### **/RELEASE\_DATE=[date\_time]**

Allows listing licenses using release dates as selection criteria.

#### **/SEARCH="string"**

Use with the **/PAGE=SAVE** qualifier to specify a string that you want to find in the information being displayed. Quotation marks are required for the **/SEARCH** qualifier, if you include spaces in the text string.

You can also dynamically change the search string by pressing the Find key (**E1**) while the information is being displayed. Quotation marks are not required for a dynamic search.

#### **/SINCE (default)**

Use with the **/TERMINATION\_DATE** and **/RELEASE\_DATE** qualifiers. Selects only those licenses whose times are on or after the time specified with the other qualifiers.

The **/SINCE** qualifier cannot be used with the **/BEFORE** qualifier.

**/TERMINATION\_DATE=*date\_time***

Allows listing licenses using termination dates as selection criteria.

**/UNIT\_REQUIREMENTS**

On Alpha systems, displays information in the License Unit Requirement Table (LURT). On Integrity server systems, displays information about the type of system, the number of active cores, and the number of sockets. The **/UNIT\_REQUIREMENTS** qualifier is incompatible with the *product-name* parameter and with the **/BRIEF** and **/PRODUCER** qualifiers.

**/USAGE**

Tells you how many license units are loaded, how many are currently allocated, and how many are currently available, as well as the license type for each product on the system. Use with the **/FULL** qualifier to display complete information – including the PID, process name, node, or user name – for each instance of use of the product. You need group privilege to see the list of users in your group who have allocated license units; you need world privilege to see the list of users in all groups.

In an OpenVMS Cluster, if you own multiple license types for a single product, you are limited to viewing the usage information for the license type loaded on the node from which you are executing the **SHOW LICENSE/USAGE** command. To find out the usage of the other license type loaded on another node, issue the command on that node. You can also use the System Management (SYSMAN) utility to do this.

In an OpenVMS Cluster, usage information is limited to the local license type. For example, VAX and Alpha availability licenses are considered by LMF to be different license types. If you are running both VAX and Alpha systems in a cluster, usage information for availability licenses is limited to the local system type. For example, if you have DEC C installed on all nodes in your OpenVMS Cluster, you can display DEC C license allocation on all the VAX nodes in the cluster from any VAX node with DEC C installed, but you cannot display the DEC C license allocation on the Alpha nodes.

Usage information is not available for unlimited licenses (a license with 0 units). Clusterwide usage information is not available for personal use or NO\_SHARE licenses. See the [VSI OpenVMS License Management Utility Guide \[https://docs.vmssoftware.com/vsi-openvms-license-management-utility-guide/\]](https://docs.vmssoftware.com/vsi-openvms-license-management-utility-guide/) for more information on license types.

**/WARNING\_INTERVAL=*n***  
**NOWARNING\_INTERVAL**

Displays a warning stating the number of licenses that will terminate in *n* days. The default is 30 days.

**/WRAP****/NOWRAP (default)**

Use with the **/PAGE=SAVE** qualifier to limit the number of columns to the width of the screen and to wrap lines that extend beyond the width of the screen to the next line.

The **/NOWRAP** qualifier extends lines beyond the width of the screen and can be seen when you use the scrolling (left and right) features provided by the **/PAGE=SAVE** qualifier.

## Examples

1. \$ SHOW LICENSE/FULL

Active licenses on node WTPOOH:

DVNETEND

Producer: DEC  
Units: 0  
Version: 0.0  
Release Date: (none)  
Termination Date: 31-DEC-2012  
Availability: 0  
Activity: 100  
MOD\_UNITS  
Product Token:

OPENVMS-ALPHA

Producer: DEC  
Units: 0  
Version: 0.0  
Release Date: (none)  
Termination Date: 31-DEC-2012  
Availability: 0  
Activity: 100  
MOD\_UNITS  
Product Token:

The **SHOW LICENSE** command in this example displays all the active licenses on the current Alpha node, WTPOOH.

## 2. \$ SHOW LICENSE/FULL

Active licenses on node MACCHU:

C

Producer: HPE  
Units: 3  
Version: 0.0  
Release Date: (none)  
Termination Date: 31-DEC-2012  
Availability: 0  
Activity: 1  
MOD\_UNITS  
IA64\_ALPHA  
Product Token:

DVNETEXT

Producer: HPE  
Units: 4  
Version: 0.0  
Release Date: (none)  
Termination Date: 31-DEC-2012  
Per Core License  
Activity: 0  
IA64  
Product Token:

OPENVMS-I64-BOE

Producer: HPE  
Units: 4  
Version: 0.0  
Release Date: (none)

```
Termination Date: 31-DEC-2012
Per Core License
Activity: 0
IA64
Product Token:
```

The **SHOW LICENSE** command in this example displays all the active licenses on the current Integrity server node, MACCHU.

3. \$ SHOW LICENSE/BRIEF

Active licenses on node WTPOOH:

```
--- Product ID ----   --- Rating ----- -- Version --
Product  Producer Units Avail  Activ Version Release Termination
DVNETEND DEC           0  0    100   0.0   (none)   (none)
VAX-VMS  DEC           0  0    100   0.0   (none)   (none)
```

The **SHOW LICENSE** command in this example displays a summary of all the active licenses on the current VAX node, WTPOOH.

4. \$ SHOW LICENSE/OUTPUT=SYS\$LOGIN:ACTIVE\_LICENSES\_OCT30.DAT

The **SHOW LICENSE** command in this example writes all the active licenses to the file named SYS\$LOGIN:ACTIVE\_LICENSES\_OCT30.DAT.

5. \$ SHOW LICENSE/FULL PERSONAL

Active licenses on node PICCHU:

```
PERSONAL
  Producer: DEC
  Units: 100
  Version: 0.0
  Release Date: (none)
  Termination Date: (none)
  Availability: 0
  Activity: 100
  RESERVE_UNITS
  Reserve: RANCE
```

The **SHOW LICENSE** command in this example displays information about the product PERSONAL, as well as the name RANCE attached to the product license (known as the RESERVE list).

6. \$ SHOW LICENSE/TERM=10-JAN-2014 test0%

Active licenses on node PICCHU:

```
--- Product ID ----   --- Rating ----- -- Version --
Product  Producer Units Avail  Activ Version Release Termination
TEST01  DEC           0  A     0     0.0   (none)   (none)
TEST02  DEC           0  B     0     0.0  10-JAN-2014 12-NOV-2014
TEST03  DEC           0  C     0     0.0  30-DEC-2014 (none)
TEST04  DEC           0  D     0     0.0   (none)   25-AUG-2015
TEST05  DEC           0  E     0     0.0  14-NOV-2016 14-AUG-2016
```

```
$ SHOW LICENSE/RELEASE=10-JAN-2014/SINCE test0%
```

Active licenses on node PICCHU:

```
--- Product ID ---- Rating ----- -- Version --
Product Producer Units Avail Activ Version Release Termination
TEST02 DEC          0 B      0      0.0 10-JAN-2014 12-NOV-2014
TEST03 DEC          0 C      0      0.0 30-DEC-2014 (none)
TEST05 DEC          0 E      0      0.0 14-NOV-2016 14-AUG-2016
```

```
$ SHOW LICENSE/RELEASE=10-JAN-2014/BEFORE test0%
```

Active licenses on node PICCHU:

```
--- Product ID ---- Rating ----- -- Version --
Product Producer Units Avail Activ Version Release Termination
TEST01 DEC          0 A      0      0.0 (none) (none)
TEST04 DEC          0 D      0      0.0 (none) 25-AUG-2015
```

In these examples, the **SHOW LICENSE** command uses the **/TERM**, **/RELEASE**, **/SINCE**, and **/BEFORE** qualifiers.

#### 7. \$ SHOW LICENSE/UNIT\_REQUIREMENTS

VMS/LMF Charge Information for node PICCHU

This is a AlphaServer 8400 5/440, hardware model type 1567

```
Type: A, Units Required: 2700 (VAX/VMS Capacity or OpenVMS
                               Unlimited or Base)
Type: B, * Not Permitted *    (VAX/VMS F&A Server)
Type: C, * Not Permitted *    (VAX/VMS Concurrent User)
Type: D, * Not Permitted *    (VAX/VMS Workstation)
Type: E, * Not Permitted *    (VAX/VMS System Integrated Products)
Type: F, * Not Permitted *    (VAX Layered Products)
Type: G, * Not Permitted *    (Reserved)
Type: H, Units Required: 1150 (Alpha Layered Products)
Type: I, Units Required: 1150 (Layered Products)
```

In this example, the **/UNIT\_REQUIREMENTS** qualifier displays information in the License Unit Requirement Table (LURT) for the Alpha node PICCHU.

#### 8. \$ SHOW LICENSE/CHARGE\_TABLE

OpenVMS I64/LMF Charge Information for node MACCHU

This is an HPE rx2600(900MHz/1.5MB), with 2 CPUs active, 2 socket(s)

Type: PPL, Units Required: 2 (I64 Per Processor)

Type: PCL, Units Required: 2 (I64 Per Core)

This example displays the **CHARGE\_TABLE** information for an Integrity server node MACCHU with two active processor cores.

#### 9. \$ SHOW LICENSE/CHAR/CLUSTER

VMS/LMF Cluster License Unit Requirements Information 14-MAR-2010

06:39:41.54

Node	A	B	C	D	E	F	G	H	I	PCL
FISH	20	-	-	-	-	-	-	1050	1050	-
SWORD	15	-	-	-	-	-	-	1050	1050	-
SALMON	12	-	-	-	-	-	-	1050	1050	-
MONGER	12	-	-	-	-	-	-	1050	1050	-
GORDON	15	-	-	-	-	-	-	1050	1050	-
ARTIST	-	-	-	-	-	-	-	-	-	2
PAINTS	-	-	-	-	-	-	-	-	-	1

## Total Cluster Unit Requirements

Type: A, Units Required: 74 (VAX/VMS Capacity or OpenVMS  
Unlimited or Base)

Type: B, \* Not Permitted \* (VAX/VMS F&A Server)

Type: C, \* Not Permitted \* (VAX/VMS Concurrent User)

Type: D, \* Not Permitted \* (VAX/VMS Workstation)

Type: E, \* Not Permitted \* (VAX/VMS System Integrated Products)

Type: F, \* Not Permitted \* (VAX Layered Products)

Type: G, \* Not Permitted \* (Reserved)

Type: H, Units Required: 5250 (Alpha Layered Products)

Type: I, Units Required: 5250 (Layered Products)

Type: PPL, Units Required: 3 (I64 Per Processor)

Type: PCL, Units Required: 3 (I64 Per Core)

In this example, the display shows how many license units are required for each license type (A, B, etc. on Alpha and VAX and PCL on Integrity servers) on each node in the cluster. If a row of three asterisks (\*\*\*) is displayed for a node, it means that the node is in the process of booting.

## 10. \$ SHOW LICENSE/OE

Current Operating Environment on node MACCHU at 8-MAR-2010  
16:12:51.72

----- Operating Environment -----				Units -----	
Name	Description	Type	Level	Loaded	Total
HAOE	High Availability	H	5	4	4

This example shows the currently operating environment (HAOE) on an Integrity server node MACCHU.

## 11. \$ SHOW LICENSE/HIER/FULL

## Operating Environment Hierarchy

----- Operating Environment -----				Units -----	
Name	Description	Type	Level	Loaded	Total
HAOE	High Availability	H	5	2	2
GWLM					
MCOE	Mission Critical	H	4	-	2
RTR-SVR					
VMSCLUSTER					
VMSCLUSTER-CLIENT					
EOE	Enterprise	H	3	-	2
AVAIL-MAN					
RMSJNL					
VOLSHAD					

```

BOE      Base                H      2      -      2
  DEGRAM
  OMS
FOE      Foundation         H      1      -      2
  OPENVMS-I64
  OPENVMS-USER
  DVNETEND
  DW-MOTIF
  UCX
  TDC
  X500-ADMIN-FACILITY
  X500-DIRECTORY-SERVER
  CIFS

```

This example displays information about the available operating environments, the hierarchy among them, and the products contained in each OE on an Integrity servers system.

## 12. \$ SHOW LICENSE/OE=BOE/FULL

```

----- Operating Environment ----- Units -----
Name      Description          Type Level   Loaded    Total
BOE      Base                H      2      4      7
  DEGRAM
  OMS
  OPENVMS-I64
  OPENVMS-USER
  DVNETEND
  DW-MOTIF
  UCX
  TDC
  X500-ADMIN-FACILITY
  X500-DIRECTORY-SERVER
  CIFS

```

This example shows all the products included in the Base Operating Environment (BOE) on an Integrity server node.

## 13. \$ SHOW LICENSE OPENVMS-I64-HAOE

Active licenses on node MACCHU:

```

----- Product ID ----- ---- Rating ----- -- Version --
Product      Producer Units PCL Activ Version Release Termination
OPENVMS-I64-HAOE HPE      4      1      0      0.0 (none) 10-MAR-2011

```

This example shows licensing information for the HAOE environment currently active on an Integrity server node MACCHU.

## 14. \$ SHOW LICENSE/WARNING\_INTERVAL=8000 test0%

Active licenses on node PICCHU:

```

--- Product ID --- ---- Rating ----- -- Version --
Product  Producer Units Avail Activ Version Release Termination
TEST01   DEC      0 A      0      0.0 (none) (none)
TEST02   DEC      0 B      0      0.0 10-JAN-2014 12-NOV-2014
TEST03   DEC      0 C      0      0.0 30-DEC-2014 (none)
TEST04   DEC      0 D      0      0.0 (none) 25-AUG-2015
TEST05   DEC      0 E      0      0.0 14-NOV-2016 14-AUG-2016
%SHOW-I-TERMIMM, 3 licenses will terminate in 8000 days

```

The **/WARNING\_INTERVAL** qualifier in this example displays three licenses that will terminate in 8000 days.

15. \$ SHOW LICENSE/USAGE/FULL DECWRITE-USER

View of loaded licenses from node SLTG24 29-DEC-2001 13:36:22.23

ACTIVITY license DECWRITE-USER usage information:

Pid	Process Name	Units	Username	Node
416000E6	MACAHAY	100	MACAHAY	SLTG24
416000E7	MACAHIGH	100	MACAHIGH	SLTG24
416000E8	ALICE	100	ALICE	SLTG24
416000E9	MORGEN	100	MORGEN	SLTG24
416000F1	ANGEL	100	ANGEL	SLTG24
416000F2	ANGEL_1	100	ANGEL	SLTG24

Units loaded: 2000      Units allocated: 600      Units available: 1400

The **SHOW LICENSE** command in this example lists the current users of the activity license for the product DECwrite. For each instance of use of the product, the process identification (PID), process name, node, and user name are identified. The units column shows the number of units allocated for each particular invocation of the product. The last line displays the units loaded when the **LICENSE LOAD** command was given, the total number of units currently allocated, and the total of unused (available for others to use) units.

16. \$ SHOW LICENSE/USAGE/FULL TEST\_PER

View of loaded licenses from node: SLTG24 30-DEC-2001 15:45:59

PERSONAL USE license DEC TEST\_PER usage information:

Units      Reserved for:

100	UNCLE
100	AUNT
100	NEPHEW
100	NIECE

Units loaded: 600      Units reserved: 400      Units available: 200

This example shows a personal use license. The DEC TEST\_PER product has enough units for six reservations with 100 units for each reservation. The license database (LDB) only has a total of four names in the reserve list attached to this product. If the license administrator (usually the system manager) wants to take full advantage of this license and adds two more names to the reserve list, he should use the following commands to update the product information:

```
$ LICENSE MODIFY TEST_PER/RESERVE=(NAME, ANOTHER_NAME)/ADD
$ LICENSE UNLOAD TEST_PER
$ LICENSE LOAD TEST_PER
```

If this product is used in a cluster environment, you may use the SYSMAN utility to unload and load the license.

17. \$ SHOW LICENSE/USAGE/FULL TEST\_CAP

View of loaded licenses from node: SLTG24 30-DEC-2001 15:45:59

Availability license DEC TEST\_CAP usage information:

```
Units   Node
    10   SLTG24
    10   SLTG43
   600   TORN80
   600   LTNUP
```

Units loaded: 620      Units allocated: 1220      Units available: \*\*\*

In this example, the number of units allocated appears to be greater than the total units loaded and the units available value is three asterisks (\*\*\*).

When you see three asterisks (\*\*\*) as the number of units available, it is generally not a cause for alarm. This situation might arise when the license database (LDB) has been updated on disk, but the new information has not been propagated to the license database in memory on all nodes in the cluster. This node, SLTG24, happens to be one of the nodes that has not received the latest LDB information.

To update the information in the license database in memory for the TEST\_CAP product, enter the following commands:

```
$ LICENSE UNLOAD TEST_CAP
$ LICENSE LOAD TEST_CAP
```

The next time you issue the **SHOW LICENSE/USAGE** command the three asterisks (\*\*\*) in display should disappear. If, however, you are using multiple LDB files in a cluster, you should read the section on the license database in the *VSI OpenVMS License Management Utility Guide* [[https://docs.vmssoftware.com/vsi-openvms-license-management-utility-guide/#section\\_tjk\\_y5d\\_s3b](https://docs.vmssoftware.com/vsi-openvms-license-management-utility-guide/#section_tjk_y5d_s3b)].

#### 18. \$ SHOW LICENSE/UNIT\_REQUIREMENT/CLUSTER

VMS/LMF Cluster License Unit Requirements Information 24-DEC-2001  
14:05:51.65

Node	A	B	C	D	E	F	G	H	I
KARBO	-	-	-	100	50	10	-	-	10
JENJON	-	-	-	100	50	10	-	-	10
HELENA	143	-	-	-	600	2400	-	-	2400
SHAKTI	-	-	-	100	50	10	-	-	10

Total Cluster Unit Requirements

```
Type: A, Units Required: 143      (VMS Capacity)
Type: B, * Not Permitted *        (VMS Server)
Type: C, * Not Permitted *        (VMS Concurrent User)
Type: D, Units Required: 300      (VMS Workstation)
Type: E, Units Required: 750      (System Integrated Products)
Type: F, Units Required: 2430     (Layered Products)
Type: G, * Not Permitted *        (VMS Reserved)
Type: H, * Not Permitted *        (Alpha Layered Products)
Type: I, Units Required: 2430     (Layered Products)
```

In this example, the display shows how many license units are required for each license type (A, B, etc.) on each node in the cluster. If a row of three asterisks (\*\*\*) is displayed for a node, it means that the node is in the process of booting.

#### 19. \$ SHOW LICENSE/USAGE

View of loaded licenses from node REDSOX 8-MAR-2010 16:20:11.14

```

----- Product ID ---- Unit usage information -----
Product          Producer Loaded Allocated Available Compliance
C                 HPE          250      0        250      Yes
DVNETEXT          HPE           4       3         1      Yes
OPENVMS-I64-BOE   HPE           2       2         0      Yes
OPENVMS-I64-HAOE HPE          20       8        12      Yes
VAXSET            HPE          10       8         2      Yes

```

This example shows how many license units are loaded, how many are currently allocated, and how many are available on REDSOX, an Integrity servers system. The last column in the display shows that are products are in compliance with their license unit requirements.

## 20. \$ SHOW LICENSE/USAGE

```

View of loaded licenses from node HOVMS2 8-MAR-2010 08:38:17.13
----- Product ID ----- Unit usage information -----
Product          Producer Loaded Allocated Available Compliance
OPENVMS-I64-HAOE HPE      Virtual Machine guest, no usage information

```

Issuing the **SHOW LICENSE/USAGE** command from an OpenVMS guest cluster member displays the text "Virtual Machine guest, no usage information" for PCL licenses loaded on the system. There is essentially no usage charge against the license units for OpenVMS guest nodes since multiple guests can run on the same host using the same license units.

# SHOW LOGICAL

**SHOW LOGICAL** — Displays translations, the level of translation, and the logical name table for a specified logical name. The **SHOW LOGICAL** command performs iterative translations. **Requires read (R) access to the table in which a logical name is cataloged to display information about the logical name.**

## Format

**SHOW LOGICAL** [*logical-name*[:][, ...]]

## Parameter

*logical-name*[:][, ...]

Specifies one or more logical names whose translations you want to display. The asterisk (\*) and the percent sign (%) wildcard characters are allowed; however, if a wildcard character is used, iterative translation is not done.

The logical name is translated iteratively up to a number of times determined by the system (from 9 to 11). That is, translations are examined to see if they are also logical names.

## Description

The **SHOW LOGICAL** command displays logical names.

The logical name LNM\$DCL\_LOGICAL contains the list of logical name tables and the order in which they are searched. Unless LNM\$DCL\_LOGICAL has been

redefined, the process, job, group, and system tables are searched, in that order (To see how LNM\$DCL\_LOGICAL is defined for your process, enter the command **SHOW LOGICAL/TABLE=LNMS\$DIRECTORIES LNM\$DCL\_LOGICAL**).

If you specify a logical name, its translations are displayed. If you do not specify a logical name, all the logical names in the tables defined by the logical name LNM\$DCL\_LOGICAL are displayed.

You can specify the tables you want to search. If you do not specify a table, **SHOW LOGICAL** searches the tables specified by the logical name LNM\$DCL\_LOGICAL.

The **SHOW LOGICAL** command performs iterative translations. If a logical name has more than one translation, then all translations at a level are displayed before going to the next level. Use the **SHOW TRANSLATION** command to display only the first translation found for a specified logical name.

The **SHOW LOGICAL** command executes an image and causes the current image (if any) to exit. Use the **SHOW TRANSLATION** command (which is built into the command interpreter) when you do not want to exit the current image.

If a logical name contains control characters, the **SHOW LOGICAL** command replaces them with periods (.) for display.

## Qualifiers

### **/ACCESS\_MODE=mode**

Displays names defined in the specified access mode and any inner access modes. You can specify one of the following keywords to indicate the access mode: USER\_MODE, SUPERVISOR\_MODE, EXECUTIVE\_MODE, or KERNEL\_MODE.

The default value for this qualifier is USER\_MODE; by default any definitions in all four access modes are displayed.

### **/ALL (default)**

Indicates that all logical names in the specified logical name tables are to be displayed. If you do not enter the **/PROCESS**, **/JOB**, **/GROUP**, **/SYSTEM**, or **/TABLE** qualifier, all logical names in the tables specified by the logical name LNM\$DCL\_LOGICAL are displayed.

### **/CLUSTER**

Displays all the logical names in all clusterwide tables (for example, the LNM\$CLUSTER and LNM\$SYSCLUSTER tables).

### **/DESCENDANTS**

#### **/NODESCENDANTS (default)**

Controls whether the system displays names from the specified logical name table and any descendant tables. A descendant table is created by the **CREATE/NAME\_TABLE** command, with the **/PARENT\_TABLE** qualifier specifying its parent table. If you use the **/DESCENDANTS** qualifier, you must also use the **/TABLE** qualifier.

### **/EXACT**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify a search string that must match the search string exactly and must be enclosed with quotation marks (" ").

If you specify the **/EXACT** qualifier without the **/SEARCH** qualifier, exact search mode is enabled when you set the search string with the Find (**E1**) key.

### **/FULL**

Displays more detailed information for the specified logical name. The information includes the access mode, attributes, the translation, and the logical name table.

### **/GROUP**

Indicates that only the group logical name table is to be searched. The **/GROUP** qualifier is synonymous with the **/TABLE=LN\$GROUP** qualifier. If you specify the **/GROUP** qualifier and you do not also specify a logical name, all names in the group table are displayed.

### **/HIGHLIGHT[=*keyword*]**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify the type of highlighting you want when a search string is found. When a string is found, the entire line is highlighted. You can use the following keywords: BOLD, BLINK, REVERSE, and UNDERLINE. BOLD is the default highlighting.

### **/JOB**

Indicates that only the job logical name table is to be searched. The **/JOB** qualifier is synonymous with the **/TABLE=LN\$JOB** qualifier. If you specify the **/JOB** qualifier and you do not also specify a logical name, all names in the job logical name table are displayed.

### **/OUTPUT[=*filespec*]**

#### **/NOOUTPUT**

Controls where the output of the **SHOW LOGICAL** command is sent. By default, the output of the **SHOW LOGICAL** command is sent to the current SYS\$OUTPUT device (usually your terminal). To send the output to a file, use the **/OUTPUT** qualifier followed by a file specification.

The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification. If you enter a partial file specification (for example, specifying only a directory), SHOW is the default file name and .LIS is the default file type.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

### **/PAGE[=*keyword*]**

#### **/NOPAGE (default)**

Controls the display of information on the screen.

You can use the following keywords with the **/PAGE** qualifier:

Keyword	Description
CLEAR_SCREEN	Clears the screen before each page is displayed.
SCROLL	Displays information one line at a time.
SAVE[= <i>n</i> ]	Enables screen navigation of information, where <i>n</i> is the number of pages to store.

The **/PAGE=SAVE** qualifier allows you to navigate through screens of information. The **/PAGE=SAVE** qualifier stores up to 5 screens of up to 255 columns of information. When you use the **/PAGE=SAVE** qualifier, you can use the following keys to navigate through the information:

Key Sequence	Description
<b>Up</b> arrow key, <b>Ctrl/B</b>	Scroll up one line.
<b>Down</b> arrow key	Scroll down one line.
<b>Left</b> arrow key	Scroll left one column.
<b>Right</b> arrow key	Scroll right one column.
Find ( <b>E1</b> )	Specify a string to find when the information is displayed.
Insert Here ( <b>E2</b> )	Scroll right one half screen.
Remove ( <b>E3</b> )	Scroll left one half screen.
Select ( <b>E4</b> )	Toggle 80/132 column mode.
Prev Screen ( <b>E5</b> )	Get the previous page of information.
Next Screen ( <b>E6</b> ), <b>Return</b> , <b>Enter</b> , <b>Space</b>	Get the next page of information.
<b>F10</b> , <b>Ctrl/Z</b>	Exit. (Some utilities define these differently.)
Help ( <b>F15</b> )	Display utility help text.
Do ( <b>F16</b> )	Toggle the display to oldest/newest page.
<b>Ctrl/W</b>	Refresh the display.

The **/PAGE** qualifier is not compatible with the **/OUTPUT** qualifier.

## **/PROCESS**

Indicates that only the process logical name table is to be searched. The **/PROCESS** qualifier is synonymous with the **/TABLE=LN\$PROCESS** qualifier. If you specify the **/PROCESS** qualifier and you do not also specify a logical name, all names in the process table are displayed.

## **/SEARCH="string"**

Use with the **/PAGE=SAVE** qualifier to specify a string that you want to find in the information being displayed. Quotation marks are required for the **/SEARCH** qualifier, if you include spaces in the text string.

You can also dynamically change the search string by pressing the Find key (**E1**) while the information is being displayed. Quotation marks are not required for a dynamic search.

## **/STRUCTURE**

### **/NOSTRUCTURE (default)**

Controls whether the system displays the "family tree" of all accessible logical name tables. The display includes the two logical name directory tables (process and system) and all logical name tables cataloged in these directory tables. Any descendant logical name tables are shown under their parent tables.

If you specify the **/STRUCTURE** qualifier, you cannot use any other qualifiers except **/ACCESS\_MODE**, **/FULL**, and **/OUTPUT**.

**/SYSTEM**

Indicates that only the system logical name table is to be searched. The **/SYSTEM** qualifier is synonymous with the **/TABLE=LNMSYSTEM** qualifier. If you specify the **/SYSTEM** qualifier and you do not also specify a logical name, all names in the system table are displayed.

**/TABLE=(name[,...])**

Specifies the tables you want to search. If you specify only one table, you can omit the parentheses. The asterisk (\*) and the percent sign (%) wildcard characters are allowed. Names with wildcards are used to match table names. Names without wildcard characters are treated both as table names and table search lists (whichever is appropriate).

You can use the **/TABLE** qualifier to specify the following:

- A user-defined logical name table (created with the **CREATE/NAME\_TABLE** command)
- The process, group, or system logical name tables
- The process or system directory tables

If you specify the table name by using a logical name that translates to more than one table, then each table is searched in the order specified. For example, if you specify **SHOW LOGICAL/TABLE=LNMSFILE\_DEV**, and **LNMSFILE\_DEV** is equated to **LNMSPROCESS**, **LNMSJOB**, **LNMSGROUP**, and **LNMSYSTEM**, then the process, job, group, and system tables are searched, in that order.

If you do not specify the **/TABLE** qualifier, the default is **/TABLE=LNMSDCL\_LOGICAL**.

**/WRAP****/NOWRAP (default)**

Use with the **/PAGE=SAVE** qualifier to limit the number of columns to the width of the screen and to wrap lines that extend beyond the width of the screen to the next line.

The **/NOWRAP** qualifier extends lines beyond the width of the screen and can be seen when you use the scrolling (left and right) features provided by the **/PAGE=SAVE** qualifier.

## Examples

1. 

```
$ SHOW LOGICAL/PROCESS
(LNM$PROCESS_TABLE)
  "SYS$COMMAND" = "_TTB4:"
  "SYS$DISK" = "WORK6:"
  "SYS$DISK" = "WORK6:"
  "SYS$ERROR" = "_TTB4:"
  "SYS$INPUT" = "_TTB4:"
  "SYS$LOGIN" = "WORK6:[ODONNELL]"
  "SYS$LOGIN_DEVICE" = "WORK6:"
  "SYS$OUTPUT" = "_TTB4:"
  "SYS$OUTPUT" = "DKA2:"
  "SYS$SCRATCH" = "WORK6:[ODONNELL]"
```

The **SHOW LOGICAL** command in this example displays all process logical names and their translations. Note that **/TABLE=LNMSPROCESS** would produce the same display as **/PROCESS**.

2. 

```
$ SHOW LOGICAL INFILE
```

```
"INFILE" = "WORK6:[LOGAN]PAYROLL.EXE" (LNM$PROCESS_TABLE)
```

The **SHOW LOGICAL** command in this example displays the translation for the logical name INFILE. The response indicates that the logical name was found in the process logical name table.

```
3. $ SHOW LOGICAL/GROUP
.
.
.
```

The **SHOW LOGICAL** command in this example displays all group logical names and their translations. Note that **/TABLE=LNM\$GROUP** would produce the same display as **/GROUP**.

```
4. $ SHOW LOGICAL/TABLE=SYSTEM SYS$LIBRARY
"SYS$LIBRARY" = "SYS$SYSROOT:[SYSLIB]" (LNM$SYSTEM_TABLE)
      = "DOCD$:[SYSC.SYSLIB]"
```

The **SHOW LOGICAL** command in this example displays the translation of the logical name SYS\$LIBRARY in the system table. The response indicates that SYS\$LIBRARY is defined in the system table, and that the logical name has two translations.

```
5. $ SHOW LOGICAL/TABLE=LNM$GROUP/TABLE=LNM$SYSTEM SYS$DISK
"SYS$DISK" = "ZZZ3:" (LNM$SYSTEM_TABLE)
```

The **SHOW LOGICAL** command in this example is qualified by both the **/TABLE=LNM\$GROUP** and **/TABLE=LNM\$SYSTEM** qualifiers. The response indicates that the logical name SYS\$DISK was found in the system logical name table. When you enter two conflicting qualifiers, as in this example, only the last qualifier you specify is used.

```
6. $ SHOW LOGICAL/TABLE=LNM$PROCESS_DIRECTORY
```

The **SHOW LOGICAL** command in this example displays the logical names in the process directory table. Each name is either a table name, or a name that translates iteratively to a table.

## SHOW MEMORY

**SHOW MEMORY** — Displays the availability and usage of those system resources that are related to memory.

### Format

**SHOW MEMORY**

### Parameters

None.

### Description

The information provided by the **SHOW MEMORY** command can help you determine whether to change certain system memory resources to improve system performance. The system memory resources are as follows:

Physical memory

Process entry slots and balance slots  
Nonpaged and paged dynamic memory  
Space in paging and swapping files  
File data cache memory usage

When the **SHOW MEMORY** command is executed, a display is written to SYS\$OUTPUT. Depending on which qualifiers you specify, the display shows the following memory resource statistics:

Physical memory usage  
Bad page list  
Number of pages allocated to an OpenVMS system  
Slot usage  
Dynamic memory usage (in bytes)  
Paging file usage (in blocks)  
Dynamic memory  
Granularity hint regions for code and data (Alpha/Integrity servers only)  
Extended File Cache facility (Alpha/Integrity servers only)  
Write bitmap (WBM) memory use (Alpha/Integrity servers only)

For a detailed description of each item displayed, see the [Examples](#) section.

## Qualifiers

### **/ALL (default)**

Displays all available information, that is, information displayed by the **/FILES**, **/PHYSICAL\_PAGES**, **/POOL**, and **/SLOTS** qualifiers.

### **/BITMAP (Alpha/Integrity servers only)**

Displays information about memory use by write bitmaps (WBM) used with Host-Based Volume Shadowing (HBVS). If the system parameter SHADOWING is set to 0, no information about bitmaps is displayed because WBM is used only with HBVS.

Note that the memory consumption displayed by **SHOW MEMORY** is often greater than that displayed by **SHOW DEVICE/BITMAP**, which displays the exact size (in bytes) of the bitmap. The memory used by a bitmap is allocated in units of pages; if a bitmap uses part of a page of memory, the rest of that page is unavailable for use.

### **/BUFFER\_OBJECTS (Alpha/Integrity servers only)**

Displays information about system resources used by buffer objects.

### **/CACHE[=(*keyword*[,...])]**

Displays information about the Virtual I/O Cache facility or the Extended File Cache facility, depending on which is loaded. The Cache facility information is displayed as part of the **SHOW MEMORY** and **SHOW MEMORY/CACHE/FULL** commands.

If the Extended File Cache is loaded, you can specify the following keywords and options:

Keyword	Description
VOLUME[= <i>device</i> ]	Requests display of volume-level statistics for the specified volume(s). If no device is specified, defaults to SYS\$DISK. Device

Keyword	Description
	specifications may be wildcarded; if so, the device specification must be based on the physical device name. Specify <b>VOLUME=*</b> to see statistics for all volumes in cache.
<b>FILE=filespec</b>	Requests display of file-level statistics for the specified file(s) in cache. The filespec must contain an explicit or implicit device specification. The filespec may be wildcarded according to RMS rules. Specify <b>FILE=dev:*.*</b> to see statistics for all files in cache for a device. Partially wild file specifications that are satisfied by large numbers of files on disk may incur significant processing overhead during display. By default, both open and closed files are displayed (use the <b>OPEN</b> and <b>CLOSED</b> keywords to further restrict which files are displayed).  Note that this command may fail if you select a large number of files for display. If you receive an error message, reduce the number of selected files and reissue the command.
<b>TOPQIO[=n]</b>	Requests display of file-level statistics for the <i>n</i> files in cache with the highest overall QIO count ( <i>n</i> defaults to 10).
<b>TOPHITRATE[=n]</b>	Requests display of file-level statistics for the <i>n</i> files in cache with the highest overall cache hit rate ( <i>n</i> defaults to 10).
	<b>OPEN</b> Include only open files in the display (default for <b>TOPQIO</b> and <b>TOPHITRATE</b> ).
	<b>CLOSED</b> Include only closed files in the display.

**/EXACT**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify a search string that must match the search string exactly and must be enclosed with quotation marks (" ").

If you specify the **/EXACT** qualifier without the **/SEARCH** qualifier, exact search mode is enabled when you set the search string with the Find (**E1**) key.

**/FILES**

Displays information about the use of each paging and swapping file currently installed.

**/FULL**

When used with **/POOL**, displays additional information about pool area.

When used with **/CACHE**, displays additional information about the file data cache that is loaded (either VIOC or XFC).

This qualifier is ignored unless the **/CACHE** or **/POOL** qualifier is specified explicitly.

**/GH\_REGIONS**

On Alpha, displays information about the granularity hint regions (GHR) that have been established. For each of these regions, information is displayed about the size of the region, the amount of free memory, the amount of memory in use, and the amount of memory released to OpenVMS from

the region. The granularity hint regions information is also displayed as part of **SHOW MEMORY**, **SHOW MEMORY/ALL**, and **SHOW MEMORY/FULL** commands.

### **/HIGHLIGHT[=*keyword*]**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify the type of highlighting you want when a search string is found. When a string is found, the entire line is highlighted. You can use the following keywords: **BOLD**, **BLINK**, **REVERSE**, and **UNDERLINE**. **BOLD** is the default highlighting.

### **/OUTPUT[=*filespec*]**

#### **/NOOUTPUT**

Controls where the output of the command is sent. If you do not enter the qualifier, or if you enter the **/OUTPUT** qualifier without a file specification, the output is sent to the current process default output stream or device, identified by the logical name SYS\$OUTPUT.

If you enter the **/OUTPUT** qualifier with a partial file specification (for example, specifying only a directory), **SHOW** is the default file name and **.LIS** the default file type. If you enter a file specification, it cannot include asterisk (\*) and the percent sign (%) wildcard characters.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

### **/PAGE[=*keyword*]**

#### **/NOPAGE (default)**

Controls the display of memory information on the screen.

You can use the following keywords with the **/PAGE** qualifier:

Keyword	Description
<b>CLEAR_SCREEN</b>	Clears the screen before each page is displayed.
<b>SCROLL</b>	Displays information one line at a time.
<b>SAVE[=<i>n</i>]</b>	Enables screen navigation of information, where <i>n</i> is the number of pages to store.

The **/PAGE=SAVE** qualifier allows you to navigate through screens of information. The **/PAGE=SAVE** qualifier stores up to 5 screens of up to 255 columns of information. When you use the **/PAGE=SAVE** qualifier, you can use the following keys to navigate through the information:

Key Sequence	Description
<b>Up</b> arrow key, <b>Ctrl/B</b>	Scroll up one line.
<b>Down</b> arrow key	Scroll down one line.
<b>Left</b> arrow key	Scroll left one column.
<b>Right</b> arrow key	Scroll right one column.
<b>Find (E1)</b>	Specify a string to find when the information is displayed.
<b>Insert Here (E2)</b>	Scroll right one half screen.
<b>Remove (E3)</b>	Scroll left one half screen.

Key Sequence	Description
Select ( <b>E4</b> )	Toggle 80/132 column mode.
Prev Screen ( <b>E5</b> )	Get the previous page of information.
Next Screen ( <b>E6</b> ), <b>Return</b> , <b>Enter</b> , <b>Space</b>	Get the next page of information.
<b>F10</b> , <b>Ctrl/Z</b>	Exit. (Some utilities define these differently.)
Help ( <b>F15</b> )	Display utility help text.
Do ( <b>F16</b> )	Toggle the display to oldest/newest page.
<b>Ctrl/W</b>	Refresh the display.

The **/PAGE** qualifier is not compatible with the **/OUTPUT** qualifier.

### **/PHYSICAL\_PAGES**

Displays information about the amount of physical memory and the number of free and modified pages.

### **/POOL**

Displays information about the usage of each dynamic memory (pool) area, including the amount of free space and the size of the largest contiguous block in each area.

### **/RESERVED (Alpha/Integrity servers only)**

Displays information about memory reservations.

### **/SEARCH="string"**

Use with the **/PAGE=SAVE** qualifier to specify a string that you want to find in the information being displayed. Quotation marks are required for the **/SEARCH** qualifier, if you include spaces in the text string.

You can also dynamically change the search string by pressing the Find key (**E1**) while the information is being displayed. Quotation marks are not required for a dynamic search.

### **/SLOTS**

Displays information about the availability of partition control block (PCB) vector slots and balance slots.

### **/UNITS=keyword**

Allows you to override the current default specified by **SET PROCESS/UNITS** so that you can display memory in your choice of blocks or bytes.

Keyword options are:

Option	Description
BLOCKS	Displays memory in blocks (equivalent to PAGES).
BYTES	Displays memory in bytes.

Option	Description
PAGES	Displays memory in page format (equivalent to BLOCKS).

**/WRAP****/NOWRAP (default)**

Use with the **/PAGE=SAVE** qualifier to limit the number of columns to the width of the screen and to wrap lines that extend beyond the width of the screen to the next line.

The **/NOWRAP** qualifier extends lines beyond the width of the screen and can be seen when you use the scrolling (left and right) features provided by the **/PAGE=SAVE** qualifier.

## Examples

### 1. \$ SHOW MEMORY

```

System Memory Resources on 20-JAN-2001 15:22:04.11
Physical Memory Usage (pages):   Total       Free       In Use   Modified
Main Memory (2.00Gb)           262144    201249     60162     733
Extended File Cache (Time of last reset: 18-JAN-2001 17:15:14.33)
  Allocated (Mbytes)           370.00   Maximum size (Mbytes)   1024.00
  Free (Mbytes)                 317.79   Minimum size (Mbytes)   370.00
  In use (Mbytes)                52.20   Percentage Read I/Os      72%
  Read hit rate                  96%    Write hit rate             0%
  Read I/O count                 119363   Write I/O count           46259
  Read hit count                 115283   Write hit count            0
  Reads bypassing cache          45       Writes bypassing cache     0
  Files cached open              372     Files cached closed        392
  Vols in Full XFC mode          0       Vols in VIOC Compatible mode 3
  Vols in No Caching mode        0       Vols in Perm. No Caching mode 0
Granularity Hint Regions (pages): Total       Free       In Use   Released
Execlet code region             1024        0        586      438
Execlet data region              256        0        256        0
S0/S1 Executive data region      576        0        576        0
Resident image code region       1024        0        830      194
Slot Usage (slots):             Total       Free       Resident  Swapped
Process Entry Slots              647       614        33        0
Balance Set Slots                645       614        31        0
Dynamic Memory Usage:           Total       Free       In Use   Largest
Nonpaged Dynamic Memory (Mb)     4.28       2.38       1.89     2.25
Bus Addressable Memory (Kb)     168.00    128.00     40.00    128.00
Paged Dynamic Memory (Mb)        5.68       3.42       2.26     3.41
Lock Manager Dyn Memory (Mb)     1.13       0.00       1.12
Buffer Object Usage (pages):           In Use   Peak
32-bit System Space Windows (S0/S1)      3        3
64-bit System Space Windows (S2)         0        0
Physical pages locked by buffer objects    3        3
Memory Reservations (pages):   Group   Reserved   In Use   Type
VCC$MIN_CACHE_SIZE             ---     47360     47360   Allocated
Total (370.00 Mbytes reserved)         47360     47360
Swap File Usage (8KB pages):           Index   Free      Size
DISK$X6XV_BRAHMA: [SYS0.SYSEX] SWAPFILE.SYS
                                         1       5168     5168
Paging File Usage (8KB pages):           Index   Free      Size
DISK$X6XV_BRAHMA: [SYS0.SYSEX] PAGEFILE.SYS
                                         254    215288    215288
Total committed paging file usage:           7418

```

Of the physical pages in use, 4951 pages are permanently allocated to OpenVMS.

This example shows reservable pages. If the reservable pages are a negative value, this indicates that you may want to consider adding to the fixed amount of page file space available.

## 2. \$ SHOW MEMORY/CACHE/FULL

System Memory Resources on 3-NOV-2001 18:36:12.79

```
Extended File Cache (Time of last reset: 31-OCT-2001 10:18:07.39)
Allocated (Mbytes)      ❶370.00 Maximum size (Mbytes)    ❷1024.00
Free (Mbytes)          ❸319.75 Minimum size (Mbytes)   ❹ 370.0
In use (Mbytes)        ❺ 50.25 Percentage Read I/Os    ❻      98%
Read hit rate          ❼      79% Write hit rate          ❽      0%
Read I/O count         ❾ 18110 Write I/O count        ❿      310
Read hit count         11 14343 Write hit count       12      0
Reads bypassing cache  13      37 Writes bypassing cache  14      0
Files cached open      15      351 Files cached closed   16      307
Vols in Full XFC mode  17      0 Vols in VIOC Compatible mode 17 0
Vols in No Caching mode17      0 Vols in Perm No Caching mode 17 0
```

I/O Statistics 18 - Distributions (MAX\_IO\_SIZE: 127 19)

```
-----
Transfer Size:      Reads      Read Hits      Writes
  1 Block IO:      35053 20      34553 21      87 22
  2 Block IO:         469          284          9
  3 Block IO:      26516      26346          24
  4 Block IO:         348          205          6
  5 Block IO:      13205      13160          0
  6 Block IO:         161          111          0
  7 Block IO:         185          152          0
    .
    .
    .
114 Block IO:         1          0          0
116 Block IO:         2          1          0
121 Block IO:         1          0          0

>127<256 Block IO:      12          0
>255      Block IO:      14          0
-----
Totals:              84411      80535      630
```

## Note

This example shows the output for the **SHOW MEMORY/CACHE/FULL** command on an Alpha system with the Extended File Cache loaded. The **SHOW MEMORY/CACHE/FULL** command will display different fields on an Alpha system with the Virtual I/O Cache loaded.

## Extended File Cache Usage

Shows the use of the Extended File Cache facility on an Alpha system.

❶ Allocated	Total amount of system memory in megabytes allocated to the Extended File Cache.
❸ Free	Number of allocated megabytes not currently in use by the cache.

⑤ In use	Number of allocated megabytes that contain valid cached data.
⑦ Read hit rate	Shows cache read hits as a percentage of read I/Os.
⑨ Read I/O count	Total number of read I/Os that have been seen by the cache since the last statistics reset.
⑪ Read hit count	Total number of read I/Os that did not perform a physical I/O, because the data for these was found in the cache since the prior statistics reset.
⑬ Reads bypassing cache	Total number of reads that bypassed the cache and went directly to disk since the last statistics reset.
⑮ Files cached open	Total number of open files in cache.
② Maximum size (Mbytes)	Maximum size of the cache in megabytes.
④ Minimum size (Mbytes)	Minimum size of the cache in megabytes. This displays the value of the memory reservation, VCC\$MIN_CACHE_SIZE. See the relevant section in the <i>VSI OpenVMS System Manager's Manual, Volume 2: Tuning, Monitoring, and Complex Systems</i> [ <a href="https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-2-tuning-monitoring-and-complex-systems/#CACHE_MIN_SIZE_SEC">https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-2-tuning-monitoring-and-complex-systems/#CACHE_MIN_SIZE_SEC</a> ] for additional information.
⑥ Percentage Read I/Os	Percentage of read I/Os that occur. For example, a read/write I/O ratio of 100% implies that all were read I/Os.
⑧ Write hit rate	(Always zero for Extended File Cache, Version 1.)
⑩ Write I/O count	Total number of write I/Os that have been seen by the cache since the last statistics reset.
⑫ Write hit count	(Always zero for Extended File Cache, Version 1.)
⑭ Writes bypassing cache	Total number of writes that bypassed the cache and went directly to disk since the last statistics reset.
⑯ Files cached closed	Total number of closed files in cache.
⑰ Volume modes	Total number of volumes in each caching state. Note that the initial release of XFC only supports VIOC compatible mode. Future releases will support full mode.
⑱ I/O Statistics	Systemwide distribution of I/O sizes (rounded up).
⑲ MAX_IO_SIZE	Current setting of the system parameter VCC_MAX_IO_SIZE in blocks. The extended file cache (XFC) will only cache files up to this size.
⑳ Reads	Number of reads for the entire system.
㉑ Read Hits	Number of reads satisfied from the cache.
㉒ Writes	Number of writes for the entire system.

## 3. \$ SHOW MEMORY/CACHE=(VOLUME=\*)

System Memory Resources on 20-JAN-2001 15:35:32.51

## Extended File Cache Volume Statistics:

```

_7$DKA200: (DISK$X6XV_BRAHMA), Caching mode is VIOC Compatible
Open files           ①      372      Closed files           ②      395
Files ever opened    ③     1007      Files ever deposited    ④      240
Allocated pages      ⑤     6405      Locks acquired          ⑥      736

```

```

Total QIOs          ⑦ 166552      Read hits          ⑧ 115984
Virtual reads       ⑨ 120068      Virtual writes     ⑩ 46484
Hit rate           ⑪ 69 %        Read aheads       ⑫ 11766
Read throughs      ⑬ 120021      Write throughs    ⑭ 46484
Read arounds       ⑮ 47         Write arounds     ⑯ 0
Ave Disk I/O Resp Time incl cache hits (microseconds) ⑰ 3497

```

Total of 1 volumes in cache

### Extended File Cache Usage

Shows the use of the Extended File Cache facility on an Alpha system.

① Open files	Number of files that are currently open and cached by the extended file cache on this volume at the instant the SHOW command was issued.
③ Files ever opened	Number of times the extended file cache has been requested to open a file on this volume.
⑤ Allocated pages	Number of main memory data pages currently being used by the extended file cache to contain actual file data, for this volume.
⑦ Total QIOs	Total number of QIO and PAGE I/O calls received by the extended file cache on this volume.
⑨ Virtual reads	Cumulative number of Virtual Read requests received by the extended file cache on this volume.
⑪ Hit rate	Percentage of Total QIOs that were completed by copying data from cache, rather than issuing real I/O to a volume.
⑬ Read throughs	Number of Virtual Reads that are capable of being satisfied by the extended file cache.
⑮ Read arounds	Number of Virtual Reads that cannot be satisfied by the extended file cache. Reasons for this include the presence of a non-XFC compliant node in an OpenVMS cluster, and the receipt of an I/O that is larger than VCC_MAX_IO_SIZE.
② Closed files	Number of closed files the extended file cache has in memory. If a subsequent file access occurs, data will be accessible from main memory rather than having to issue I/O to the real volume.
④ Files ever deposited	Files removed from memory. Reasons the extended file cache may remove a file from its memory include requests for memory from the rest of the system, and conflicting access modes in a cluster.
⑥ Locks acquired	Current number of file access locks that are in use on this volume.
⑧ Read hits	Cumulative number of times a read has been satisfied from the data cache.
⑩ Virtual writes	Cumulative number of virtual write I/Os received on this volume by the cache.
⑫ Read aheads	Cumulative number of times the extended file cache issued read ahead I/Os on this volume after detecting sequential file I/O virtual reads.
⑭ Write throughs	Cumulative number of times a virtual write has been capable of modifying cached data.

⑩ Write arounds	Cumulative number of times a virtual write has been detected that cannot update data in cache memory.
⑪ Average Disk I/O Response Time	Average disk I/O response time, including cache hits, in microseconds. Note that on a symmetric multiprocessing (SMP) system, the response time only includes that of I/Os starting or finishing on the same CPU. Any physical I/Os are ignored.

#### 4. \$ SHOW MEMORY/CACHE=(VOL=DKA100,TOPQIO=3)

System Memory Resources on 3-NOV-2001 18:36:12.79

Extended File Cache Top QIO File Statistics:

\_\$7\$DKA200: (DISK\$X6Y0\_RESD), Caching mode is VIOC Compatible

\_\$7\$DKA200:[SYS0.SYSEXE]SYSDUMP.DMP;2 (open)

Caching is enabled, active caching mode is Write Through

Allocated pages	① 334	Total QIOs	② 1712
Read hits	③ 1559	Virtual reads	④ 1712
Virtual writes	⑤ 0	Hit rate	⑥ 91 %
Read aheads	⑦ 0	Read throughs	⑧ 0
Write throughs	⑨ 0	Read arounds	⑩ 0
		Write arounds	⑪ 0

\_\$7\$DKA200:[VMS\$COMMON.SYSEXE]SYS\$QUEUE\_MANAGER.QMAN\$JOURNAL;1 (open)

Caching is enabled, active caching mode is Write Through

Allocated pages	931	Total QIOs	1057
Read hits	5	Virtual reads	1044
Virtual writes	13	Hit rate	0 %
Read aheads	2	Read throughs	1044
Write throughs	13	Read arounds	0
		Write arounds	0

\_\$7\$DKA200:[VMS\$COMMON.SYSLIB]DECC\$SHR.EXE;1 (open)

Caching is enabled, active caching mode is Write Through

Allocated pages	135	Total QIOs	730
Read hits	673	Virtual reads	730
Virtual writes	0	Hit rate	0 %
Read aheads	2	Read throughs	0
Write throughs	0	Read arounds	0
		Write arounds	0

Total of 3 files for this volume

### Extended File Cache Top QIO File Statistics Usage

Shows the use of the Extended File Cache Top QIO File Statistics facility on an Alpha system.

① Allocated pages	Number of main memory data pages currently being used by the extended file cache to contain actual file data, for this volume
③ Read hits	Cumulative number of times a read has been satisfied from the data cache.
⑤ Virtual writes	Cumulative number of virtual write I/Os received on this volume by the cache.

<b>⑦</b> Read aheads	Cumulative number of times the extended file cache issued read ahead I/Os on this volume after detecting sequential file I/O virtual reads.
<b>⑨</b> Write throughs	Cumulative number of times a virtual write has been capable of modifying cached data.
<b>②</b> Total QIOs	Total number of QIO and PAGE I/O calls received by the extended file cache on this volume.
<b>④</b> Virtual reads	Cumulative number of Virtual Read requests received by the extended file cache on this volume.
<b>⑥</b> Hit rate	Percentage of Total QIOs that were completed by copying data from cache, rather than issuing real I/O to a volume.
<b>⑧</b> Read throughs	Number of Virtual Reads that are capable of being satisfied by the extended file cache.
<b>⑩</b> Read arounds	Number of Virtual Reads that cannot be satisfied by the extended file cache. Reasons for this include the presence of a non-XFC compliant node in an OpenVMS cluster, and the receipt of an I/O that is larger than VCC_MAX_IO_SIZE.
<b>⑪</b> Write arounds	Cumulative number of times a virtual write has been detected that cannot update data in cache memory.

5. \$ SHOW MEMORY/CACHE=(VOL=DKA100, TOPHITRATE=3)

System Memory Resources on 3-NOV-2001 18:36:12.79

Extended File Cache Top Hitrate File Statistics:

\_\$\_\$DKA200: (DISK\$X6Y0\_RESD), Caching mode is VIOC Compatible

```

_$_$DKA200:[VMS$COMMON.SYSLIB]SMGSHR.EXE;1 (open)
Caching is enabled, active caching mode is Write Through
Allocated pages      ①    16      Total QIOs      ②    277
Read hits            ③    267      Virtual reads   ④    277
Virtual writes       ⑤     0      Hit rate      ⑥    96 %
Read aheads         ⑦     0      Read throughs ⑧    277
Write throughs      ⑨     0      Read arounds ⑩     0
                                   Write arounds ⑪     0

```

```

_$_$DKA200:[VMS$COMMON.SYSLIB]UTIL$SHARE.EXE;1 (open)
Caching is enabled, active caching mode is Write Through
Allocated pages      8      Total QIOs      185
Read hits            178     Virtual reads   185
Virtual writes       0      Hit rate      96 %
Read aheads         1      Read throughs 185
Write throughs      0      Read arounds  0
                                   Write arounds  0

```

```

_$_$DKA200:[VMS$COMMON.SYSLIB]CMA$TIS_SHR.EXE;1 (open)
Caching is enabled, active caching mode is Write Through
Allocated pages      6      Total QIOs      165
Read hits            159     Virtual reads   165
Virtual writes       0      Hit rate      96 %
Read aheads         2      Read throughs 165
Write throughs      0      Read arounds  0

```

Write arounds

0

Total of 3 files for this volume

**Extended File Cache Top Hit rate File Statistics Usage**

Shows the use of the Extended File Cache Top Hit rate File Statistics facility on an Alpha system.

❶ Allocated pages	.Number of main memory data pages currently being used by the extended file cache to contain actual file data, for this volume
❸ Read hits	Cumulative number of times a read has been satisfied from the data cache.
❺ Virtual writes	Cumulative number of virtual write I/Os received on this volume by the cache.
❷ Read aheads	Cumulative number of times the extended file cache issued read ahead I/Os on this volume after detecting sequential file I/O virtual reads.
❹ Write throughs	Cumulative number of times a virtual write has been capable of modifying cached data.
❷ Total QIOs	Total number of QIO and PAGE I/O calls received by the extended file cache on this volume.
❹ Virtual reads	Cumulative number of Virtual Read requests received by the extended file cache on this volume.
❻ Hit rate	Percentage of Total QIOs that were completed by copying data from cache, rather than issuing real I/O to a volume.
❽ Read throughs	Number of Virtual Reads that are capable of being satisfied by the extended file cache.
❿ Read arounds	Number of Virtual Reads that cannot be satisfied by the extended file cache. Reasons for this include the presence of a non-XFC compliant node in an OpenVMS cluster, and the receipt of an I/O that is larger than VCC_MAX_IO_SIZE.
❶ Write arounds	Cumulative number of times a virtual write has been detected that cannot update data in cache memory.

## 6. \$ SHOW MEMORY/CACHE=(FILE=SYS\$LOGIN:\*.\*,OPEN,CLOSED)

System Memory Resources on 3-NOV-2001 18:36:12.79

Extended File Cache Statistics:

```

_$7$DKA200:[SYS0.SYSMGR]ACCOUNTNG.DAT;1 (open)
Caching is enabled, active caching mode is Write Through
Allocated pages    ❶      1      Total QIOs        ❷      17
Read hits          ❸      0      Virtual reads    ❹      1
Virtual writes     ❺     16      Hit rate       ❻      0 %
Read aheads        ❷      0      Read throughs  ❸      0
Write throughs     ❹     16      Read arounds   ❿      0
                                   Write arounds   ❶      0

```

```

_$7$DKA200:[SYS0.SYSMGR]ACME$SERVER.LOG;129 (open)
Caching is enabled, active caching mode is Write Through

```

Allocated pages	1	Total QIOs	2
Read hits	0	Virtual reads	1
Virtual writes	1	Hit rate	0 %
Read aheads	0	Read throughs	1
Write throughs	1	Read arounds	0
		Write arounds	0

\_\$7\$DKA200:[SYS0.SYSMGR]CLUE\$STARTUP\_BRAHMA.LOG;935 (closed)

Caching is enabled, active caching mode is Write Through

Allocated pages	2	Total QIOs	32
Read hits	0	Virtual reads	0
Virtual writes	32	Hit rate	0 %
Read aheads	0	Read throughs	0
Write throughs	32	Read arounds	0
		Write arounds	0

.  
.  
.

\_\$7\$DKA200:[VMS\$COMMON.SYSMGR]VMS\$AUDIT\_SERVER.DAT;1 (open)

Caching is enabled, active caching mode is Write Through

Allocated pages	1	Total QIOs	8
Read hits	3	Virtual reads	8
Virtual writes	0	Hit rate	37 %
Read aheads	1	Read throughs	8
Write throughs	0	Read arounds	0
		Write arounds	0

Total of 50 files for this volume

### Extended File Cache Statistics Usage

Shows the use of the Extended File Cache Statistics facility on an Alpha system.

① Allocated pages	.Number of main memory data pages currently being used by the extended file cache to contain actual file data, for this volume
③ Read hits	Cumulative number of times a read has been satisfied from the data cache.
⑤ Virtual writes	Cumulative number of virtual write I/Os received on this volume by the cache.
⑦ Read aheads	Cumulative number of times the extended file cache issued read ahead I/Os on this volume after detecting sequential file I/O virtual reads.
⑨ Write throughs	Cumulative number of times a virtual write has been capable of modifying cached data.
② Total QIOs	Total number of QIO and PAGE I/O calls received by the extended file cache on this volume.
④ Virtual reads	Cumulative number of Virtual Read requests received by the extended file cache on this volume.
⑥ Hit rate	Percentage of Total QIOs that were completed by copying data from cache, rather than issuing real I/O to a volume.

⑧ Read throughs	Number of Virtual Reads that are capable of being satisfied by the extended file cache.
⑩ Read arounds	Number of Virtual Reads that cannot be satisfied by the extended file cache. Reasons for this include the presence of a non-XFC compliant node in an OpenVMS cluster, and the receipt of an I/O that is larger than VCC_MAX_IO_SIZE.
⑪ Write arounds	Cumulative number of times a virtual write has been detected that cannot update data in cache memory.

## 7. \$ SHOW MEMORY/PHYSICAL\_PAGES

```

                System Memory Resources on  3-NOV-2001 16:11:30.76
Physical Memory Usage (pages): Total ①  Free ②  In Use ③  Modified ④
Main Memory (32.00Mb)           65536  44233    20955      308

```

Of the physical pages in use, 10970 pages are permanently allocated to VMS.

### Physical Memory Usage

Shows the use of physical memory.

① Total	Number of physical memory pages available for general system use. Multiport memory pages used for shared memory global sections, mailboxes, and common event blocks are not included in this number.
② Free	Number of pages on the free page list.
③ In Use	Number of pages currently being used. This number is calculated by adding the number of pages on the free, modified, and bad lists and then subtracting that sum from the total number of available pages.
④ Modified	Number of pages on the modified page list.

### Bad Page List

#### Note

This display is written only when there are pages on the bad page list.

Shows the contents of the bad page list.

Total	Number of pages on the bad page list.
Dynamic	Number of memory errors detected after the system was booted.
I/O Errors	Number of errors detected during page fault handling.
Static	Number of memory errors detected during boot-time scan.

By default, either single-bit or double-bit errors cause the pages to be removed during the boot-time scan.

### Pages Allocated to OpenVMS

Any **SHOW MEMORY** display that includes the physical memory display concludes with the number of pages permanently allocated to the OpenVMS system. These pages include nonpaged executive

code and data, the PFN database, nonpaged dynamic memory, the interrupt stack, and the system page table.

#### 8. \$ SHOW MEMORY/SLOTS

```

                System Memory Resources on 3-NOV-2001 16:11:35.31
Slot Usage (slots):      Total ❶   Free ❷   Resident ❸   Swapped ❹
Process Entry Slots      75       28       46         1
Balance Set Slots       70       26       44         0

```

##### Slot Usage (slots)

Displays the use of process entry slots and balance set slots.

❶ Total	Number of process entry slots (the value of the system parameter MAXPROCESSCNT) and balance set slots (the value of the system parameter BALSETCNT) permanently allocated when the system was bootstrapped.
❷ Free	Number of slots currently available.
❸ Resident	Number of slots currently used by memory-resident processes. The number of balance set slots in use can never be any larger than the number of process entry slots in use because the SWAPPER and NULL processes have process entry slots but do not require balance set slots.
❹ Swapped	Number of slots used by outswapped processes. For process entry slots, this number includes all processes that have been partially outswapped. For balance set slots, this number includes those processes that have had their process bodies outswapped but have process headers that are still resident.

#### 9. \$ SHOW MEMORY/POOL

```

                System Memory Resources on 5-DEC-2001 03:59:35.29
Dynamic Memory Usage (bytes):  Total ❶   Free ❷   In Use ❸   Largest ❹
Nonpaged Dynamic Memory      24993792  23511872  1481920  23363776
Bus Addressable Memory        131072    114688    16384    114688
Paged Dynamic Memory          5799936  3530784  2269152  3530176
Lock Manager Dynamic Memory  1048576   254976   793600

```

##### Dynamic Memory Usage (in bytes)

Shows the use of the nonpaged and paged pool areas that allocate variably sized blocks.

❶ Total	Total number of bytes set aside for each area.
❷ Free	Total amount of free space in each dynamic memory area.
❸ In Use	Amount of space currently allocated from each area. This number is the total size minus the number of free bytes.
❹ Largest	Size of the largest contiguous block in each area. For the paged pool, this number represents the largest block that can be allocated. For the nonpaged pool, an allocation request larger than this number will cause the nonpaged pool to grow (if other constraints allow growth).

This attribute does not apply to the lock manager, as all items for the lock manager are the same size.
---

## 10. \$ SHOW MEMORY/POOL/FULL

System Memory Resources on 5-DEC-2001 03:59:35.29

```

Nonpaged Dynamic Memory                                (Lists + Variable)
Current Size (bytes)  ❶ 24993792 Current Size (pagelets)  ❶ 48816
Initial Size (NPAGEDYN) ❷ 24993792 Initial Size (pagelets) ❷ 48816
Maximum Size (NPAGEVIR) ❸ 499998720 Maximum Size (pagelets) ❸ 976560
Free Space (bytes) ❹ 22230144 Space in Use (bytes) ❺ 2763648
Largest Variable Block ❻ 19676672 Smallest Variable Block ❼ 2176
Number of Free Blocks ❸ 38334 Free Blocks LEQU 64 Bytes ❾ 0
Free Blocks on Lookasides ❿ 38330 Lookaside Space (bytes) 2537472

Bus Addressable Memory                                (Lists + Variable)
Current Size (bytes) ❶ 131072 Current Size (pagelets) ❶ 256
Initial Size (NPAGEDYN) ❷ 131072 Initial Size (pagelets) ❷ 256
Free Space (bytes) ❹ 114688 Space in Use (bytes) ❺ 16384
Largest Variable Block ❻ 114688 Smallest Variable Block ❼ 114688
Number of Free Blocks ❸ 1 Free Blocks LEQU 64 Bytes ❾ 0
Free Blocks on Lookasides ❿ 0 Lookaside Space (bytes) 0

Paged Dynamic Memory                                (Lists + Variable)
Current Size (MB) ❶ 22.88 Current Size (pagelets) ❶ 46864
Free Space (MB) ❹ 21.96 Space in Use (MB) ❺ 0.91
Largest Variable Block ❻ 21.77 Smallest Variable Block (MB) ❼ 21.77
Number of Free Blocks ❸ 166 Free Blocks LEQU 64 Bytes ❾ 4
Free Blocks on Lookasides ❿ 165 Lookaside Space (KB) 201.85
Over-limit Lookaside Blocks ⓫ 3 Over-limit Space (KB) 7.45

Lock Manager Dynamic Memory
Current Size (Mbytes) ❶ 13.85 Current Size (pages) ❶ 1774
Free Space (Mbytes) ❹ 10.06 Hits ❷ 54050
Space In Use ❺ 3.79 Misses ❸ 1664
Number of Empty Pages ❷ 26 Expansions ❹ 1792
Number of Free Packets ❸ 41244 Packet Size ❶ 256

```

**Dynamic Memory**

Shows the use of dynamic memory areas consisting of variably sized blocks.

❶ Current Size	Current size (in 512-byte pagelets on Alpha ) of each dynamic memory area. For the lock manager display, the unit of measurement is megabytes.
❷ Initial Size	Initial size of nonpaged dynamic memory and the name of the system parameter (NPAGEDYN) that controls this size.
❸ Maximum Size	Maximum size to which nonpaged dynamic memory can grow and the name of the system parameter (NPAGEVIR) that controls this size.
❹ Free Space	Amount of free space in each dynamic memory area.
❺ Space in Use	Amount of space currently allocated from each area.
❻ Largest Block	Size of the largest contiguous area in each pool area.

⑦ Smallest Block	Size of the smallest hole (free block) in each pool area.
⑧ Free Blocks	Total number of free blocks in each pool area. The size of this number is a measure of pool fragmentation.
⑨ Blocks LEQU 64	Number of free blocks that are 64 bytes long or shorter. This number is another measure of pool fragmentation because while allocation of these small blocks is unlikely, they contribute to the allocation time whenever an allocation request is made.
⑩ Empty Pages	Number of pages that do not have any packets allocated.
⑪ Free Packets	Total number of packets not in use. This number is the sum of free packets from partially used pages and the packets of all Empty Pages.
⑫ Hits	Total number of packet allocations.
⑬ Misses	Total number of packet allocation requests that could not be satisfied because the number of packets requested were not available. A miss causes dynamic memory to expand by one page to satisfy the packet allocation request.
⑭ Expansions	Total number of times that dynamic memory increased by a page to satisfy packet allocation requests.
⑮ Packet Size	Packet size of 256 bytes, which is used by the lock manager to hold either a lock block data structure or a resource block data structure.
⑯ Lookasides Free Blocks	Total number of memory packets placed on "lookaside lists". If a packet of the correct size is on a lookaside list, it can be allocated very quickly and efficiently, however, it cannot then be used as part of any other size packet. An excess of packets on the lookaside list can be a cause for the inability to allocate other sizes.
⑰ Over-limit Lookaside Blocks	Total number of memory packets that exist on "lookaside lists" that are no longer actively used because the SYSGEN parameter PAGED_LAL_SIZE was lowered. These packets will be available for use again if the SYSGEN parameter is increased to include them, or if there was a paged pool shortage and they are reclaimed. If there are no lookaside list packets on these "over-limit" lists then this line will not appear.

## 11. \$ SHOW MEMORY/FILES

```

System Memory Resources on 22-MAY-2001 19:04:19.67
Swap File Usage (8KB pages):
Disk$ALPHASYS:[SYS48.SYSEXE]SWAPFILE.SYS      Index ①    Free    Size
Disk$SWAP:[SYS48.SYSEXE]SWAPFILE.SYS;1        2        1048   1048

Total size of all swap files:                    1952

Paging File Usage (8KB pages):
Disk$PAGE:[SYS48.SYSEXE]PAGEFILE.SYS;1        Index ②    Free    Size
Disk$ALPHASYS:[SYS48.SYSEXE]PAGEFILE.SYS      254       16888  16888

Total size of all paging files:                  33776
Total committed paging file usage: ③           1964

```

### Paging File Usage (in blocks)

Shows the usage of paging and swapping files.

❶ Swap File Usage	Number of swap files. Begins with an index value of 1 and increases in count.
❷ Paging File Usage	Number of page files. Begins with an index value of 254 and decreases in count.
❸ Total Paging File Usage	Total committed page file usage. As in previous releases, more pages can reside in page-file sections systemwide than would fit into installed page files.

## SHOW NETWORK

SHOW NETWORK — Displays information about network services registered on a node.

### Format

**SHOW NETWORK** [*network-service*]

### Parameter

*network-service*

Specifies a network service for which you want to display information.

If you do not specify a service, the **SHOW NETWORK** command displays information about all services that are currently registered on the local node.

### Description

The **SHOW NETWORK** command displays information about network services available on an OpenVMS system.

### Qualifiers

**/FULL**

Displays all the information for the specified network service.

**/OLD**

If you are running DECnet Phase IV, retains the behavior of the **SHOW NETWORK** command prior to OpenVMS Version 7.0. If the local node is a routing node, the **/OLD** qualifier provides routing information.

**/OUTPUT[=*filespec*]**

**/NOOUTPUT**

Controls where the output of the command is sent. By default, the output of the **SHOW NETWORK** command is sent to the current SYS\$OUTPUT device (usually your terminal).

The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

## Examples

### 1. \$ SHOW NETWORK

```
Product:  DECNET Node:  VADIR                      Address(es):  24.365
Product:  TCP/IP Node:  vadir.lkr.dec.com Address(es):  161.114.99.17
```

This command was executed on a system running DECnet Phase V and TCP/IP. It indicates that the DECNET and "TCP/IP" network-service parameters are valid for this system.

### 2. \$ SHOW NETWORK "TCP/IP"

```
Product: TCP/IP  Node: vadir.lkr.dec.com  Address(es):  161.114.99.17
```

When the TCP/IP network-service parameter is used, it must be enclosed in enclosed in quotes because it contains a slash.

### 3. \$ SHOW NETWORK/FULL DECNET

```
Product:  DECNET                      Manufacturer:  Hewlett-Packard
Enterprise Company
Node:  CRAP1                          Address(es):  17.51
Network Type:  DNA IV                  Interface(s):  net 0
```

Node Volatile Characteristics as of 8-OCT-2009 09:15:12

Executor node = 17.51 (CRAP1)

```
Identification          = HPE DECnet for OpenVMS I64
Management version      = V4.0.0
Incoming timer           = 45
Outgoing timer           = 60
Incoming Proxy           = Enabled
Outgoing Proxy           = Enabled
NSP version              = V4.1.0
Maximum links            = 32
Delay factor             = 80
Delay weight             = 5
Inactivity timer         = 60
Retransmit factor        = 10
Routing version          = V2.0.0
Type                     = nonrouting IV
Routing timer            = 600
Broadcast routing timer  = 180
Maximum address          = 1023
Maximum circuits         = 16
Maximum cost             = 1022
Maximum hops             = 30
Maximum visits           = 63
Maximum area             = 63
Max broadcast nonrouters = 64
Max broadcast routers    = 32
Maximum path splits      = 1
Area maximum cost        = 1022
Area maximum hops        = 30
Maximum buffers          = 100
Buffer size              = 576
```

```
Default access          = incoming and outgoing
Pipeline quota          = 4032
Alias maximum links      = 32
Path split policy        = Normal
Maximum Declared Objects = 31
```

Known Link Volatile Summary as of 8-OCT-2009 09:15:12

No information in database

Node Counters as of 8-OCT-2009 09:15:12

Executor node = 17.51 (CRAP1)

```
856 Seconds since last zeroed
471 Bytes received
468 Bytes sent
27 Messages received
28 Messages sent
1 Connects received
1 Connects sent
0 Response timeouts
0 Received connect resource errors
2 Maximum logical links active
0 Aged packet loss
0 Node unreachable packet loss
0 Node out-of-range packet loss
0 Oversized packet loss
0 Packet format error
0 Partial routing update loss
0 Verification reject
```

The DECNET network-service parameter is used to signify either DECnet Phase IV or DECnet Phase V. Use the **/FULL** qualifier to determine the DECnet phase on the node. This is an example from a system running DECnet Phase IV.

#### 4. \$ SHOW NETWORK/FULL DECNET

```
Product:  DECNET      Manufacturer:  HPE
Node:     VADIR       Address(es):   24.365
Network Type:  DNA V   Interface(s):  net 0
```

```
Node 0
at 2002-01-16-12:50:30.528-05:00Iinf
```

Identifiers

```
Name          = DEC:.XPR.VADIR
Address        =
{
(
  [ DNA_CMIP-MICE ] ,
  [ DNA_SessionControlV3 , number = 19 ] ,
```

```

    [ DNA_OSIttransportV1 , 'DEC0'H ] ,
    [ DNA_OSInetwork , 49::00-18:AA-00-04-00-6D-61:21 ]
) ,
(
    [ DNA_CMIP-MICE ] ,
    [ DNA_SessionControlV3 , number = 19 ] ,
    [ DNA_OSIttransportV1 , 'DEC0'H ] ,
    [ DNA_OSInetwork , 49::00-18:AA-00-04-00-12-60:21
(DEC:.XPR.BULEAA) ]
) ,
(
    [ DNA_CMIP-MICE ] ,
    [ DNA_SessionControlV2 , number = 19 ] ,
    [ DNA_OSIttransportV1 , 'DEC0'H ] ,
    [ DNA_IP , 161.114.99.17 ]
) ,
(
    [ DNA_CMIP-MICE ] ,
    [ DNA_SessionControlV3 , number = 19 ] ,
    [ DNA_NSP ] ,
    [ DNA_OSInetwork , 49::00-18:AA-00-04-00-6D-61:20 ]
) ,
(
    [ DNA_CMIP-MICE ] ,
    [ DNA_SessionControlV3 , number = 19 ] ,
    [ DNA_NSP ] ,
    [ DNA_OSInetwork , 49::00-18:AA-00-04-00-12-60:20
(DEC:.XPR.BULEAA) ]
)
}

```

## Status

```

UID                = 562B4000-43CF-11CF-8001-AA0004007E10
State              = On
Functions Enabled  =
{
    Address Watcher ,
    CMIP Listener
}
ID                = 00-00-F8-01-FD-62

```

## Characteristics

```

Version            = T5.0.3
Implementation     =
{
    [
        Name = OpenVMS AXP ,
        Version = "V7.2-1 "
    ] ,
    [
        Name = HPE DECnet-Plus for OpenVMS ,
        Version = "V7.2-1 ECO03 31-MAY-2001 16:54:53.36"
    ]
}
Script Location    = <Default value>
Maximum Listeners  = 0

```

```
Listener Template      = <Default value>
Secondary Names        =
{
}
```

This example is from a system running DECnet Phase V.

#### 5. \$ SHOW NETWORK/OLD

```
OpenVMS Network status for local node 12.378 EMARET on 16-JAN-2002
14:46:35.64
```

This is a nonrouting node, and does not have any network information.  
The designated router for EMARET is node 12.1023 A12LKR.

The **/OLD** qualifier can be used only on a system running DECnet Phase IV.

## SHOW PRINTER

SHOW PRINTER — Displays the current settings for a printer.

### Format

```
SHOW PRINTER device-name[:]
```

### Parameter

*device-name*[:]

Specifies the name of the printer for which settings are to be displayed.

### Description

The **SHOW PRINTER** command displays the settings that are currently defined for the specified printer. Settings include the following:

Printer type	Form feed
Page width	Case
Page length	Character translation
Line termination type	Wrapping

Printer settings are established by the **SET PRINTER** command. You must have OPER (operator) privilege to use the **SET PRINTER** command.

### Qualifiers

```
/OUTPUT[=filespec]  
/NOOUTPUT
```

Controls where the output of the command is sent. By default, the output of the **SHOW PRINTER** command is sent to the current SY\$OUTPUT device (usually your terminal). To send the output to a file, use the **/OUTPUT** qualifier followed by a file specification.

The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification. If you enter a partial file specification (for example, specifying only a directory), **SHOW** is the default file name and **.LIS** is the default file type.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

## **/IDSTRING**

Returns the USB printer ID string as a text string and displays it on your screen. This information appears at the end of the typical **SHOW PRINTER** command display.

## **/SERIALNUM**

Returns the USB printer serial number as a text string and displays to the screen. The USB printer returns the serial number in Unicode format, and this is converted to ASCII text before being displayed.

# Examples

### 1. \$ SHOW PRINTER LPA0:

```
Printer LPA0:, device type LP11, is online, allocated, spooled
Error count           0   Operations completed           880
Owner process  "SYMBIONT_0001"  Owner UIC                [0,0]
Owner process ID      21C0008D  Dev Prot   S:RWLP,O:RWLP,G:RWLP,W:RWLP
Reference count       2   Default buffer size           132
Page width           132   Page Length                 66
No Carriage_return    Formfeed           Lowercase
No Passall            No Wrap             Printall
No Fallback           No Tab              Truncate
No Sixels             No Bitmapped        No Polled
Unidirectional
Intermediate device: STAR$DUA1:
Associated queue: LN01$PRINT
```

The **SHOW PRINTER** command in this example displays the settings for the printer LPA0.

### 2. \$ SHOW PRINTER LPA0/IDSTRING

```
Printer LPA0:, device type PC printer, is online, record-oriented
device, carriage control.
Error count           0   Operations completed           0
Owner process         ""   Owner UIC                [SYSTEM]
Owner process ID      00000000  Dev Prot   S:RWPL,O:RWPL,G,W
Reference count       0   Default buffer size           132
Page width           132   Page Length                 66
No Carriage_return    Formfeed           Uppercase
No Passall            No Wrap             No Printall
No Fallback           No Tab              Truncate
No Sixels             No Bitmapped        Polled
Unidirectional
IDString:
  MFG:                HEWLETT-PACKARD;
  MDL:                DESKJET 895C;
  CMD:                MLC,PCL,PML;
  CLASS:              PRINTER;
  DESCRIPTION:        Hewlett-Packard DeskJet 895C;
  SERN:               MX88P2V0VWGO;
```

```
VSTATUS:                                $HB0$FC0,ff,DN,IDLE,CUT;
```

The **SHOW PRINTER/IDSTRING** command in this example displays the ID string for the printer LPA0.

```
3. $ SHOW PRINT LPA0/IDSTRING
Printer LRA0:, device type LP11, is online, record-oriented device,
carriage control.
Error count                0      Operations completed                0
Owner process              ""      Owner UIC                      [SYSTEM]
Owner process ID           00000000 Dev Prot                    S:RWPL,O:RWPL,G,W
Reference count            0      Default buffer size          132
Page width                 132    Page Length                   66
No Carriage_return        Formfeed      Uppercase
No Passall                No Wrap        No Printall
No Fallback               No Tab          Truncate
No Sixels                 No Bitmapped      No Polled
Unidirectional
%SYSTEM-F-DEVOFFLINE, device is not in configuration or not available
```

If the device has been disconnected and marked offline, the **SHOW PRINTER/IDSTRING** command displays this information.

If the attempt to read the ID string should fail (for an unknown reason other than device disconnection), the reference to the ID string appears as:

```
%SHOW-W-NOIDSTRING, ID String could not be retrieved
```

```
4. $ SHOW PRINT LPA0/SERIALNUM
Printer LPA0:, device type PC printer, is online, record-oriented
device, carriage control.
Error count                0      Operations completed                0
Owner process              ""      Owner UIC                      [SYSTEM]
Owner process ID           00000000 Dev Prot                    S:RWPL,O:RWPL,G,W
Reference count            0      Default buffer size          132
Page width                 132    Page Length                   66
No Carriage_return        Formfeed      Uppercase
No Passall                No Wrap        No Printall
No Fallback               No Tab          Truncate
No Sixels                 No Bitmapped      Polled
Unidirectional
Serial Number:            MX88P2V0VWGO
```

The **SHOW PRINTER/SERIALNUM** command in this example displays the serial number for the printer LPA0.

If the device has been disconnected and marked offline, the **SHOW PRINTER/SERIALNUM** command replaces the reference to the serial number with the following message:

```
%SYSTEM-F-DEVOFFLINE, device is not in configuration or not available
```

If the ID string is not supported by the USB printer in question, the reference to the ID string will appear as:

```
%SHOW-W-NOSERIALNUM, Serial number could not be retrieved
```

# SHOW PROCESS

SHOW PROCESS — Displays information about a process and its subprocesses. **Requires GROUP privilege to show other processes in the same group. Requires WORLD privilege to show processes outside your group.**

## Format

SHOW PROCESS [*node-name::*]*process-name*]

## Parameters

*node-name::*

The name of the node on which the specified process is running.

You must specify a node name on the same OpenVMS Cluster on which the current process is running.

*process-name*

The name of the process about which information is to be displayed. The process name can have up to 15 alphanumeric characters.

The specified process name must be in the same group as the current process.

## Description

The **SHOW PROCESS** command displays information about a process and its subprocesses. If no qualifier is entered, only the following subset of information is displayed:

Time  
Process terminal  
User name and user identification code (UIC)  
Node name  
Process name and process identification (PID)  
Priority  
Default directory  
Allocated devices  
Number of kernel threads

A local process name can look like a remote process name; therefore, if you specify ATHENS::SMITH, the system checks for a process named ATHENS::SMITH on the local node before checking node ATHENS for a process named SMITH.

You also can use the **/IDENTIFICATION=*pid*** qualifier to specify a process name. If you use the **/IDENTIFICATION** qualifier and the *process-name* parameter together, the qualifier overrides the parameter. If you do not specify either the *process-name* parameter or the **/IDENTIFICATION** qualifier, information is displayed for the current process.

If you have GROUP or WORLD privilege, you can display information about processes other than your own. With GROUP privilege you can look at other processes in your group. With WORLD privilege you can look at processes outside of your group. You must use the **/IDENTIFICATION** qualifier to look at processes outside of your group.

## Qualifiers

### /ACCOUNTING

Shows the resources used by the process.

### /ALL

Displays the basic subset of information as well as information about:

- Accounting
- Dynamic memory use
- Privileges
- Quotas
- Shelving
- Subprocesses
- Wildcard status

### /CASE\_LOOKUP

Lists the active case sensitivity setting in your process (either BLIND or SENSITIVE).

VSI strongly recommends that you use caution when enabling case sensitivity in your processes.

See the relevant section in the [Guide to OpenVMS File Applications \[https://docs.vmssoftware.com/guide-to-openvms-file-applications/\]](https://docs.vmssoftware.com/guide-to-openvms-file-applications/) [https://docs.vmssoftware.com/guide-to-openvms-file-applications/#UPPER\_LOWER\_LETTERS] for additional information.

### /CONTINUOUS

Displays continuously updated information about the local process in an OpenVMS environment. You cannot use the **/CONTINUOUS** qualifier to display information about a process on another node in a cluster environment.

While the continuous display is running, you can press the following keys to customize the output display:

Key	Action
<b>E</b>	Exits the continuous display.
<b>Q</b>	Dynamically displays process quotas.
<b>T</b>	Displays information for threads in the process. Press the <b>T</b> key repeatedly to cycle through multiple threads.
<b>V</b>	Displays a map of the pages in the virtual address space of the process.  Each character displayed in the map represents the type of page. If the current program counter is in the page, the page type is indicated by an at sign (@). Pages locked in the working set are indicated by the letter L. Global pages are indicated by the letter G. Other valid pages in the working set are indicated by an asterisk (*).
<b>Space</b>	Returns to the default display.

The **/CONTINUOUS** qualifier cannot be used with the **/OUTPUT** qualifier.

**/DUMP**

Displays the image dump setting which is set or cleared by the **SET PROCESS/DUMP** command.

**/EXACT**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify a search string that must match the search string exactly and must be enclosed with quotation marks (" ").

If you specify the **/EXACT** qualifier without the **/SEARCH** qualifier, exact search mode is enabled when you set the search string with the Find (**E1**) key.

**/HIGHLIGHT[=*keyword*]**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify the type of highlighting you want when a search string is found. When a string is found, the entire line is highlighted. You can use the following keywords: BOLD, BLINK, REVERSE, and UNDERLINE. BOLD is the default highlighting.

**/IDENTIFICATION=*pid***

Requires GROUP or WORLD privilege to access processes other than your own.

Displays information about the process with the specified process identification (PID). The PID is assigned by the system when the process is created. When you specify a PID, you can omit the leading zeros.

If you specify the **/IDENTIFICATION** qualifier, it overrides the *process-name* parameter. If, in addition, you specify the **/MEMORY** qualifier, the PID value must be that of the current process.

**/INTERVAL=*n***

Use with the **/CONTINUOUS** qualifier to update the information at the specified number of seconds.

**/MEMORY**

Displays the process's use of dynamic memory areas. The **/MEMORY** qualifier is allowed only for the current process.

**/OUTPUT[=*filespec*]****/NOOUTPUT**

Controls where the output of the command is sent. By default, the output of the **SHOW PROCESS** command is sent to the current SYS\$OUTPUT device (usually your terminal). To send the output to a file, use the **/OUTPUT** qualifier followed by a file specification.

The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification. If you enter a partial file specification (for example, specifying only a directory), SHOW is the default file name and .LIS is the default file type.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

The **/OUTPUT** qualifier is incompatible with the **/CONTINUOUS** qualifier.

**/PAGE[=*keyword*]**  
**/NOPAGE (default)**

Controls the display of process information on the screen.

You can use the following keywords with the **/PAGE** qualifier:

Keyword	Description
CLEAR_SCREEN	Clears the screen before each page is displayed.
SCROLL	Displays information one line at a time.
SAVE[= <i>n</i> ]	Enables screen navigation of information, where <i>n</i> is the number of pages to store.

The **/PAGE=SAVE** qualifier allows you to navigate through screens of information. The **/PAGE=SAVE** qualifier stores up to 5 screens of up to 255 columns of information. When you use the **/PAGE=SAVE** qualifier, you can use the following keys to navigate through the information:

Key Sequence	Description
Up arrow key, <b>Ctrl/B</b>	Scroll up one line.
Down arrow key	Scroll down one line.
Left arrow key	Scroll left one column.
Right arrow key	Scroll right one column.
Find ( <b>E1</b> )	Specify a string to find when the information is displayed.
Insert Here ( <b>E2</b> )	Scroll right one half screen.
Remove ( <b>E3</b> )	Scroll left one half screen.
Select ( <b>E4</b> )	Toggle 80/132 column mode.
Prev Screen ( <b>E5</b> )	Get the previous page of information.
Next Screen ( <b>E6</b> ), <b>Return</b> , <b>Enter</b> , <b>Space</b>	Get the next page of information.
<b>F10</b> , <b>Ctrl/Z</b>	Exit. (Some utilities define these differently.)
Help ( <b>F15</b> )	Display utility help text.
Do ( <b>F16</b> )	Toggle the display to oldest/newest page.
<b>Ctrl/W</b>	Refresh the display.

The **/PAGE** qualifier is not compatible with the **/OUTPUT** qualifier.

**/PRIVILEGES**

Displays current privileges and rights for the process. To display only privileges, also specify the **/NORIGHTS** qualifier. Use the **SET PROCESS/PRIVILEGES** command to enable process privileges on a system.

**/QUOTAS**

Displays, for each resource, either a quota or a limit. The values displayed for quotas reflect any quota reductions resulting from subprocess creation. The values displayed for limits reflect the resources available to a process at creation.

**/RAD**

Displays home resource affinity domain (RAD).

OpenVMS support for RADs is available on the Alpha GS series systems and Integrity server NUMA capable systems.

**/RIGHTS (default)****/NORIGHTS**

Displays the current rights for the specified process. Use the **/NORIGHTS** qualifier with the **/PRIVILEGES** qualifier to suppress the rights display.

**/SCHEDULING\_CLASS**

Displays the scheduling class of the specified process.

**/SEARCH="string"**

Use with the **/PAGE=SAVE** qualifier to specify a string that you want to find in the information being displayed. Quotation marks are required for the **/SEARCH** qualifier, if you include spaces in the text string.

You can also dynamically change the search string by pressing the Find key (**E1**) while the information is being displayed. Quotation marks are not required for a dynamic search.

**/SHELVING**

Displays whether the process automatically unshelves files.

**/SUBPROCESSES**

Displays the current subprocesses in hierarchical order.

**/SYMLINK**

The **SHOW PROCESS/ALL** and **SHOW PROCESS/SYMLINK** commands display the status of the symlink wildcard search mode.

**/TOKEN (Alpha/Integrity servers Only)**

Displays the current token size as either Traditional (255 bytes) or Extended (4000 bytes). (A token is any element in a command line that is bounded by spaces. For example, the command **COPY X.TXT Y.TXT** contains three tokens.) The token size is determined by the setting of bit 1 in the DCL\_CTLFLAGS system parameter. You can use the **SET PROCESS/TOKEN** command to change the token size.

**/UNITS**

Displays whether the process currently reports disk space in bytes or blocks. You can change this setting using **SET PROCESS/UNITS**.

**/WRAP****/NOWRAP (default)**

Use with the **/PAGE=SAVE** qualifier to limit the number of columns to the width of the screen and to wrap lines that extend beyond the width of the screen to the next line.

The **/NOWRAP** qualifier extends lines beyond the width of the screen and can be seen when you use the scrolling (left and right) features provided by the **/PAGE=SAVE** qualifier.

## Examples

### 1. \$ SHOW PROCESS OCALA::MALIK

```
14-DEC-2001 15:35:19.39  User: MALIK    Process ID: 28200364
                          Node: OCALA    Process name: MALIK
Terminal:                RTA5:
User identifier: [VMS,MALIK]
Base priority:          4
Default file spec: WORK5:[MALIK]
Devices allocated: RTA5:
```

The **SHOW PROCESS** command in this example is entered by the user MALIK. The system displays the subset of information for the owned process on node OCALA. The information includes the following:

- Date and time the **SHOW PROCESS** command is entered
- User name
- Process identification (PID) number
- Node name
- Process name
- Device name of the current SY\$INPUT device
- User identification code (UIC)
- Base execution priority
- Default device (only for processes on the same node)
- Default directory (only for current processes)
- Devices allocated to the process and volumes mounted, if any

### 2. \$ SHOW PROCESS/ACCOUNTING

```
14-DEC-2001 14:48:01.31  User: MALIK    Process ID: 28200364
                          Node: OCALA    Process name: "MALIK"

Accounting information:
Buffered I/O count:      4878  Peak working set size:      844
Direct I/O count:        1284  Peak virtual size:          1176
Page faults:             6100  Mounted volumes:           0
Images activated:         22
Elapsed CPU time:         0 00:01:20.51
Connect time:            0 04:06:03.75
```

The **SHOW PROCESS** command in this example displays the accounting statistics for the process. The values under "Peak working set size" and "Peak virtual size" are rendered and in pagelets on Alpha.

### 3. \$ SHOW PROCESS/PRIVILEGES

```
14-DEC-2001 14:59:28.53  User: MALIK    Process ID: 28200364
                          Node: OCALA    Process name: "MALIK"

Process privileges:
GROUP                    may affect other processes in same group
TMPMBX                   may create temporary mailbox
NETMBX                   may create network device
```

```
Process rights identifiers:
  INTERACTIVE
  DIALUP
```

The **SHOW PROCESS** command in this example displays the current privileges for the process.

4. \$ SHOW PROCESS/QUOTAS

```
14-DEC-2001 15:00:28.79  User: MALIK  Process ID:    28200364
                          Node: OCALA  Process name:  "MALIK"
```

```
Process Quotas:
Account name: VMS
CPU limit:                Infinite  Direct I/O limit:      6
Buffered I/O byte count quota: 17904  Buffered I/O limit:    6
Timer queue entry quota:    10      Open file quota:      31
Paging file quota:         24945    Subprocess quota:      8
Default page fault cluster:  64      AST limit:            14
Enqueue quota:             30      Shared file limit:     9
Max detached processes:    11      Max active jobs:      14
```

The **SHOW PROCESS** command in this example displays the available quotas and limits. The value under "Paging file quota" is rendered in pagelets on Alpha.

5. \$ SHOW PROCESS/SUBPROCESSES

```
14-DEC-2001 15:44:59.39  User: MALIK  Process ID:    28200364
                          Node: OCALA  Process name:  "MALIK_1"
```

Processes in this tree:

```
MALIK
  MALIK_1 (*)
  MALIK_2
```

The **SHOW PROCESS** command in this example shows the current process tree. The current process is indicated by the asterisk ( \* ). Processes both below and above the current process are shown.

6. \$ SHOW PROCESS/CONTINUOUS BOB

```
                                Process BOB                                12:26:53

State          CUR              Working set          269
Cur/base priority  8/4          Virtual memory      1713
Current PC       7FFEE07E        CPU time           00:00:13.82
Current PSL      03C00000        Direct I/O          246
Current user SP  7FF785A4        Buffered I/O        646
PID             226006C0        Page faults         3417
```

UIC	[VMS,BOB]	Event flags	C8000007
			C0000000
SYS\$SYSROOT:[SYSEXE]SHOW.EXE			

In this example, the /**CONTINUOUS** qualifier causes the display of information about process BOB to be updated continuously. Note that the Virtual pages heading appears on Alpha indicating the virtual memory used as a number of CPU-specific pages. The value displayed for "Working set" is also a number of CPU-specific pages.

#### 7. \$ SHOW PROCESS/CONTINUOUS CIMSERVER

```

                                Process CIMSERVER
07:38:02

      State                      LEF                      Working set
2599

      Cur/base priority          9/4                      Virtual pages
15135

      Current PC                  8065BDC0                  CPU time          0
00:00:14.33

      Current PSL                 00000000                  Direct I/O
5889

      Current user SP             7ACE6680                  Buffered I/O
88641

      PID                         20200822                  Page faults
1487

      UIC                         [SYSTEM]                  Event flags
C0000001

80000000

      $1$DGA02:[SYS0.SYSCOMMON.] [WBEM_SERVICES]CIMSERVER.EXE;1

```

[Press Q key]

```

                                Process CIMSERVER
07:38:18

      State                      LEF                      Working set
2599

      PID                         20200822                  Page faults
1487

      UIC                         [SYSTEM]                  Event flags
C0000001

80000000

```

```

# open files remaining          125/128          ( 97%)
Direct I/O count/limit         100/100          (100%)
Buffered I/O count/limit       99/100           ( 99%)
BUFIO byte count/limit         251840/251840      (100%)
ASTs remaining                 98/100           ( 98%)
Timer entries remaining         15/16           ( 93%)
PGFL quota count/limit         42408/43750      ( 96%)
ENQ quota count/limit          2048/2048      (100%)

```

```
$!$DGA02:[SYS0.SYSCOMMON.][WBEM_SERVICES]CIMSERVER.EXE;1
```

In this example, the standard continuous display is interrupted when the **Q** key is pressed. The display then dynamically changes to show the quotas in two columns: one column with the actual counts and another with percentages.

#### 8. \$ SHOW PROCESS/MEMORY

```

14-DEC-2001 14:59:04.48   User: MALIK   Process ID:   28200364
                           Node: OCALA   Process Name: "MALIK"

```

##### Process Dynamic Memory Area

```

Current Size (bytes)      25600   Current Total Size (pages)      50
Free Space (bytes)        22698   Space in Use (bytes)           2902
Size of Largest Block     22496   Size of Smallest Block         15
Number of Free Blocks       7     Free Blocks LEQU 32 Bytes       3

```

The **SHOW PROCESS** command in this example displays the use of dynamic memory areas for the current process, MALIK. These areas are described as follows:

Current size	Displays the current size in bytes and pagelets on Alpha of each dynamic memory area.
Free space	Displays the amount of free space in each dynamic memory area.
Space in use	Displays the amount of space currently allocated from each area.
Largest block	Displays the size of the largest contiguous area in each pool area.
Smallest block	Displays the size of the smallest free block in each pool area.
Free blocks	Displays the total number of free blocks in each pool area. The size of this number is a measure of pool fragmentation.
Blocks LEQU 32 Blocks LEQU 64 (Alpha)	Displays the number of free blocks that are 32 bytes or 64 bytes or shorter on Alpha. This number is another measure of pool fragmentation, because while allocation of these small blocks is unlikely, they contribute to the allocation time whenever an allocation request is made.

#### 9. \$ SHOW PROCESS REDSOX::RAMIREZ

```

27-OCT-2004 23:40:20.04   User: RAMIREZ   Process ID: 19182004
                           Node: REDSOX   Process name: RAMIREZ

```

```

Terminal:      RTA5:
User identifier: [VMS, RAMIREZ]
Base priority:  4
Default file spec: WORK5:[RAMIREZ]
Devices allocated: RTA5:

```

The **SHOW PROCESS** command in this example displays the basic subset of information for the process RAMIREZ on node REDSOX.

**10. \$ SHOW PROCESS/SHELVING LYONS**

```
15-JUNE-2001 10:07:25.11 User: LYONS      Process ID: 20206A50
                          Node: BANANA     Process name: "LYONS"
```

Auto-unshelve: on

The **SHOW PROCESS** command in this example shows that the LYONS process automatically unshelves files.

**11. \$ SHOW PROCESS/DUMP RALSTON**

```
31-DEC-2001 10:38:32.48 User: RALSTON    Process ID: 20C0011B
                          Node: AAAAAA     Process name: "_RTA1:"
```

Image Dump: on

The **SHOW PROCESS** command in this example shows that the image dump capability for the RALSTON process is enabled. This causes the contents of the address space to be written to the file named SYS\$LOGIN:(*image-name*).DMP (where the image name is the same as the file name) when an image terminates due to an unhandled error.

See the [SET PROCESS/DUMP](#) command for additional information.

**12. \$ SHOW/SYMLINK**

```
$ 17-SEP-2009 05:31:34.92 User: SYSTEM      Process ID:
20A0045C
                          Node: LENOX1      Process name: "SYSTEM"
```

Symlink search mode: No wildcard

This example shows that wildcard is not used for symlink search.

## SHOW PROTECTION

**SHOW PROTECTION** — Displays the current default process protection to be applied to all new files created during the terminal session or batch job.

### Format

**SHOW PROTECTION**

### Parameters

None.

### Description

The **SHOW PROTECTION** command displays the current default file protection to be applied to all new files created during the terminal session or batch job. You can change the default protection at any time with the **SET PROTECTION/DEFAULT** command.

Use the **DIRECTORY/PROTECTION** command to see the current protection for one or more specific files.

## Example

```
$ SHOW PROTECTION
SYSTEM=RWED, OWNER=RWED, GROUP=RE, WORLD=NO ACCESS
$ SET PROTECTION=(GROUP:RWED,WORLD:RE)/DEFAULT
$ SHOW PROTECTION
SYSTEM=RWED, OWNER=RWED, GROUP=RWED, WORLD=RE
```

The **SHOW PROTECTION** command in this example requests a display of the current protection defaults and the user identifiers; the **SET PROTECTION/DEFAULT** command changes the file access allowed to other users in the same group and to miscellaneous system users. The next **SHOW PROTECTION** command shows the modified protection defaults.

## SHOW QUEUE

**SHOW QUEUE** — Displays information about queues and the jobs that are currently in queues.  
**Requires read (R) access to the job.**

### Format

**SHOW QUEUE** [*queue-name*]

### Parameter

*queue-name*

Specifies the name of the queue for which you want information displayed. The asterisk (\*) and the percent sign (%) wildcard characters are allowed. The default value for the *queue-name* parameter is the asterisk (\*) wildcard character. If no queue name is specified, information on all queues is displayed.

## Description

The **SHOW QUEUE** command displays the name, type, status, and attributes of batch and output queues as well as information about jobs in the queues. When you enter the **SHOW QUEUE** command with no qualifiers, the OpenVMS system lists the names, types, and status of all the specified queues along with information about your jobs in those queues. The **SHOW QUEUE** command assumes the **/BRIEF** qualifier by default.

In an OpenVMS Cluster, the **SHOW QUEUE** command displays information on all the queues available for the cluster.

If you want information about queues or a complete list of the jobs in those queues, use the **SHOW QUEUE** command. For information about specific jobs, use the **SHOW ENTRY** command.

## Qualifiers

### **/ALL\_JOBS**

Displays all the jobs in the specified queues. You must have read (R) access to the job to show information about any jobs.

### **/BATCH**

Displays only batch queues and jobs in those queues.

**/BRIEF (default)**

Displays a one-line description of each queue and jobs that are in it. This information includes the name, type, and status of each queue. It also includes the entry number, the job name, the user name, and the status for each job shown. The **/FULL** and **/FILES** qualifiers override the **/BRIEF** qualifier.

**/BY\_JOB\_STATUS=(keyword-list)**

Displays queues that contain jobs that match the specified status. By default, jobs owned by the user are displayed. Specify the status with one or more of the following keywords:

Keyword	Description	
EXECUTING	Requests the display of jobs in any of the following states:	
	ABORTING EXECUTING PRINTING PROCESSING	STALLED STARTING SUSPENDED
	ABORTING means that the job is halting prior to normal completion and will not continue processing. A SUSPENDED state means that the job stopped during processing, but should continue when the cause of the SUSPENDED state is resolved. PROCESSING is the executing state for server queues. PRINTING is the executing state for printer and terminal queues. STARTING means the job is beginning to be processed or printed. A STALLED or SUSPENDED state means that the job stopped during processing, but should continue when the cause of the STALLED or SUSPENDED state is resolved.	
HOLDING	Requests the display of jobs on hold. Holding status indicates that the job is being held in the queue indefinitely.	
PENDING	Requests the display of jobs with pending status. Pending status indicates that the job is waiting its turn to execute.	
RETAINED	Requests the display of jobs retained in the queue after execution. Retained status indicates that the job has completed, but it remains in the queue.	
TIMED_RELEASE	Requests the display of jobs on hold until a specified time. Timed release status indicates that the job is being held in the queue for execution at a specified time.	

Note that if you specify the qualifier without a keyword, the system will only display queues that actually contain jobs.

**/DEVICE[=(keyword-list)]**

Displays a particular type of queue and jobs in that queue.

Specify the type of device queue with one or more of the following keywords:

Keyword	Description
PRINTER	Requests the display of print queues.
SERVER	Requests the display of server queues.
TERMINAL	Requests the display of terminal queues.

You can specify more than one keyword. If you do not specify a keyword with the **/DEVICE** qualifier, all printer, terminal, and server queues are displayed.

### **/EXACT**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify a search string that must match the search string exactly and must be enclosed with quotation marks (" ").

If you specify the **/EXACT** qualifier without the **/SEARCH** qualifier, exact search mode is enabled when you set the search string with the Find (**F1**) key.

### **/FILES**

Adds to the display the list of files associated with each job. The **/FILES** qualifier overrides the **/BRIEF** qualifier.

### **/FULL**

Displays complete information about queues, jobs contained in queues, and the files associated with the jobs. The **/FULL** qualifier overrides the **/BRIEF** qualifier.

### **/GENERIC**

Displays only generic queues and jobs in those queues. A generic queue is not an execution queue. Its function is to hold jobs of a particular type (line printer jobs, for example) and direct them to execution queues for processing.

### **/HIGHLIGHT[=keyword]**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify the type of highlighting you want when a search string is found. When a string is found, the entire line is highlighted. You can use the following keywords: **BOLD**, **BLINK**, **REVERSE**, and **UNDERLINE**. **BOLD** is the default highlighting.

### **/OUTPUT[=filespec]**

#### **/NOOUTPUT**

Controls where the output of the command is sent. By default, the output of the **SHOW QUEUE** command is sent to the current SYS\$OUTPUT device (usually your terminal). To send the output to a file, use the **/OUTPUT** qualifier followed by a file specification.

The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification. If you enter a partial file specification (for example, specifying only a directory), **SHOW** is the default file name and **.LIS** is the default file type.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

### **/PAGE[=keyword]**

#### **/NOPAGE (default)**

Controls the display of information on the screen.

You can use the following keywords with the **/PAGE** qualifier:

Keyword	Description
CLEAR_SCREEN	Clears the screen before each page is displayed.
SCROLL	Displays information one line at a time.

Keyword	Description
SAVE[= <i>n</i> ]	Enables screen navigation of information, where <i>n</i> is the number of pages to store.

The **/PAGE=SAVE** qualifier allows you to navigate through screens of information. The **/PAGE=SAVE** qualifier stores up to 5 screens of up to 255 columns of information. When you use the **/PAGE=SAVE** qualifier, you can use the following keys to navigate through the information:

Key Sequence	Description
Up arrow key, <b>Ctrl/B</b>	Scroll up one line.
Down arrow key	Scroll down one line.
Left arrow key	Scroll left one column.
Right arrow key	Scroll right one column.
Find ( <b>E1</b> )	Specify a string to find when the information is displayed.
Insert Here ( <b>E2</b> )	Scroll right one half screen.
Remove ( <b>E3</b> )	Scroll left one half screen.
Select ( <b>E4</b> )	Toggle 80/132 column mode.
Prev Screen ( <b>E5</b> )	Get the previous page of information.
Next Screen ( <b>E6</b> ), <b>Return</b> , <b>Enter</b> , <b>Space</b>	Get the next page of information.
<b>F10</b> , <b>Ctrl/Z</b>	Exit. (Some utilities define these differently.)
Help ( <b>F15</b> )	Display utility help text.
Do ( <b>F16</b> )	Toggle the display to oldest/newest page.
<b>Ctrl/W</b>	Refresh the display.

The **/PAGE** qualifier is not compatible with the **/OUTPUT** qualifier.

#### **/SEARCH="string"**

Use with the **/PAGE=SAVE** qualifier to specify a string that you want to find in the information being displayed. Quotation marks are required for the **/SEARCH** qualifier, if you include spaces in the text string.

You can also dynamically change the search string by pressing the Find key (**E1**) while the information is being displayed. Quotation marks are not required for a dynamic search.

#### **/SUMMARY**

Displays the total number of executing jobs, pending jobs, holding jobs, retained jobs, and timed release jobs for each queue. For output queues, the total block count for pending jobs is also shown.

#### **/WRAP**

##### **/NOWRAP (default)**

Use with the **/PAGE=SAVE** qualifier to limit the number of columns to the width of the screen and to wrap lines that extend beyond the width of the screen to the next line.

The **/NOWRAP** qualifier extends lines beyond the width of the screen and can be seen when you use the scrolling (left and right) features provided by the **/PAGE=SAVE** qualifier.

## Examples

### 1. \$ SHOW QUEUE/ALL/BY\_JOB\_STATUS=pending

```
Printer queue KLEE$LCA0, stopped, mounted form DEFAULT
/BASE_PRIORITY=4 /DEFAULT=(FEED,FORM=ELITE (stock=DEFAULT))
/OWNER=[SYSTEM] /PROTECTION=(S:M,O:D,G:R,W:S)
```

Entry	Jobname	Username	Blocks	Status
2045	APPLICA	MARTIN	102	Pending

```
Batch queue SYS_TEX, available, on NODE22::
/BASE_PRIORITY=3 /JOB_LIMIT=25 /OWNER=[SYSTEM]
/PROTECTION=(S:M,O:D,G:R,W:S)
```

Entry	Jobname	Username	Status
1388	CHAPTER1.JOB	MARTIN	Pending

```
Generic batch queue CLUSTER_BATCH
/GENERIC=(HMSCMS_BATCH,NODE22_BATCH) /OWNER=[SYSTEM]
/PROTECTION=(S:M,O:D,G:R,W:S)
```

Entry	Jobname	Username	Status
936	no privilege		Pending

The **SHOW QUEUE** command in this example displays only the queues in which jobs are currently pending. The **/ALL** qualifier requests the display of all pending jobs. Notice that you cannot see job information for entry 936. You must have **GROUP** privilege to show all jobs in your group or **OPER** privilege to show all jobs in all groups.

### 2. \$ SHOW QUEUE/FULL ARMADA\*

```
Batch queue ARMADA_BATCH, idle, on ARMADA::
/AUTO_START_ON=(ARMADA::) /BASE_PRIORITY=3 /JOB_LIMIT=3
/OWNER=[SYSTEM] /PROTECTION=(S:M,O:D,G:R,W:S)
```

```
Printer queue ARMADA$PRINT, stopped, on ARMADA::LPA0,
mounted form DEFAULT
/BASE_PRIORITY=4 /DEFAULT=(FEED,FORM=ELITE (stock=DEFAULT))
/OWNER=[SYSTEM] /PROTECTION=(S:E,O:D,G:R,W:W)
```

Entry	Jobname	Username	Blocks	Status
605	SET	DUDSON	140	Pending (queue stopped)
	Submitted 21-DEC-2001 16:14 /FORM=ELITE (stock=DEFAULT)			
	/PRIORITY=200			
	File: _\$5\$DUA1:[DUDSON]SET.CLD;5			
606	CLOSE	DUDSON	140	Pending (queue stopped)
	Submitted 21-DEC-2001 16:16 /FORM=DEFAULT /PRIORITY=200			
	File: _\$5\$DUA1:[DUDSON]CLOSE.TXT;2			

```
Printer queue ARMADA$PRINTER_1, idle, on ARMADA::TTA3,
mounted form DEFAULT
```

```
<Printer queue on node ARMADA for a LN03R printer>
  /BASE_PRIORITY=4 /DEFAULT=(FEED,FORM=DEFAULT) /LIBRARY=SMU$DEVCTL
  Lowercase /OWNER=[SYSTEM] /PROCESSOR=CPSS$SMB
  /PROTECTION=(S:M,O:D,G:R,W:S) /SEPARATE=(FLAG)
```

The **SHOW QUEUE** command in this example lists information on all of your current job entries. Complete information about the queues, the jobs contained in those queues, and the files associated with the jobs is displayed.

3. \$ SHOW QUEUE/SUMMARY

```
Batch queue HMSCMS_BATCH, available, on HMSCMS::

    Job summary:  1 executing,  5 holding

Server queue NM$QUE01, available, on NODE22::, mounted form DEFAULT

    Job summary:  2 executing

Generic server queue NM$QUEUE

    Job summary:  1 timed release

Batch queue PIZZA_BATCH, idle, on PIZZA::

    Job summary:  queue is empty

Batch queue NODE22_BATCH, available, on NODE22::

    Job summary:  1 executing,  1 timed release

Printer queue ARMADA$PRINT, stopped, on ARMADA::LPA0, mounted
form DEFAULT

    Job summary:  8 pending (565 blocks)

Terminal queue ALLBQ, stopped, on KATYA::TTA2, mounted form DEFAULT

    Job summary:  2 pending (445 blocks)
```

The **SHOW QUEUE** command in this example lists all queues and displays the total number of jobs on the queues.

4. \$ SHOW QUEUE DOC\$LN03

```
Server queue DOC$LN03, stopped, on NEWTON::, mounted form DEFAULT

Entry  Jobname    Username   Blocks   Status
-----
436    DOCPLAN     HERSHEY    8        Retained until 11-JAN-2001 16:56
      %JBC-F-JOBABORT, job aborted during execution
      Completed 11-JAN-2001 15:56 on queue DOC$LN03
```

This **SHOW QUEUE** display includes the date and time at which a retained job completed and the queue on which it executed. You can specify the **/RETAIN** qualifier with the **PRINT**, **SUBMIT**, or **SET ENTRY** command to specify the circumstances under which you want your job to be retained

in a queue. In this example, the user set job retention to be one hour after job completion. Depending on the queue's job retention policy, the job might be deleted from the queue at 16 : 56.

See the [PRINT](#), [SUBMIT](#), or [SET ENTRY](#) command descriptions for more information on the **/RETAIN** qualifier.

## SHOW QUEUE/CHARACTERISTICS

**SHOW QUEUE/CHARACTERISTICS** — Displays information about queue characteristics defined for the system. A characteristic is a user-defined attribute of a batch or output queue, such a sink color.

### Format

**SHOW QUEUE/CHARACTERISTICS**

[*characteristic-name*]

### Parameter

*characteristic-name*

Specifies the name of a characteristic. The asterisk (\*) and the percent sign (%) wildcard characters are allowed. The default value for the *characteristic-name* parameter is the asterisk wildcard (\*). Thus, information about all characteristics is displayed when you do not specify a characteristic name.

You create a characteristic name with the **DEFINE/CHARACTERISTIC** command. You can then assign it to a queue by using the **INITIALIZE/QUEUE**, the **SET QUEUE**, or the **START/QUEUE** command with the **/CHARACTERISTICS** qualifier. You can also specify characteristics for a job by using the **/CHARACTERISTICS** qualifier with the **PRINT**, the **SUBMIT**, or the **SET ENTRY** command.

### Description

The **SHOW QUEUE/CHARACTERISTICS** command displays the characteristic name and number of characteristics defined for the system. To see which characteristics are associated with a particular queue, use the **SHOW QUEUE** command with the **/FULL** qualifier.

### Qualifier

**/OUTPUT[=*filespec*]**  
**/NOOUTPUT**

Controls where the output of the command is sent. By default the output of the **SHOW QUEUE/CHARACTERISTICS** command is sent to the current SY\$OUTPUT device(usually your terminal). To send the output to a file, use the **/OUTPUT** qualifier followed by a file specification.

The file specification may not include any wildcard characters. If you enter a partial file specification (for example, specifying only a directory), **SHOW** is the default file name and **.LIS** is the default file type.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

## Examples

1. `$ SHOW QUEUE/CHARACTERISTICS`

Characteristic name	Number
-----	-----
BLUEINK	6
BROWNINK	25
COLOR_CHART	1
REDINK	0
TEXMAC_JOB	2

The **SHOW QUEUE/CHARACTERISTICS** command in this example displays all the characteristics that have been defined for this system.

2. (wide)

`$ SHOW QUEUE/CHARACTERISTICS *INK`

Characteristic name	Number
-----	-----
BLUEINK	6
BROWNINK	25
REDINK	0

The **SHOW QUEUE/CHARACTERISTICS** command in this example displays the name and number of all characteristics that end with INK.

## SHOW QUEUE/FORM

**SHOW QUEUE/FORM** — Displays information about forms defined for the system. Forms define the size and type paper and the layout of text that are used for print jobs.

### Format

**SHOW QUEUE/FORM** [*form-name*]

### Parameter

*form-name*

Specifies the name of the form. The asterisk (\*) and the percent sign (%) wildcard characters are allowed. The default value for the *form-name* parameter is an asterisk (\*), which means that the names of all forms on the system are displayed.

### Description

The **SHOW QUEUE/FORM** command displays the name and number of forms defined for the system. To display the attributes associated with forms, use the **/FULL** qualifier.

Use the **SHOW QUEUE/FORM** command to find out which forms are available on the system. To see which forms are available on one or more queues, use the **SHOW QUEUE** command with the **/FULL** qualifier.

Form names are created by the **DEFINE/FORM** command. You can specify a particular form for a print job by using the **/FORM** qualifier with the **PRINT** or **SET ENTRY** command. Forms are assigned to queues with the **INITIALIZE/QUEUE**, the **SET QUEUE**, or the **START/QUEUE** command.

## Qualifiers

### **/BRIEF (default)**

Displays a brief description (form names, numbers, and descriptions) about the forms on the system.

### **/FULL**

Displays a full description (including paper size and margin settings) about the forms on the system.

### **/OUTPUT[=*filespec*]**

### **/NOOUTPUT**

Controls where the output of the command is sent. By default the output of the **SHOW QUEUE/FORM** command is sent to the current SY\$OUTPUT device (usually your terminal). To send the output to a file, use the **/OUTPUT** qualifier followed by a file specification.

The file specification cannot include the asterisk (\*) and the percent sign (%) wildcard characters. If you enter a partial file specification (for example, specifying only a directory), **SHOW** is the default file name and **.LIS** is the default file type.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

## Examples

1. \$ SHOW QUEUE/FORM DEFAULT

Form name	Number	Description
-----	-----	-----
DEFAULT	0	System-defined default

The **SHOW QUEUE/FORM** command in this example displays only the default form.

2. \$ SHOW QUEUE/FORM LN01\*

Form name	Number	Description
-----	-----	-----
LN01_LANDSCAPE (stock=DEFAULT)	105	132 by 66 (landscape)
LN01_LANDSCAPE_INDENTED (stock=DEFAULT)	107	132 by 65 (landscape)
LN01_PORTRAIT (stock=DEFAULT)	106	80 by 60 (portrait)

The **SHOW QUEUE/FORM** command in this example displays the names of all forms, including the stock, that begin with LN01. The display includes the names, stock for each form, numbers, and brief descriptions of those forms.

3. \$ SHOW QUEUE/FORM/FULL

Form name	Number	Description
-----	-----	-----
132_51_STD (stock=DEFAULT)	102	132 by 51 (standard short)
/LENGTH=51 /MARGIN=(BOTTOM=6) /STOCK=DEFAULT /TRUNCATE		
/WIDTH=132		
40_66_STD (stock=DEFAULT)	103	40 by 66 (standard labels)
/LENGTH=66 /MARGIN=(BOTTOM=6) /STOCK=DEFAULT /WIDTH=40		
BLUE_PAPER_STOCK (stock=DIGITAL_8X11_STOCK1412TEA)		
22222 blue paper, DEC order# 22222		
/LENGTH=66 /MARGIN=(BOTTOM=6) /STOCK=DIGITAL_8X11_STOCK1412TEA		
/TRUNCATE /WIDTH=80		
DEFAULT	0	System-defined default
/LENGTH=66 /MARGIN=(BOTTOM=6) /STOCK=DEFAULT /TRUNCATE		

```
        /WIDTH=132
LN01_LANDSCAPE (stock=DEFAULT)          105    132 by 66 (landscape)
        /LENGTH=66 /STOCK=DEFAULT /WIDTH=132
LN01_LANDSCAPE_INDENTED (stock=DEFAULT)
                                107    132 by 65 (landscape)
        /LENGTH=65 /SETUP=(LN01_TOP_MARGIN_150) /STOCK=DEFAULT
        /WIDTH=132
LN01_PORTRAIT (stock=DEFAULT)           106    80 by 60 (portrait)
        /LENGTH=60 /SETUP=(LN01_PORTRAIT) /STOCK=DEFAULT /WIDTH=80

MEMO (stock=DEFAULT)                   110    LN03 indented memo format
        /LENGTH=64 /MARGIN=(TOP=2,LEFT=5) /STOCK=DEFAULT /TRUNCATE
        /WIDTH=80
```

This **SHOW QUEUE/FORM** command also displays the names of all form types and stock for the system. By using the **/FULL** qualifier, you can see what image size has been set for each form type.

## SHOW QUEUE/MANAGERS

**SHOW QUEUE/MANAGERS** — Provides information about the queue manager(s) on the system or OpenVMS Cluster.

### Format

**SHOW QUEUE/MANAGERS** [*queue-manager-name*]

### Parameter

*queue-manager-name*

Specifies the name of the queue manager for which you want information displayed. The asterisk (\*) and the percent sign (%) wildcard characters are allowed. The default value for the *queue-manager-name* parameter is the asterisk (\*) wildcard character. If no queue manager name is specified, information on all queue managers is displayed.

### Description

The **SHOW QUEUE/MANAGERS** command displays information about the queue manager(s) on the system or OpenVMS Cluster. The command assumes the **/BRIEF** qualifier as the default, and displays a one-line description that include search queue manager's name, status, and process node name. The **/FULL** qualifier displays the following information:

- Full file specification of the queue database master file (disk, directory, and file name of the shared master file)
- Name of queue manager
- Status of queue manager
- The node name on which the queue manager process is running (if the queue manager process is currently running)
- Prioritized list of nodes on which the queue manager process can run
- Disk and directory containing the queue database files specific to the particular queue manager

If a queue manager process is not running, the current location node name will not be displayed for that queue manager.

The queue manager status can be one of the following:

State	Description
Start pending	The queue manager process is attempting to start up, however, it is waiting for a node on which it can run to enter the cluster.
Starting	The queue manager is in the process of starting up as a result of a <b>START /QUEUE/MANAGER</b> command or failing over from another node in the cluster.
Running	The queue manager is running.
Failing over	The queue manager is in the process of failing over to another node in the cluster.
Stopping	The queue manager is in the process of stopping.
Stopped	The queue manager is stopped and will not start until a <b>START /QUEUE/MANAGER</b> command is executed.

## Qualifiers

### /BRIEF

Displays a one-line description of queue manager(s) on the system or cluster. The information displayed includes the name and status of the queue manager and the node on which its process is running. The **/BRIEF** qualifier is present by default.

### /FULL

Displays complete information about queue manager(s) on the system or cluster. The **/FULL** qualifier overrides the **/BRIEF** qualifier.

## Examples

```
1. $ SHOW QUEUE/MANAGERS/FULL
Master file:  SYS$COMMON:[SYSEXE]QMAN$MASTER.DAT;

Queue manager BATCHQ_MANAGER, running, on BBBBBB::
  /ON=(BBBBBB, AAAAAA, CCCCCC, EEEEE, *)
Database location:  DISK1:[QUEUES]

Queue manager PRINTQ_MANAGER, starting, on AAAAAA::
  /ON=(AAAAAA, BBBBBB, CCCCCC, EEEEE, *)
Database location:  DISK2:[QUEUES]

Queue manager SYS$QUEUE_MANAGER, running, on FFFFFFFF::
  /ON=(FFFFFFF, EEEEE, CCCCCC, BBBBBB, AAAAAA, *)
Database location:  DISK1:[QUEUES]

Queue manager TRANSFER_MANAGER, stopped
  /ON=(AAAAAA, BBBBBB, EEEEE)
Database location:  DISK1:[TRANSFER]
```

The **SHOW QUEUE/MANAGERS /FULL** command displays complete information about a queue manager on a system or cluster.

2. `$ SHOW QUEUE/MANAGERS`  
Queue manager BATCHQ\_MANAGER, running, on BBBBBB::  
  
Queue manager PRINTQ\_MANAGER, starting, on AAAAAA::  
  
Queue manager SYS\$QUEUE\_MANAGER, running, on FFFFFF::  
  
Queue manager TRANSFER\_MANAGER, stopped
3. The **SHOW QUEUE/MANAGERS** command in this example shows information about the queue manager in brief format. The **/BRIEF** qualifier is the default and does not need to be specified.

```
$ SHOW QUEUE/MANAGERS/FULL SYS$QUEUE_MANAGER
Master file:  SYS$COMMON:[SYSEXE]QMAN$MASTER.DAT;

Queue manager SYS$QUEUE_MANAGER, running, on FFFFFF::
  /ON=(FFFFFF, EEEEE, CCCCC, BBBBB, AAAAA, *)
Database location:  DISK1:[QUEUES]
```

The command, **SHOW QUEUE/MANAGERS/FULL SYS\$QUEUE\_MANAGER**, in this example shows a request for a specific queue manager by name.

## SHOW QUOTA

**SHOW QUOTA** — Displays the current disk quota that is authorized for a specific user on a specific disk. This display includes a calculation of the amount of space available and the amount of overdraft that is permitted. **Requires read (R) access to the quota file in order to display the quotas of other users.**

### Format

**SHOW QUOTA**

### Description

The **SHOW QUOTA** command indicates whether a quota exists for any specific user on a specific disk. The display that results gives the quotas used, authorized, and available in blocks. The amount of overdraft permitted is also shown.

### Qualifiers

**/DISK[=*device-name*[:]]**

Specifies the disk whose quotas are to be examined. By default, the current default disk (defined by the logical name SYS\$DISK) is examined.

**/USER=*uic* OR *identifier***

Specifies which user's quotas are to be displayed. By default, the current user's quotas are displayed.

### Examples

1. `$ SHOW QUOTA`  
User [360,010] has 2780 blocks used, 7220 available,  
of 10000 authorized and permitted overdraft of 500 blocks on DISK\$

The **SHOW QUOTA** command in this example displays the amount of disk space authorized, used, and still available on the current default disk for the present user. The permitted overdraft in this example is 500 blocks.

2. 

```
$ SHOW QUOTA /USER=[360,007]/DISK=XXX1:
%SYSTEM-F-NODISKQUOTA, no disk quota entry for this UIC
```

The **SHOW QUOTA** command in this example displays the fact that the user with user identification code (UIC) [ 360 , 007 ] has no disk quota allocation on device XXX1.

3. 

```
$ SHOW QUOTA /USER=[360,111]
User [360,111] has 27305 blocks used, 2305 OVERDRAWN,
of 25000 authorized and permitted overdraft of 4000 blocks on DISK$
```

The **SHOW QUOTA** command in this example illustrates a user with an overdrawn quota.

## SHOW RMS\_DEFAULT

**SHOW RMS\_DEFAULT** — Displays the current default values for the multiblock count, the multibuffer count, the network transfer size, the prolog level, the extend quantity, and the query lock option.

### Format

**SHOW RMS\_DEFAULT**

### Parameters

None.

### Description

The **SHOW RMS\_DEFAULT** command displays information that OpenVMS Record Management Services (RMS) uses for file operations including the default values for the multibuffer count, the multiblock count, the network block count, the prolog level, the extend quantity, and the query lock option. The command provides these values at both the current process level and at the system level.

The **SHOW RMS\_DEFAULT** command lists the multibuffer count values for each of the file types, including the values for the three classes of sequential files(disk, magtape and unit record).

### Qualifier

**/OUTPUT[=*filespec*]**  
**/NOOUTPUT**

Specifies the file to which the display is written (default is SYSS\$OUTPUT). The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification. If you enter the **/OUTPUT** qualifier with a partial file specification (for example, specifying only a directory), **SHOW** is the default output file name and **.LIS** the default output file type.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

### Example

```
$ SHOW RMS_DEFAULT
```

	MULTI- BLOCK COUNT		MULTIBUFFER COUNTS					NETWORK BLOCK COUNT
			Indexed	Relative		Sequential		
					Disk	Magtape	Unit Record	
Process	0		0	0	0	0	0	0
System	16		0	0	0	0	0	8
	Prolog		Extend	Quantity		VCC_DFW	QUERY_LOCK	
Process	0			0		0	System	
System	0			0		0	Enabled	
	CONTENTION_POLICY							
Process	System							
System	Never							

The **SHOW RMS\_DEFAULT** command in this example shows a system multiblock count of 16 and a network block count of 8. These are typical values. Note that the placeholder, VCC\_DFW, is currently reserved for use by VSI.

## SHOW ROOT

**SHOW ROOT** — Displays the current value of the system root and, if defined, the process root.

### Format

**SHOW ROOT**

### Example

```
$ SHOW ROOT
DISK1:[000000]
$ SET ROOT DISK5:[ PSX$ROOT]
$ SHOW ROOT
DISK5:[ PSX$ROOT]
$
```

The **SHOW ROOT** command in this example displays the current root path. The **SET ROOT** command changes these defaults, and the next **SHOW ROOT** command displays the new default root.

## SHOW SECURITY

**SHOW SECURITY** — Displays the name, class, and profile of a protected object.

### Format

**SHOW SECURITY** *object-name*

### Parameter

*object-name*

Specifies the name of an object whose security profile is to be displayed. If the object class is SECURITY\_CLASS, you can specify an asterisk (\*) as *object-name* to see a display of all security class objects. An object name of the FILE class (explicitly or implicitly specified) can include the asterisk (\*) and the percent sign (%) wildcard characters; however, wildcard characters are not allowed in any class other than FILE or SECURITY\_CLASS.

## Description

The **SHOW SECURITY** command displays the name, class, and profile of a protected object. A profile includes an access control list (ACL), the protection code, and the owner of a protected object. For **SECURITY\_CLASS** objects, **SHOW SECURITY** displays all the template profiles, which are the basis for profiles of new objects.

The **/CLASS** qualifier identifies the class *object-name* is a member of. If the class is **DEVICE** and the object is a disk device on which a volume is mounted as a Files-11 (rather than foreign) volume, then both the device and the volume profiles are displayed.

All qualifiers other than **/CLASS** apply only to files.

For a description of protected objects, see the relevant section in the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#SEC_OBJ_LIST) [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#SEC\_OBJ\_LIST].

## Qualifiers

### **/BACKUP**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/BACKUP** qualifier selects files according to the dates of their most recent backups (rather than by the creation, expiration, or modification date). By default, **SHOW SECURITY** selects files according to their creation date.

### **/BEFORE[=*time*]**

Selects only those files dated prior to the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: **BOOT**, **LOGIN**, **TODAY** (default), **TOMORROW**, or **YESTERDAY**. Specify the **/CREATED** or the **/MODIFIED** qualifier to indicate the time attribute to be used as the basis for selection. The **/CREATED** qualifier is the default.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic **Date**.

### **/BY\_OWNER[=*uic*]**

Selects files whose owner's UIC matches the UIC specified with *uic*. The default UIC is that of the current process.

Specify the UIC by using the standard format described in the relevant section in the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC_SECTION) [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC\_SECTION].

### **/CLASS=*class***

Specifies the class of the object whose profile is to be displayed. By default, the command assumes the object class is **FILE**. Object class keywords are as follows:

CAPABILITY	LOGICAL_NAME_TABLE
COMMON_EVENT_CLUSTER	QUEUE
DEVICE	RESOURCE_DOMAIN
FILE	SECURITY_CLASS
GROUP_GLOBAL_SECTION	SYSTEM_GLOBAL_SECTION
ICC_ASSOCIATION	VOLUME

**/CREATED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/CREATED** qualifier selects files according to the date they were created (rather than by the backup, expiration, or modification date). By default, **SHOW SECURITY** selects files according to their creation date.

**/EXCLUDE=(filespec[,...])**

Excludes the specified files from the **SHOW SECURITY** operation. You can include a directory, but not a device, in the file specification. You cannot use relative version numbers to exclude a specific version.

**/EXPIRED**

Modifies the time specified with the **/BEFORE** or the **/SINCE** qualifier. The **/EXPIRED** qualifier selects files according to their expiration dates rather than by the backup, creation, or modification date. (The expiration date is set with the **SET FILE/EXPIRATION\_DATE** command.) By default, files are selected according to their creation date.

**/MODIFIED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/MODIFIED** qualifier selects files according to the dates on which they were last modified, rather than by the backup, creation, or expiration date. By default, files are selected according to their creation date.

**/SINCE[=time]**

Selects only those files dated on or after the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: **BOOT**, **JOB\_LOGIN**, **LOGIN**, **TODAY** (default), **TOMORROW**, or **YESTERDAY**. Specify the **/CREATED** or the **/MODIFIED** qualifier to indicate the time attribute to be used as the basis for selection. The **/CREATED** qualifier is the default.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic **Date**.

**/SYMLINK=keyword**

The valid keywords for this qualifier are **[NO]WILDCARD**, **[NO]ELLIPSIS**, and **[NO]TARGET**. Descriptions are as follows:

Keyword	Description
<b>NOWILDCARD</b>	Indicates that symlinks are disabled during directory wildcard searches.
<b>WILDCARD</b>	Indicates that symlinks are enabled during wildcard searches.
<b>NOELLIPSIS</b>	Indicates that symlinks are matched for all wildcard fields except for ellipsis.
<b>ELLIPSIS</b>	Equivalent to <b>WILDCARD</b> (included for command symmetry).
<b>TARGET</b>	Indicates that if the named file is a symlink, then the symlink is followed to operate on the symlink target.
<b>NOTARGET</b>	Indicates that the command operates on the named file whether it is an ordinary file or a symlink.

If the file named in the **SHOW SECURITY** command is a symlink, the command by default operates on the symlink itself.

## Examples

1. \$ SHOW SECURITY LNM\$SYSTEM\_TABLE /CLASS=LOGICAL\_NAME\_TABLE

LNM\$SYSTEM\_TABLE object of class LOGICAL\_NAME\_TABLE

```
Owner: [SYSTEM]
Protection: (System: RWC, Owner: RWC, Group: R, World: R)
Access Control List:
    (IDENTIFIER=[USER, SVENSEN], ACCESS=CONTROL)
```

This example shows a typical request to display the security elements of an object. The logical name table LNM\$SYSTEM\_TABLE is displayed with the settings of the security elements owner, protection, and ACL.

2. \$ SHOW SECURITY/CLASS=DEVICE \$99\$DUA22

\_ \$99\$DUA22: object of class DEVICE

```
Owner: [SALES, TSUTTER]
Protection: (System: RWPL, Owner: RWPL, Group: R, World)
Access Control List: <empty>
```

RES17SEP object of class VOLUME

```
Owner: [FEAST, FY93]
Protection: (System: RWCD, Owner: RWCD, Group: RWCD, World: RWCD)
Access Control List: <empty>
```

\$ SHOW DEVICE \$99\$DUA22

Device Name	Device Status	Error Count	Volume Label	Free Blocks	Trans Count	Mnt Cnt
\$99\$DUA22: (KUDOS)	Mounted	0	RES17SEP	649904	1	2

This example shows a request for the security profile of a disk device. The resulting display provides both the profiles of the disk \$99\$DUA22 and the volume RES17SEP that is mounted on it. The subsequent **SHOW DEVICE** command confirms that the volume is mounted on the device \$99\$DUA22.

3. \$ SHOW SECURITY LOGICAL\_NAME\_TABLE /CLASS=SECURITY\_CLASS

LOGICAL\_NAME\_TABLE object of class SECURITY\_CLASS

```
Owner: [SYSTEM]
Protection: (System: RWCD, Owner: RWCD, Group: R, World: R)
Access Control List: <empty>
```

Template: GROUP

```
Owner: [SYSTEM]
Protection: (System: RWCD, Owner: R, Group: R, World: R)
Access Control List: <empty>
```

Template: JOB

```
Owner: [SYSTEM]
Protection: (System: RWCD, Owner: RWCD, Group, World)
Access Control List: <empty>
```

```
Template: DEFAULT
```

```
Owner: [SYSTEM]
Protection: (System: RW, Owner: RW, Group: R, World: R)
Access Control List: <empty>
```

This example shows the output for the special case of a security class object. The security class object LOGICAL\_NAME\_TABLE is displayed with the security profile. In addition, three templates are displayed.

#### 4. \$ SHOW SECURITY \* /CLASS=SECURITY\_CLASS

```
SECURITY_CLASS object of class SECURITY_CLASS
Owner: [SYSTEM]
Protection: (System: RWCD, Owner: RWCD, Group: R, World: R)
Access Control List: <empty>

LOGICAL_NAME_TABLE object of class SECURITY_CLASS
Owner: [SYSTEM]
Protection: (System: RWCD, Owner: RWCD, Group: R, World: R)
Access Control List: <empty>
```

This example shows the output for the special case of showing all the security classes currently registered. The asterisk (\*) wildcard character is used; any other form of wildcard characters is not accepted. Security profiles are shown for each security class. Note that template information is not shown.

## SHOW SERVER ACME\_SERVER (Alpha/Integrity servers Only)

SHOW SERVER ACME\_SERVER (Alpha/Integrity servers Only) — Displays information about the ACME server and ACME agent. **Requires the SYSPRV privilege.**

### Format

```
SHOW SERVER ACME_SERVER
```

### Description

The **SHOW SERVER ACME\_SERVER** command provides a system manager with the ability to display information about the ACME server and one or more ACME agents.

For related information, see the [SET SERVER ACME\\_SERVER](#) command.

### Qualifiers

**/AGENT[=(*agent*,...*agent*)] (default)**  
**/NOAGENT**

Specifies whether to display ACME agent information.

**/BRIEF (default)**

Displays summary information.

**/CLUSTER**

Executes the command on all cluster members.

**/FULL**

Displays complete information.

**/NODE=(*node-name*[,...])**

Specifies the cluster member or members for which information is to be displayed.

**/OUTPUT=*filespec***

Sends the output information to the specified file.

**/PAGE**

Displays information one screen at a time.

**/SERVER (default)****/NOSERVER**

Specifies whether to display ACME server information.

## Example

1. \$ SHOW SERVER ACME\_SERVER

This example shows the output for **SHOW SERVER ACME/BRIEF** on an Alpha system.

```
ACME Information on node TSINOD  29-JUN-2004 10:08:12.32  Uptime
000:05:45
```

```
ACME Server id: 5  State: Processing New Requests ❶
```

```
  Agents Loaded:      2  Active:      2 ❷
  Thread Maximum:    4  Count:      4
  Request Maximum:   8  Count:      0
```

```
ACME Agent id: 1  State: Active ❸
```

```
  Name: "VMS" ❹
  Image: "DISK$AXP_721:[VMS$COMMON.SYSLIB]VMS$VMS_ACMESHR.EXE;1" ❺
  Identification: "VMS ACME built  3-JUN-1999" ❻
  Information: "No requests completed since the last startup" ❼
  Domain of Interpretation: Yes ❽
  Execution Order:      1 ❾
```

```
ACME Agent id: 2  State: Active
```

```
  Name: "MSV1_0"
  Image: "DISK$AXP_721:[SYS0.SYSLIB]PWRK$MSV1_0_ACMESHR.EXE;2"
  Identification: "MSV1_0 ACME X-22"
  Information: "MSV1_0 ready to process requests."
  Domain of Interpretation: Yes
  Execution Order:      2
```

The following are the item descriptions keyed to the callouts in the example output:

❶ Server state

- ❷ Server agent/thread/request-slot statistics
- ❸ Agent state
- ❹ Agent name
- ❺ Agent file-specification
- ❻ Agent-defined identification string (static)
- ❼ Agent-defined information string (dynamic)
- ❽ Domain-of-interpretation (DOI) indicator
- ❾ Execution order (the order in which agents are called for each request)

## 2. \$ SHOW SERVER ACME\_SERVER/FULL

This example shows the output for **SHOW SERVER ACME/FULL** on an Alpha system.

```
ACME Information on node AUTUMN 25-SEP-2009 04:15:37.34 Uptime 0
22:19:26
```

```
ACME Server id: 255 State: Processing New Requests
```

```
Agents Loaded:      2 Active:      2
Thread Maximum:    1 Count:      1
Request Maximum:   700 Count:      0 ❶
Requests awaiting service:      0 ❷
Requests awaiting dialogue:      0 ❸
Requests awaiting AST:           0 ❹
Requests awaiting resource:      0 ❺
Logging status: Active
```

```
Tracing status: Inactive
```

```
Log file: "SYS$SYSROOT:[SYSMGR]ACME$SERVER.LOG;147"
```

```
ACME Agent id: 1 State: Active
```

```
Name: "VMS"
```

```
Image: "DISK$JEDIXC42:[VMS$COMMON.SYSLIB]VMS$VMS_ACMESHR.EXE;1"
```

```
Identification: "VMS ACME built 20-SEP-2006"
```

```
Information: "Unused max 1: 0u 0r 0a 1a 1w 0m 0o 0c 1h 1d" ❹
```

```
Domain of Interpretation: Yes
```

```
Execution Order:      1
```

```
Credentials Type:      1 Name: "VMS"
```

```
Resource wait count:      0 ❷
```

```
ACME Agent id: 2 State: Active
```

```
Name: "LDAP-STD"
```

```
Image: "DISK$JEDIXC42:[VMS$COMMON.SYSLIB]LDAPACME$LDAP-
STD_ACMESHR.EXE;2"
```

```
Identification: "LDAP ACME Standard V1.5"
```

```
Information: "ACME_LDAP_DOI Agent is initialized"
```

```
Domain of Interpretation: Yes
```

```
Execution Order:      2
```

```
Credentials Type:      3 Name: "LDAP"
```

```
Resource wait count:      0 ❸
```

```
$
```

The following are the item descriptions keyed to the callouts in the example output:

- ❶ Number of requests currently handled by the ACME agent.
- ❷ Number of requests waiting to get serviced.
- ❸ Number of requests waiting for user dialogue/inputs.

- ④ Number of requests waiting for system services to send AST.
- ⑤ Total number of requests waiting for the availability of ACME agents such as the VMS ACME and LDAP ACME agents.
- ⑥ Internal counter values of VMS ACME agent.
- ⑦ Number of requests waiting for the availability of resources such as the SYSUAF file from the VMS ACME agent.
- ⑧ Number of requests waiting for the availability of resources such as the SYSUAF file from the LDAP ACME agent.

## SHOW SERVER REGISTRY\_SERVER (Alpha/Integrity servers Only)

SHOW SERVER REGISTRY\_SERVER (Alpha/Integrity servers Only) — Displays information about the Registry server. **Requires the SYSPRV privilege.**

### Format

**SHOW SERVER REGISTRY\_SERVER**

### Description

The **SHOW SERVER REGISTRY\_SERVER** command provides a system manager with the ability to display information about the Registry server.

For related information, see the [SET SERVER REGISTRY\\_SERVER](#) command.

### Qualifiers

#### **/CLUSTER**

Displays information about each server in the cluster.

Cannot be used with the **/MASTER** or **/NODE** qualifiers.

#### **/MASTER**

**Requires the SYSLCK privilege.**

Displays information about the Registry master server only.

Cannot be used with the **/CLUSTER** or **/NODE** qualifiers.

#### **/NODE=(*node-name*[,...])**

Displays information about the Registry servers on the specified nodes in the order in which the nodes are listed. The specified nodes must be in the current cluster.

Cannot be used with the **/CLUSTER** or **/MASTER** qualifiers.

#### **/OUTPUT=*filespec***

Sends the output information to the specified file.

## Examples

1. `$ SHOW SERVER REGISTRY_SERVER`

This command displays information about the node you are on. For example:

```
Registry Information on node OPNEYE 29-JUN-2004 16:37:26.52 -  
Uptime 20 04:10:55
```

2. `$ SHOW SERVER REGISTRY_SERVER/MASTER`

This command displays information about the Registry master server. For example:

```
Registry Master Server is running on OPNEYE, Pid: 20A0021A
```

## SHOW SHADOW (Alpha/Integrity servers Only)

**SHOW SHADOW (Alpha/Integrity servers Only)** — Displays the status of a specified shadow set on the system. If no qualifiers are specified, displays a summary of the device.

### Format

`SHOW SHADOW[DSAn[ : ]]`

### Parameter

**DSA<sub>n</sub>[ : ]**

Specifies the virtual unit name of the shadow set for which information is to be displayed.

If no virtual unit is specified, information is displayed for all mounted shadow sets.

### Qualifiers

**/ACTIVE**

Displays one of three possible states:

- Merge or Copy is not required
- Copy is in progress on node *node-name*, *n%* completed
- Merge is in progress on node *node-name*, *n%* completed

**/BY\_PRIORITY**

**/BY\_PRIORITY DSA<sub>n</sub>:**

Displays a list of shadow sets on the system, sorted in the order in which a recovery operation (copy, full merge, or minimerge) is scheduled to occur. If a copy or merge is active, the display shows on which system it is occurring. This list is specific to the system on which the command is executed, so the list might vary across systems in a cluster. Higher numbers indicate a higher priority.

**Tip:** When the command specifies a virtual unit (DSA*n*:), the display shows the current priority and status of just this virtual unit. If any copy or merge operations are in progress, the system on which the operation is occurring is also displayed, along with the operation's progress.

### **/COPY**

Displays one of three possible states:

- Copy is not required
- Copy is pending
- Copy is in progress on node *node-name*, *n%* completed

### **/FULL**

Displays complete information about the specified devices (or all devices if no device is specified). The only other qualifier that can be specified with **/FULL** is **/OUTPUT**.

### **/MERGE**

Displays one of three possible states:

- Merge is not required
- Merge is pending
- Merge is in progress on node *node-name*, *n%* completed

### **/NAME[=*policy-name*]**

Used with **/POLICY=HBMM** to display the characteristics of a specific, named host-based minimerge (HBMM) policy or, if no policy name is specified, all named HBMM policies on the cluster.

### **/OUTPUT[=*filespec*]**

Outputs any messages to the specified file.

### **/POLICY=HBMM**

Displays the host-based minimerge (HBMM) policy associated with the specified devices.

HBMM is the only value supported for **/POLICY**, and it must be included.

If the command is issued with no device specification, information is output for all devices. There might be a noticeable delay between the output of device information or before returning to the DCL command prompt. This delay is normal.

### **/SITE=*n***

Displays every shadow set member device (and the virtual device of which it is a member) that has the site value specified by *n*.

## **Examples**

1. \$ SHOW SHADOW DSA112:  
\_DSA112: Volume Label: DSA112  
Virtual Unit State: Steady State  
No Enhanced Shadowing Features in use

```

VU Timeout Value      1200    VU Site Value      0
Copy/Merge Priority    5000    Mini Merge        Disabled
Served Path Delay      30

Device $1$DGA112
  Read Cost            2        Site 0
  Member Timeout       180

Device $1$DGA113
  Read Cost            2        Site 0
  Member Timeout       180

```

This display is for a shadow set that is in a steady state. That is, there are no active or pending merges or copy operations for this shadow set and HBMM has not been enabled.

2. \$ SHOW SHADOW DSA112:

```

_DSA112:  Volume Label: DSA112
Virtual Unit State: MiniMerge Active (5%), Copy Pending (32%) on NODE1
Enhanced Shadowing Features in use:
  Host-Based Minimerge (HBMM)

```

```

VU Timeout Value      1200    VU Site Value      0
Copy/Merge Priority    5000    Mini Merge        Enabled
Served Path Delay      30

```

```

HBMM Policy
  HBMM Reset Threshold: 50000
  HBMM Master lists:
    Up to any 6 nodes in the cluster
  HBMM bitmaps are active on NODE1,NODE2
  Modified blocks since bitmap creation: 137033

```

```

Device $1$DGA112
  Read Cost            2        Master Member, Merging (5%)
  Member Timeout       180      Site 0

```

```

Device $1$DGA113
  Read Cost            2        Copy Target (32%)
  Member Timeout       180      Site 0

```

This display is for a shadow set that is enabled for HBMM. A shadow set member copy and a shadow set merge are required for this shadow set. The shadow member copy was 32% complete when a merge became necessary. Because the merge was a minimerge, it preempted the copy and the status of the copy now displays as pending.

3. \$ SHOW SHADOW DSA12

```

_DSA12:  Volume Label: DGA12
Virtual Unit State: Merge Active (23%), Copy Pending (3%) on NODE1
Enhanced Shadowing Features in use:
  Host-Based Minimerge (HBMM)

```

```

VU Timeout Value      300    VU Site Value      5
Copy/Merge Priority    5000    Mini Merge        Enabled
Served Path Delay      0

```

```

HBMM Policy
  HBMM Reset Threshold: 50000
  HBMM Master lists:
    Up to any 2 of the nodes: NODE1,NODE2
  HBMM bitmaps are active on the following nodes: NODE2,NODE1
Modified blocks since bitmap creation: 254

```

```

Device $1$DGA12          Master Member, Merging (23%)
  Read Cost              2      Site 5
  Member Timeout         180

```

```

Device $1$DGA22          Copy Target (3%)
  Read Cost              2      Site 0
  Member Timeout         180

```

```

Device $1$DGA32          Merging (23%)
  Read Cost              2      Site 0
  Member Timeout         180

```

This example displays status information for shadow set DSA12. A minimerge operation takes precedence over a copy operation, so the copy has been stopped at 3% and the merge is now active and 23% completed.

Note that the VU site value and the site value for device \$1\$DGA12 are both 5. Therefore, read I/O to DSA12 on this system is directed to \$1\$DGA12.

#### 4. \$ SHOW SHADOW /BY\_PRIORITY

```

Device      Mbr
Name        Cnt  Priority Virtual Unit State      Active
                                     on Node
_DSA30:      2    5000   Steady State
_DSA12:      3    4000   Steady State
_DSA234:      3    3000   Not Mounted on this node
Total of 2 Operational shadow sets; 0 in Mount Verification; 1 not
mounted

```

The display resulting from this command shows that device DSA30 (with a priority of 5) will start a copy or merge operation on this system before DSA12 (with a priority of 4). It also shows that DSA30 is a two-member shadow set and that DSA12 is a three-member shadow set.

The last line of the display summarizes all the shadow sets and their states, including shadow sets that have exceeded their mount verification timeout limits. Operational shadow sets are shadow sets that are mounted with one or more members and that may or may not have copy or merge operations in progress. These shadow sets are available to applications for reads and writes.

#### 5. \$ SHOW SHADOW /BY\_PRIORITY

```

Device      Mbr
Name        Cnt  Priority Virtual Unit State      Active
                                     on Node
_DSA30: 2+1    5000   Merge Pending (23%), Copy Active (5%) NODE1
_DSA12:  2     4000   Steady State
_DSA234:      3    3000   Not Mounted on this node
Total of 2 Operational shadow sets; 0 in Mount Verification; 1 not
mounted

```

This display shows that a copy is being performed on system NODE1 and is 5% done. The member count (Mbr Cnt) of 2+1 indicates that there are two source members in the shadow set and

another member is being added. The shadow set had completed 23% of a merge when the third member was added. When the copy operation is complete, the merge will resume from that point.

6. \$ SHOW SHADOW /BY\_PRIORITY DSA11

Device	Mbr					Active
Name	Cnt	Priority	Virtual Unit	State		on Node
_DSA11:	3	5000	Merge	Active (29%)		NODE3

This command displays the status of only DSA11, which is 29% through a merge operation on NODE3.

7. \$ SHOW SHADOW /MERGE

Device	Volume Name	Status
_DSA1010:	FOOBAR	Merge Pending (23%), Copy Active (77%) on NODE1

This command requests the status of a merge operation. The display provides the status of the merge, but also reveals that a copy operation is currently active.

8. \$ SHOW SHADOW DSA1010 /ACTIVE

Device	Volume Name	Status
_DSA1010:	FOOBAR	Merge Active (25%) on NODE1

The copy shown to be in progress in the previous example has completed; now the merge has resumed and is 25% done. NODE1 is doing the merge.

9. \$ SHOW SHADOW DSA1010

```
_DSA1010: Volume Label: FOOBAR
Virtual Unit State: Merge Pending (0%)
Enhanced Shadowing Features in use:
    Host-Based Minimerge (HBMM)

VU Timeout Value      3600    VU Site Value      0
Copy/Merge Priority    5000    Mini Merge         Disabled
Served Path Delay     30

Device $252$DUA610      Master Member Merging (0%)
  Read Cost              2      Site 0
  Member Timeout         10

Device $252$DUA1010     Merging (0%)
  Read Cost              2      Site 0
  Member Timeout         10

Device $252$DUA716      Merging (0%)
  Read Cost              2      Site 0
  Member Timeout         10
```

In this example, another event has caused the set to go into a merge state. However, this set is not currently being acted on – perhaps because the system does not have any more SHADOW\_MAX\_COPY threads or because the relative priority of this shadow set is lower, causing

other merges to be completed first. When a system is able to perform the merge, the word Active appears in the display and the Merging percent begins to increase.

10. \$ SHOW SHADOW DSA12 /POLICY=HBMM

```
HBMM Policy for device _DSA12:
  HBMM Reset Threshold: 50000
  HBMM Master lists:
    Up to any 2 of the nodes: NODE1,NODE2,NODE3
  HBMM bitmaps are active on the following nodes: NODE2,NODE1
  HBMM Reset Count      4      Last Reset  9-JAN-2004 13:40:11.45
  Modified blocks since last bitmap reset: 142367
```

This command displays host-based minimerge (HBMM) information for device DSA12.

In this example, an HBMM policy has been defined for DSA12. No more than two of the systems NODE1 and NODE2 can have master bitmaps for DSA12 at any time. The bitmap is reset when the bitmap has bits set to represent a total of 50000 blocks written to DSA12. When this command was entered, both NODE1 and NODE2 had master bitmaps.

Note that the "modified blocks" value exceeds that of the reset threshold. This can happen because the bitmap is not reset immediately upon crossing the reset threshold. The reset threshold is checked periodically, and the interval for checking the reset threshold is controlled by the system parameter SHADOW\_HBMM\_RTC; the default is 150 seconds.

11. \$ SHOW SHADOW/POLICY=HBMM/NAME=PEAKS\_ISLAND

```
HBMM Policy PEAKS_ISLAND
  HBMM Reset Threshold: 50000
  HBMM Master lists:
    Up to any 2 of the nodes: NODE1,NODE2,NODE3
    Any 1 of the nodes: NODE4,NODE5
    Up to any 2 of the nodes: NODE6,NODE7,NODE8
```

This command displays the HBMM named policy PEAKS\_ISLAND.

12. \$ SHOW SHADOW /POLICY=HBMM

```
HBMM Policy for device _DSA12:
  HBMM Reset Threshold: 50000
  HBMM Master lists:
    Up to any 2 of the nodes: NODE1,NODE2
  HBMM bitmaps are active on NODE1,NODE2
  Modified blocks since bitmap creation: 254

HBMM Policy for device _DSA30:
  HBMM Reset Threshold: 50000
  HBMM Master lists:
    Up to any 2 of the nodes: FLURRY,FREEZE,HOTTUB

HBMM Policy for device _DSA99:
  HBMM Reset Threshold: 50000
  HBMM Master lists:
    Up to any 2 of the nodes: NODE1,NODE2,NODE3
    Any 1 of the nodes: NODE4,NODE5
    Up to any 2 of the nodes: ICEBAR,SWEDEN,MILANO

HBMM Policy for device _DSA999:
```

```
HBMM Reset Threshold: 50000
HBMM Master lists:
  Up to any 2 of the nodes: NODE1,NODE2,NODE3
  Any 1 of the nodes: NODE4,NODE5
  Up to any 2 of the nodes: ICEBAR,SWEDEN,MILANO
```

The command in this example displays a list of all shadow sets that have HBMM policies.

13. \$ SHOW SHADOW /POLICY=HBMM /NAME

```
HBMM Policy PEAKS_ISLAND
  HBMM Reset Threshold: 50000
  HBMM Master lists:
    Up to any 2 of the nodes: NODE1,NODE2,NODE3
    Any 1 of the nodes: NODE4,NODE5
    Up to any 2 of the nodes: NODE6,NODE7,NODE8

HBMM Policy POLICY_1
  HBMM Reset Threshold: 50000
  HBMM Master lists:
    Up to any 2 of the nodes: NODE1,NODE2,NODE3
    Any 1 of the nodes: NODE4,NODE5

HBMM Policy ICE_HOTELS
  HBMM Reset Threshold: 50000
  Up to any 2 of the nodes: QUEBEC,SWEDEN,FINLND
  Any 1 of the nodes: ALASKA,GRNLND
```

The command in this example displays a list of all named HBMM policies on the cluster.

14. \$ SHOW SHADOW DSA12 /OUTPUT=DSA12\_OUTPUT.LIS

The output of this **SHOW SHADOW** command is directed to the file named DSA12\_OUTPUT.LIS.

15. \$ SHOW SHADOW DSA12 /FULL

```
_DSA12:   VolumeLabel: DGA12
  Virtual Unit State:  Steady State
  Enhanced Shadowing Features in use:
    Host-Based Minimerge (HBMM)

Cluster Virtual Unit Status: 0001 - normal
Local Virtual Unit Status: 00000110 - Local Read,Policy Active

Total Devices          2          VU_UCB          81435180
Source Members         2          SCB LBN          003FEB5F
Act Copy Target        0          Generation      00A2BA31
Act Merge Target       0          Number         441DA800
Last Read Index        0          Master Mbr Index      0
Copy Hotblocks         0          Copy Collisions      0
SCP Merge Repair Cnt   0          APP Merge Repair Cnt  0
VU Timeout Value       300        VU Site Value        0
Copy/Merge Priority     5000       Mini Merge          Enabled
Served Path Delay      0

HBMM Policy
```

```

HBMM Reset Threshold: 50000
HBMM Master lists:
  Up to any 2 of the nodes: XYZ100,XYZ200
HBMM bitmaps are active on the following nodes: XYZ200,XYZ100
Modified blocks since bitmap creation: 254

```

```

Device $1$DGA12          Master Member
  Index 0 Status  000000A0  src,valid
  Ext. Member Status    00
  Read Cost          2      Site 0
  Member Timeout      180    UCB  81643840

```

```

Device $1$DGA22
  Index 1 Status  000000A0  src,valid
  Ext. Member Status    00
  Read Cost          2      Site 0
  Member Timeout      180    UCB  81642840

```

```

Device $1$DGA32
  Index 1 Status  000000A0  src,valid
  Ext. Member Status    00
  Read Cost          2      Site 0
  Member Timeout      180    UCB  81641840

```

This example shows a full information display for device DSA12.

#### 16. \$ SHOW SHADOW DSA0 /FULL

```

_DSA0:    Volume Label: TOPAZ_XA7V
  Virtual Unit State:    Steady State
  Cluster Virtual Unit Status: 0001 - normal
  Local Virtual Unit Status: 00000110 - enforce_local_read,
hbmm_eval_policy_enabled

```

```

Enhanced Shadowing Features in use:
  Dissimilar Device Shadowing (DDS)
  Host-Based Minimerge (HBMM)

```

```

Total Devices          2      VU_UCB          817AFD80
Source Members         2      SCB LBN          001F5C50
Act Copy Target        0      Generation      00A31141
Act Merge Target       0      Number          C6925F29
Last Read Index        0      Master Mbr Index    0
Copy Hotblocks         0      Copy Collisions     0
SCP Merge Repair Cnt   0      APP Merge Repair Cnt 0
VU Timeout Value       3600    VU Site Value       0
Copy/Merge Priority     5000    Mini Merge          Enabled
Served Path Delay      30

```

```

HBMM Policy
  HBMM Reset Threshold: 50000
  HBMM Master lists:
    Up to any 6 nodes in the cluster
  HBMM bitmaps are active on ABCD2,ABCD1
  Modified blocks since bitmap creation: 254

```

```
Device $252$DKA0           Master Member
  Index 0 Status  000000A0   mbr_src,mbr_valid
  Ext. Member Status      00
  Read Cost              2    Site 0
  Member Timeout         120   UCB  8163D880

Device $252$DKA100
  Index 1 Status  000000A0   mbr_src,mbr_valid
  Ext. Member Status      00
  Read Cost              2    Site 0
  Member Timeout         120   UCB  8163E880
```

This example shows sample output when both HBMM and Dissimilar Device Shadowing are in use.

## SHOW STATUS

SHOW STATUS — Displays the current status of your process.

### Format

**SHOW STATUS**

### Parameters

None.

### Description

The **SHOW STATUS** command verifies that your current process is running. The **SHOW STATUS** information can also indicate if the process is using an abnormal amount of CPU time, is opening too many files, or is accruing too many page faults. The information displayed includes the following:

- Current time and date
- Elapsed CPU time used by the current process
- Buffered I/O count
- Current working set size
- Open file count
- Direct I/O count
- Current amount of physical memory occupied
- Number of page faults

The information displayed by **SHOW STATUS** is similar to that displayed by the **Ctrl/T** function. (See the [SET CONTROL](#) command.)

### Example

```
$ SHOW STATUS
```

```
Status on 14-DEC-2001 12:56:48.68      Elapsed CPU :    0 00:00:55.02
Buff. I/O :      5117      Cur. ws. :    300      Open files :      1
Dir. I/O :      458      Phys. Mem. :   162      Page Faults : 8323
```

The **SHOW STATUS** command in this example displays the current status of your process.

## SHOW SYMBOL

SHOW SYMBOL — Displays the value of the specified symbol.

### Format

**SHOW SYMBOL** [*symbol-name*]

### Parameter

*symbol-name*

Specifies the name of the symbol whose value you want to display. You must specify a symbol name unless you use the **/ALL** qualifier. The asterisk (\*) and the percent sign (%) wildcard characters are allowed in the *symbol-name* parameter.

---

### Note

When you specify a wildcard character, the command searches only the local symbol table of the current command level and the global symbol table (as if you had specified **/LOCAL/GLOBAL**). You can search symbol tables of preceding command levels by symbol name, but not by wildcard.

---

## Description

The **SHOW SYMBOL** command searches for the specified symbol name in several places. First, it looks in the local symbol table of the current command level. Next, it searches the local symbol tables of preceding command levels (unless a wildcard was specified). Last, it searches the global symbol table. The **SHOW SYMBOL** command displays the first match it finds.

The **/LOCAL** and **/GLOBAL** qualifiers override the search order.

### Qualifiers

#### **/ALL**

Displays the current values of all symbols in the specified symbol table (**/LOCAL** or **/GLOBAL**). If you specify the **/ALL** qualifier and do not specify either the **/LOCAL** or the **/GLOBAL** qualifier, the **SHOW SYMBOL** command displays the contents of the local symbol table for the current command level.

#### **/GLOBAL**

Searches only the global symbol table for the specified symbol name. If you specify both the **/ALL** and **/GLOBAL** qualifiers, all names in the global symbol table are displayed.

**/LOCAL**

Searches only the local symbol table for the current command level for the specified symbol name. If you specify both the **/ALL** and **/LOCAL** qualifiers, all names in the local symbol table for the current command level are displayed.

**/LOG (default)****/NOLOG**

Controls whether the system generates an informational message if the symbol value has been truncated. The value is truncated if it exceeds 255 characters.

## Examples

1. 

```
$ SHOW SYMBOL PURGE
PURGE = "PURGE/KEEP=2"
```

The **SHOW SYMBOL** command in this example displays the current value of the symbol name **PURGE**. The command interpreter first searches the local symbol table for the current command level, then local symbol tables for preceding command levels, and finally the global symbol table. The single equal sign (=) following **PURGE** means it is a local symbol.

2. 

```
$ SHOW SYMBOL/GLOBAL/ALL
$FACILITY == "%X00000000"
$IDENT == "%X00000000"
$RESTART == "FALSE"
$SEVERITY == "1"
$STATUS == "%X10000001"
LOG == "@LOG"
TIME == "SHOW TIME"
```

The **SHOW SYMBOL** command in this example displays all the symbols defined in the global symbol table. Note that the symbols **\$FACILITY**, **\$IDENT**, **\$RESTART**, **\$SEVERITY**, and **\$STATUS**, which are maintained by the system, are also displayed.

3. 

```
$ SHOW SYMBOL/LOCAL TIME
%DCL-W-UNDSYM, undefined symbol
```

The **SHOW SYMBOL** command in this example searches only the local symbol table for the symbol **TIME**. The response indicates that **TIME** currently has no value.

## SHOW SYSTEM

**SHOW SYSTEM** — Displays status information about current processes.

### Format

**SHOW SYSTEM**

### Parameters

None.

## Description

The **SHOW SYSTEM** command displays the following information about processes on the system:

Time  
Process name and identification  
Processing state  
Priority  
Total process I/O count  
Cumulative processor time used  
Cumulative page faults  
Amount of physical memory being used  
Type of process

It also checks to see whether the machine is a multiprocessor. A machine is considered a multiprocessor if the following conditions are true:

- The system parameter **MULTIPROCESSING** is not equal to zero.
- The machine accommodates more than one CPU.

If the machine is a multiprocessor, the **SHOW SYSTEM** command includes information about the multiprocessing environment. Each process in the currently executing state (indicated by the **CUR** symbol) reveals which processor it is running on. It does this by including a number beside the **CUR** symbol.

The **SHOW SYSTEM** command examines the processes on the system without stopping activity on the system. This means that process information may change during the time that **SHOW SYSTEM** collects the data to be displayed. As a result, there may be minor inconsistencies in the **SHOW SYSTEM** display. For example, **SHOW SYSTEM** may display two processes that schedule state **CUR** on the same CPU.

## Qualifiers

**/BATCH (default)**  
**/NOBATCH**

Displays all batch jobs for the local system. When used with the **/CLUSTER** qualifier, the **/BATCH** qualifier displays all batch jobs in the OpenVMS Cluster environment. When you use the **/NOBATCH** qualifier, all batch jobs are excluded from the display.

**/CLUSTER**

Displays the specified processes on all nodes in an OpenVMS Cluster.

**/EXACT**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify a search string that must match the search string exactly and must be enclosed with quotation marks (" ").

If you specify the **/EXACT** qualifier without the **/SEARCH** qualifier, exact search mode is enabled when you set the search string with the Find (**E1**) key.

**/FULL**

Displays the user identification code (UIC), the processor type, and the process size, in addition to the default information. The UIC is displayed below the process name.

**/GRAND\_TOTAL**  
**/NOGRAND\_TOTAL (default)**

Displays a trailing line with the total of all processes matching the selection criteria and the total number of all processes on all systems displayed by the command. (See also the [/TOTAL](#) qualifier.)

**/HEADING**  
**/NOHEADING**

Displays a heading line above the system output. When you use the **/NOHEADING** qualifier, the heading line is excluded from the display.

**/IMAGE**

Lists all processes with their current image. (Requires WORLD privilege.)

**/HIGHLIGHT[=*keyword*]**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify the type of highlighting you want when a search string is found. When a string is found, the entire line is highlighted. You can use the following keywords: BOLD, BLINK, REVERSE, and UNDERLINE. BOLD is the default highlighting.

**/IDENT=*pid***

Displays all processes on the system that have the specified process identification (PID) code number.

**/INTERACTIVE**  
**/NOINTERACTIVE**

Displays all interactive processes on the system. When you use the **/NOINTERACTIVE** qualifier, all interactive processes are excluded from the display.

**/MULTITHREAD**

Displays all multithreaded processes for the local system. When used with the **/FULL** qualifier, the **/MULTITHREAD** qualifier displays information about each kernel thread in a multithreaded process.

For more information on kernel threads, see the relevant section in the [VSI OpenVMS Programming Concepts Manual](https://docs.vmssoftware.com/vsi-openvms-programming-concepts-manual-volume-i/#KTHREADS_STRUCTURE) [[https://docs.vmssoftware.com/vsi-openvms-programming-concepts-manual-volume-i/#KTHREADS\\_STRUCTURE](https://docs.vmssoftware.com/vsi-openvms-programming-concepts-manual-volume-i/#KTHREADS_STRUCTURE)].

**/NETWORK**  
**/NONETWORK**

Displays all network processes on the system. When you use the **/NONETWORK** qualifier, all network processes are excluded from the display.

**/NODE[=(*name*,...)]**

Displays all the processes on the specified node or nodes. If you enter the **/NODE** qualifier without a value, the qualifier displays all the processes on the local node of an OpenVMS Cluster environment.

**/OUTPUT[=*filespec*]**  
**/NOOUTPUT**

Controls where the output of the command is sent. By default, the output of the **SHOW SYSTEM** command is sent to the current SYS\$OUTPUT device (usually your terminal). To send the output to a file, use the **/OUTPUT** qualifier followed by a file specification.

The file specification may not include the asterisk (\*) and the percent sign (%) wildcard characters. If you enter a partial file specification (for example, specifying only a directory), SHOW is the default file name and .LIS is the default file type.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

**/OWNER\_UIC=*uic***

Displays all processes on the system that have the specified user identification code (UIC) number.

**/PAGE[=*keyword*]**  
**/NOPAGE (default)**

Controls the display of system information on the screen.

You can use the following keywords with the **/PAGE** qualifier:

Keyword	Description
CLEAR_SCREEN	Clears the screen before each page is displayed.
SCROLL	Displays information one line at a time.
SAVE[= <i>n</i> ]	Enables screen navigation of information, where <i>n</i> is the number of pages to store.

The **/PAGE=SAVE** qualifier allows you to navigate through screens of information. The **/PAGE=SAVE** qualifier stores up to 5 screens of up to 255 columns of information. When you use the **/PAGE=SAVE** qualifier, you can use the following keys to navigate through the information:

Key Sequence	Description
Up arrow key, <b>Ctrl/B</b>	Scroll up one line.
Down arrow key	Scroll down one line.
Left arrow key	Scroll left one column.
Right arrow key	Scroll right one column.
Find ( <b>E1</b> )	Specify a string to find when the information is displayed.
Insert Here ( <b>E2</b> )	Scroll right one half screen.
Remove ( <b>E3</b> )	Scroll left one half screen.
Select ( <b>E4</b> )	Toggle 80/132 column mode.
Prev Screen ( <b>E5</b> )	Get the previous page of information.
Next Screen ( <b>E6</b> ), <b>Return</b> , <b>Enter</b> , <b>Space</b>	Get the next page of information.
<b>F10</b> , <b>Ctrl/Z</b>	Exit. (Some utilities define these differently.)
Help ( <b>F15</b> )	Display utility help text.

Key Sequence	Description
Do (F16)	Toggle the display to oldest/newest page.
Ctrl/W	Refresh the display.

The **/PAGE** qualifier is not compatible with the **/OUTPUT** qualifier.

**/PROCESS[=*name*] (default)**  
**/NOPROCESS**

Displays all specified processes on the system. If you do not specify a process name with the **/PROCESS** qualifier, all processes are displayed.

When you use the **/NOPROCESS** qualifier with the **/CLUSTER** qualifier, only the node or nodes available on the cluster are displayed with their respective uptimes and operating system version.

You can include the asterisk (\*) and the percent sign (%) wildcard characters in the process name.

**/SCHEDULING\_CLASS[=*class\_name*]**  
**/NOSCHEDULING\_CLASS**

Displays processes that belong to a specific scheduling class (*class\_name*). If the class name is not specified, all class scheduled processes are displayed along with the name of their scheduling class.

**/SEARCH="*string*"**

Use with the **/PAGE=SAVE** qualifier to specify a string that you want to find in the information being displayed. Quotation marks are required for the **/SEARCH** qualifier, if you include spaces in the text string.

You can also dynamically change the search string by pressing the Find key (E1) while the information is being displayed. Quotation marks are not required for a dynamic search.

**/STATE=*process-state***

Displays all processes with the specified process state. You can include the asterisk (\*) and the percent sign (%) wildcard characters in the process-state name. The following process states are available:

CEF (Common event flag wait)	COLPG (Collided page wait)
COM (Computable)	COMO (Computable but outswapped)
CUR (Current)	FPG (Free page wait)
HIB (Hibernating)	HIBO (Hibernating and outswapped)
LEF (Local event flag wait)	LEFO (Local event flag wait and outswapped)
MUTEX <sup>1</sup> (Miscellaneous wait)	PFW (Page fault wait)
PSXFR (POSIX fork wait)	RWAST (AST wait)
RWBRK (Waiting for BROADCAST to finish)	RWCAP (CPU capability required)
RWCLU (Cluster transition wait)	RWCSV (Cluster server)
RWIMG (Image activation lock)	RWLCK (Lock ID database)
RWMBX (Mailbox full)	RWMPB (Modified page writer busy)

RWMPE (Modified page list empty)	RWNPG (Nonpaged pool)
RWPAG (Paged pool)	RWPFF (Page file full)
RWQUO (Pooled quota)	RWSCS (SCS wait)
RWSWP (Swapfile space list empty)	SUSP (Suspended)
SUSPO (Suspended and outswapped)	

<sup>1</sup>MUTEX is output if one of the RW\* states cannot be output.

## /SUBPROCESS

## /NOSUBPROCESS

Displays all subprocesses on the system. When you use the **/NOSUBPROCESS** qualifier, all subprocesses are excluded from the output.

## /TOTAL

## /NOTOTAL (default)

Displays a trailer after the system process list containing the total number of processes matching the selection criteria and the total number of processes on a system.

## /WRAP

## /NOWRAP (default)

Use with the **/PAGE=SAVE** qualifier to limit the number of columns to the width of the screen and to wrap lines that extend beyond the width of the screen to the next line.

The **/NOWRAP** qualifier extends lines beyond the width of the screen and can be seen when you use the scrolling (left and right) features provided by the **/PAGE=SAVE** qualifier.

# Examples

## 1. \$ SHOW SYSTEM

```
OpenVMS 7.3 on node KRYPTN 14-DEC-2001 17:45:47:78 Uptime 2 21:53:59
  Pid    Process Name State  Pri    I/O      CPU   Page flts Pages
 27400201 SWAPPER      HIB   16      0  0 00:29:52.05      0      0
 27401E03 DOCBUILD     LEF    4  37530  0 00:05:47.62  96421   601
 27402604 BATCH_789     LEF    4   3106  0 00:00:48.67   4909  2636 B
 27401C05 BATCH_60      LEF    6    248  0 00:00:06.83   1439  1556 B
 27400207 ERRFMT        HIB    8   6332  0 00:00:41.83     89   229
 27400208 CACHE_SERVER    HIB   16   2235  0 00:00:05.85     67   202
 27400209 CLUSTER_SERVER     HIB    8   4625  0 00:22:13.28    157   448
 2740020C JOB_CONTROL   HIB   10 270920  0 01:07:47.88   5163  1384
 2740020D CONFIGURE     HIB    9    125  0 00:00:00.53     104   264
.
.
.

27400E8D Sir Lancelot   LEF    5    226  0 00:00:07.87   4560   697
2740049A Guenevere       LEF    4    160  0 00:00:02.69    534   477
27401EA0 BATCH_523      CUR  4  17470  0 03:25:49.67   8128  5616 B
274026AF KING           CUR  6  14045  0 00:02:03.24  20032   397
274016D5 DAVIS          LEF    6    427  0 00:00:09.28   5275  1384
27401ED6 deGroot        HIB    5    935  0 00:00:10.17   3029  2204 S
274012D7 BATCH_689      LEF    4  49216  0 00:14:18.36   7021  3470 B
274032D9 DECW$MAIL       LEF    4   2626  0 00:00:51.19   4328  3087 B
274018E3 SERVER_0021     LEF    6    519  0 00:00:07.07   1500   389 N
```

```

274016E8 NMAIL_0008      HIB      4  10955  0 00:00:55.73   5652  151
274034EA DOERING         LEF      4   2132  0 00:00:23.85   5318  452
274022EB KERR            CUR 6    4    492  0 00:00:12.15   5181  459
274018EF DUFRESNE        LEF      5 121386  0 00:28:00.97   7233 4094
27401AF0 EMACS$RTA43     LEF      4  14727  0 00:03:56.54   8411 4224 S
27400CF4 EAGAN           HIB      5  25104  0 00:06:07.76  37407 1923
274020F5 TAN             LEF      7  14726  0 00:02:10.74  34262 1669
27400CF6 KELLEY          LEF      9  40637  0 00:05:15.63  18454  463
The SHOW SYSTEM command in this example was issued from a VAX system and
shows
all processes on the node EON.

```

The **SHOW SYSTEM** command in this example displays all processes on the system.

The information in this example includes the following:

- Process identification (PID) code – A 32-bit binary value that uniquely identifies a process.
- Process name – A 1 to 15-character string used to identify a process.
- Process state – The activity level of the process, such as COM (computing), HIB (hibernation), LEF (local event flag) wait, or CUR (if the process is current). If a multiprocessing environment exists, the display shows the CPU ID of the processor on which any current process is executing.

Note that the **SHOW SYSTEM** command examines the processes on the system without stopping activity on the system. In this example, process information changed during the time that the **SHOW SYSTEM** command collected the data to be displayed. As a result, this display includes two processes, named GAWAIN and S. Whiplash, with the state CUR on the same CPU, CPU ID 6 in the example.

- Current priority<sup>1</sup> – The priority level assigned to the process (the higher the number, the higher the priority).
- Total process I/O count<sup>1</sup> – The number of I/O operations the process has used thus far. This consists of both the direct I/O count and the buffered I/O count.
- Charged CPU time<sup>1</sup> – The amount of CPU time that a process has used so far.
- Number of page faults<sup>1</sup> – The number of exceptions generated by references to pages that are not in the process's working set.
- Pages<sup>1</sup> – The number of CPU-specific pages in physical memory that the process is currently occupying.
- Process indicator – Letter B indicates a Batch Job; letter S indicates a Sub Process; letter N indicates a Network Process. If the letter M precedes B, S, or N, it indicates that it is a multithreaded process.
- User identification code (UIC) – An 8-digit octal number assigned to a process. This number is displayed only if the **/FULL** qualifier is specified.

## 2. \$ SHOW SYSTEM /CLUSTER

<sup>1</sup>This information is displayed only if the process is currently in the balance set; if the process is not in the balance set, these columns contain the following message:

```
-- swapped out --
```

```

OpenVMS V7.3 on node ALPES 14-DEC-2001 09:09:58.61 Uptime 2 2:27:11
Pid      Process Name      State Pri I/O      CPU      Page flts Pages
31E00041 SWAPPER                  HIB   16   0  0 00:00:02.42      0      0
31E00047 CACHE_SERVER          HIB   16  58  0 00:00:00.26      80     36
31E00048 CLUSTER_SERVER         CUR    9 156  0 00:00:58.15    1168    90
31E00049 OPCOM                HIB    7 8007  0 00:00:33.46    5506   305
31E0004A AUDIT_SERVER          HIB    9  651  0 00:00:21.17    2267    22
31E0004B JOB_CONTROL         HIB   10 1030  0 00:00:11.02     795   202
.
.
.

```

The **SHOW SYSTEM** command in this example is taken from an Alpha system and shows all processes on all nodes of the cluster.

3. \$ SHOW SYSTEM /NODE=ALTOS

```

OpenVMS V7.3-2 on node ALTOS 15-SEP-2009 10:26:49.59 Uptime 73
13:53:35
Pid      Process Name      State Pri I/O      CPU      Page flts
Pages
24200201 SWAPPER                  HIB   16      0  0 00:02:41.09      0
0
24200207 CLUSTER_SERVER         CUR  7 13    19735  0 01:21:54.29      95
115
24200208 SHADOW_SERVER          HIB    6 5445809  0 00:04:53.18      68
122
24200209 CONFIGURE              HIB   10     23  0 00:04:20.35      42
30
2420020A USB$UCM_SERVER         HIB    6    165  0 00:00:02.72     164
225
2420020B LANACP                HIB   12     79  0 00:00:00.01     108
138
2420020D FASTPATH_SERVER       HIB   10     9  0 00:00:00.01      76
96
2420020E IPCACP                HIB   10    11  0 00:00:06.88      35
51
2420020F ERRFMT                HIB    7 210219  0 00:00:49.99     113
138
24200210 CACHE_SERVER          HIB   16   18716  0 00:00:01.33      31
46

```

The **SHOW SYSTEM** command in this example is taken from an Alpha system and shows all processes on the node ALTOS.

4. \$ SHOW SYSTEM/NOPROCESS/CLUSTER/FULL

```

OpenVMS V7.3-2 on node ALTOS 6-AUG-2009 14:31:26.31 Uptime 33
17:58:12
hp AlphaServer GS1280 7/1150

OpenVMS V7.3-2 on node ARUSHA 6-AUG-2009 14:31:26.32 Uptime 32
21:42:11
hp AlphaServer GS1280 7/1150

OpenVMS V8.3-1H1 on node BANFF 6-AUG-2009 14:31:26.33 Uptime 33
17:44:02
HPE rx2600 (1.30GHz/3.0MB)

```

```
OpenVMS V7.3-2 on node CHOBE 6-AUG-2009 14:31:26.33 Uptime 32
21:14:00
hp AlphaServer GS1280 7/1150
```

This example displays only the nodes available on the cluster with their respective uptimes and operating system versions because the **/NOPROCESS** qualifier suppresses the display of processes. The **/FULL** qualifier also displays the type of hardware on which the system is running.

5. \$ SHOW SYSTEM/PROCESS=S\*

```
OpenVMS V7.3 on node AAAAAA 12-MAY-2001 10:30 AM Uptime 3 12:43:55
  Pid    Process Name  State  Pri  I/O      CPU      Page flts  Pages
20C00101 SWAPPER        HIB    16    0  0 00:00:00.05      0      0
20C0010E SHADOW_SERVER  HIB     6    7  0 00:00:00.03     32      4
20C0010F SECURITY_SERVER HIB    10   35  0 00:00:02.16    292    323
20C00110 SMISERVER      HIB     9   67  0 00:00:00.20    152    131
20C0011A STEFANELLI   CUR    0    4  63 0 00:00:00.29    538     55
```

This example displays only the processes on the system that begin with the letter S.

6. \$ SHOW SYSTEM/NOHEADING/OUTPUT=SYSPROC.DAT

```
20C00101 SWAPPER        HIB    16    0  0 00:00:00.05      0      0
20C00105 CONFIGURE      HIB    10   24  0 00:02:00.86     41     21
20C00107 IPCACP         HIB    10    9  0 00:00:00.04     33     43
20C00108 ERRFMT         HIB     7 3583  0 00:00:04.31     50     61
20C00109 CACHE_SERVER   HIB    16    3  0 00:00:00.02     27     35
20C0010A CLUSTER_SERVER HIB    10   11  0 00:00:00.10     59     75
```

This example places the display of system processes into the SYSPROC.DAT file without the heading information using the **/OUTPUT** qualifier. In this way, you can create a data file for processing because the heading is suppressed using the **/NOHEADING** qualifier.

7. \$ SHOW SYSTEM/IDENT=20C0010D/FULL

```
OpenVMS V7.3 on node AAAAAA 12-MAY-2001 10:35 AM Uptime 3 12:48:19
DEC 4000 Model 610
  Pid    Process Name  State  Pri  I/O      CPU      Page flts  Pages
20C0010D JOB_CONTROL  HIB    10   41  0 00:00:00.25     51     66
[SYSTEM]                                     528Kb
```

This example displays a system process by PID number.

8. \$ SHOW SYSTEM/OWNER=TIMMER

```
OpenVMS V7.3 on node AAAAAA 12-MAY-2001 10:34 AM Uptime 3 12:47:37
  Pid    Process Name  State  Pri  I/O      CPU      Page flts  Pages
20C00119 DECW$TE_0119  LEF     6  334  0 00:00:01.00    975    657
20C0011A TIMMER      LEF     8   63  0 00:00:00.29    538     55
20C0011B _RTA1:      CUR    0    4  554  0 00:00:01.72   1771     70
```

This example displays the system processes belonging to user TIMMER.

9. \$ SHOW SYSTEM/STATE=L\*

```
OpenVMS V7.3 on node AAAAAA 12-MAY-2001 10:36 AM Uptime 3 12:49:46
  Pid    Process Name  State  Pri  I/O      CPU      Page flts  Pages
20C00119 DECW$TE_0119  LEF     6  334  0 00:00:01.00    975    657
20C0011A STADLER      LEF     8   63  0 00:00:00.29    538     55
```

This example displays the system processes with process states that begin with the letter L.

10. \$ SHOW SYSTEM/MULTITHREAD

```
OpenVMS V7.3 on node ZIMBER 30-OCT-2001 11:34:11.51 Uptim 8 20:21:31
```

Pid	Process Name	State	Pri	I/O	CPU	Page flts	Pages
0000008C	SECURITY_SERVER	HIB	11	131	0 00:55:25.25	4370	194 M

\$ SHOW SYSTEM/MULTITHREAD/FULL

OpenVMS V7.3 on node ZIMBER 30-OCT-2001 11:34:13.98 Uptime 8 20:21:34  
AlphaStation 400 4/233

Pid	Process Name	State	Pri	I/O	CPU	Page flts	Pages
0000008C	SECURITY_SERVER	HIB	11	131	0 00:55:25.26	4370	194 M
0000010C		HIB	11				
	[SYSTEM]						1552Kb

These examples show the results of the **/MULTITHREAD** qualifier and the combination results of the **/MULTITHREAD** and **/FULL** qualifiers.

#### 11. \$ SHOW SYSTEM/CLUSTER/TOTAL/SUBPROCESS/GRAND\_TOTAL

OpenVMS V7.2-2 on node CHEER 27-JAN-2003 16:09:26.94 Uptime 3  
23:20:43

Pid	Process Name	State	Pri	I/O	CPU	Page flts	Pages
262000AC	DTGREET	LEF	4	757	0 00:00:06.76	476	493
S							

Total of 1/31 total processes.

OpenVMS V7.3-2 on node GATOR 27-JAN-2003 16:09:26.95 Uptime 1  
14:41:58

Pid	Process Name	State	Pri	I/O	CPU	Page flts	Pages
27000428	DTWM	LEF	4	26422	0 00:00:11.61	715	846
S							
270004B9	SYSTEM_141	HIB	1	155	0 00:00:00.12	351	393
S							

Total of 2/37 total processes.

OpenVMS V7.3-1 on node FISHER 27-JAN-2003 16:09:26.97 Uptime 5  
02:16:57

Pid	Process Name	State	Pri	I/O	CPU	Page flts	Pages
25A00149	DTWM	LEF	4	395380	0 00:12:51.27	712	837
S							
25A010AE	SYSTEM_76	HIB	1	209	0 00:00:00.66	339	381
S							

Total of 2/34 total processes.

OpenVMS V7.1-2 on node MONKEY 27-JAN-2003 16:09:27.05 Uptime 1  
14:56:02

Pid	Process Name	State	Pri	I/O	CPU	Page flts	Pages
26C00130	DTWM	LEF	6	5868	0 00:00:11.84	642	777
S							

Total of 1/31 total processes.

OpenVMS V7.3-2 on node QUERY 27-JAN-2003 16:09:27.10 Uptime 3  
22:16:23

Pid	Process Name	State	Pri	I/O	CPU	Page	flts	Pages
26601139	SYSTEM_203	HIB	2	157	0 00:00:00.68		346	387
S								
2660013A	DTWM	LEF	4	275709	0 00:10:24.99		728	852
S								

Total of 2/37 total processes.

Grand total of 8/183 processes on 6 nodes.

The **SHOW SYSTEM** command in this example displays the total count of subprocesses and processes on each node of a cluster. The last line lists the grand total of all subprocesses in the cluster (8) followed by the grand total of all processes in the cluster (183).

## SHOW TERMINAL

**SHOW TERMINAL** — Displays the current characteristics of a specific terminal. Each characteristic corresponds to an option of the **SET TERMINAL** command.

### Format

**SHOW TERMINAL** [*device-name*[:]]

### Parameter

*device-name*[:]

Specifies the name of the terminal for which you want the characteristics displayed. The default is your terminal (SYS\$COMMAND).

### Description

The **SHOW TERMINAL** command displays the information about terminal settings for such things as terminal speed, width, number of lines, graphics, and device type.

Note that the **SHOW TERMINAL** command does not describe terminal fallback characteristics if any are activated. If the Terminal Fallback Facility (TFF) is enabled, you can invoke the Terminal Fallback Utility (TFU) and issue the subcommand **SHOW TERMINAL/FALLBACK**. For more information, see the *OpenVMS Terminal Fallback Utility Manual*.

### Qualifiers

**/BRIEF**

Displays a subset of more commonly used terminal characteristics.

**/FULL (default)**

Displays all terminal characteristics.

**/OUTPUT[=*filespec*]  
/NOOUTPUT**

Controls where the output of the command is sent. If you do not enter the qualifier, or if you enter the **/OUTPUT** qualifier without a file specification, the output is sent to the current process default output stream or device, identified by the logical name SYS\$OUTPUT.

If you enter the **/OUTPUT** qualifier with a partial file specification (for example, specifying only a directory), **SHOW** is the default file name and **.LIS** the default file type. If you enter a file specification, it cannot include the asterisk (\*) and the percent sign (%) wildcard characters.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

**/PERMANENT**

Requires LOG\_IO (logical I/O) or PHY\_IO (physical I/O) privilege.

Displays the permanent characteristics of the terminal.

## Examples

**1. \$ SHOW TERMINAL/BRIEF**

```
Terminal: _RTA1:      Device_Type: VT300_Series  Owner: _RTA1:
                                     Username: REHOR
```

**Terminal Characteristics:**

Speed: 9600	Page: 62	Width: 80
No Remote	Hostsync	TTsync
No Modem	Broadcast	Wrap
No Hangup	No Disconnect	Overstrike editing
No Dialup	Application keypad	Line Editing

In this example, the **SHOW TERMINAL** command displays a subset of the more commonly used terminal characteristics.

**2. \$ SHOW TERMINAL/FULL**

```
Terminal: _TTE4:      Device_Type: VT102      Owner: FRANKLIN
Physical Terminal: _LTA49
  Input: 9600      LFfill: 0      Width: 80      Parity: None
  Output: 9600     CRfill: 0      Page: 24
```

**Terminal Characteristics:**

Interactive	Echo	Type_ahead	No Escape
No Hostsync	TTsync	Lowercase	Tab
Wrap	Scope	No Remote	Eightbit
Broadcast	No Readsyc	No Form	Fulldup
No Modem	No Local_echo	No Autobaud	Hangup
No Brdcstmbx	No DMA	No Altypeahd	Set_speed
Line Editing	Overstrike editing	No Fallback	No Dialup
No Secure server	No Disconnect	No Psthru	No Syspassword
No SIXEL Graphics	Soft Characters	Printer port	Numeric Keypad
ANSI_CRT	No Regis	No Block_mode	Advanced_video
Edit_mode	DEC_CRT	DEC_CRT2	No DEC_CRT3

In this example, the **SHOW TERMINAL** command displays the characteristics of this specific terminal. If you are displaying statistics about a terminal allocated to another user, the input, output, LFfill, CRfill, width, page, and parity statistics are not shown (see the next example).

## 3. \$ SHOW TERMINAL/FULL

```
Terminal: _RTA1:      Device_Type: VT300_Series  Owner: _RTA1:
                                     Username: VILLA
Remote Port Info: NODE12::VILLA
```

```
Input:    9600      LFfill:  0      Width:   80      Parity: None
Output:   9600      CRfill:  0      Page:    62
```

## Terminal Characteristics:

Interactive	Echo	Type_ahead	No Escape
Hostsync	TTsync	Lowercase	Tab
Wrap	Scope	No Remote	Eightbit
Broadcast	No Readsynchron	No Form	Fullldup
No Modem	No Local_echo	No Autobaud	No Hangup
No Brdcstmbx	No DMA	No Altypeahd	Set_speed
No Commsync	Line Editing	Overstrike editing	No fallback
No Dialup	No Secure server	No Disconnect	No Psthru
No Syspassword	SIXEL Graphics	No Soft Characters	Printer port
Application keypad	ANSI_CRT	Regis	No Block_mode
Advanced_video	Edit_mode	DEC_CRT	DEC_CRT2
DEC_CRT3	No DEC_CRT4	No DEC_CRT5	Ansi_Color
VMS Style Input	<CTRL-H> Delete		

In this example, the **SHOW TERMINAL** command displays the full terminal characteristics.

## SHOW TIME

SHOW TIME — Displays the current date and time.

### Format

**SHOW [DAY]TIME**

### Parameters

None.

### Example

```
$ SHOW TIME
3-NOV-2001 00:02:00
```

The **SHOW TIME** command in this example displays the current date and time.

## SHOW TRANSLATION

SHOW TRANSLATION — Displays the first translation found for the specified logical name. You can specify the tables that are searched. **Requires read (R) access to a logical name table to display information about any logical name cataloged in that table.**

### Format

**SHOW TRANSLATION *logical-name***

## Parameter

### *logical-name*

Specifies the logical name whose translation you want to display.

## Description

The **SHOW TRANSLATION** command searches one or more logical name tables for a specified logical name and returns the equivalence name of the first match found. You can specify the tables you want to search. If you do not specify a table, **SHOW TRANSLATION** searches the tables defined by the logical name LNM\$DCL\_LOGICAL.

The logical name LNM\$DCL\_LOGICAL contains the list of logical name tables and the order in which they are searched. Unless LNM\$DCL\_LOGICAL has been redefined for your process, the process, job, group, and system logical name tables are searched, in that order. The first match found is displayed. (To see how LNM\$DCL\_LOGICAL is defined for your process, enter the command **SHOWLOGICAL /TABLE=LNMDIRECTORIES LNM\$DCL\_LOGICAL**.)

If a table contains more than one entry with the same name, but each name has a different mode, then the translation for the name with the outermost (least privileged) mode is returned.

The **SHOW TRANSLATION** command is similar to the **SHOW LOGICAL** command; however, the **SHOW TRANSLATION** command is executed within the DCL command interpreter (the **SHOW LOGICAL** command calls an image). Therefore, the **SHOW TRANSLATION** command does not cause the current image to exit and does not deassign user mode logical names. Also, the **SHOW TRANSLATION** command does not display iterative translations of a name.

## Qualifier

### */TABLE=name*

Searches the specified table. The default value for the *name* parameter is LNM\$DCL\_LOGICAL.

If you specify the table name by using a logical name that translates to more than one table, then each table is searched in the order specified until a match is found.

## Examples

1. 

```
$ SHOW TRANSLATION PAYROLL
PAYROLL = DISK1:[ACCOUNTS.WORKING]FACTOR1.DAT;37 (LNM$PROCESS_TABLE)
```

The **SHOW TRANSLATION** command in this example displays the translation for the logical name PAYROLL and also displays the name of the table where the logical name was found. In this example, PAYROLL was found in LNM\$PROCESS\_TABLE, the process logical name table.

2. 

```
$ DEFINE DISK DKA1:
$ DEFINE/GROUP DISK DKA2:
$ SHOW TRANSLATION DISK
DISK = DKA1:(LNM$PROCESS_TABLE)
```

The **DEFINE** commands in this example place entries for the logical name DISK in both the process and group logical name tables. Then, the **SHOW TRANSLATION** command shows the translation associated with the logical name DISK. By default, the process, job, group, and system tables are

searched (in that order). The first match found is displayed. The logical name `DISK` from the process table (`LN$PROCESS_TABLE`) is displayed because it is found before the name `DISK` in the group table.

- ```
3. $ RUN ORION
    Ctrl/Y
    $ SHOW TRANSLATION TERMINAL
      TERMINAL = _TTT3: (LN$PROCESS_TABLE)
    $ CONTINUE
```

The **RUN** command in this example executes the image `ORION.EXE`. After the **Ctrl/Y** function interrupts the image, the **SHOW TRANSLATION** command displays a logical name assignment. The **CONTINUE** command resumes the execution of the image.

- ```
4. $ SHOW TRANSLATION/TABLE=LN$SYSTEM USER
    USER = "DKA2:" (LN$SYSTEM_TABLE)
```

The **SHOW TRANSLATION** command in this example displays the translation for the logical name `USER`. Because a table name is specified, the **SHOW TRANSLATION** command does not use the default search order. Only the specified table, `LN$SYSTEM`, is searched. `LN$SYSTEM` is the system logical name table.

- ```
5. $ DEFINE/TABLE=LN$PROCESS_DIRECTORY MYPROC -
    _$ TEST_TABLE, LN$PROCESS
    $ SHOW TRANSLATION/TABLE=MYPROC FILER
      FILER = "[SMITH.FILER]" (TEST_TABLE)
```

In this example, `MYPROC` defines a list of logical name tables that you want searched. It asks the system to first search `TEST_TABLE` (a user-defined table) and then to search `LN$PROCESS` (the process logical name table). `MYPROC` is stored in `LN$PROCESS_DIRECTORY`, the process directory table. When you enter the **SHOW TRANSLATION** command to find `FILER` in the `MYPROC` table, the tables `TEST_TABLE` and `LN$PROCESS` are searched, in that order. The first match found is displayed.

## SHOW USERS

**SHOW USERS** — Displays the user name and node name (in an OpenVMS Cluster environment) of interactive, subprocess, and batch users on the system.

### Format

**SHOW USERS** [*username*]

### Parameter

*username*

Specifies the user about whom you want information. The asterisk (\*) and the percent sign (%) wildcard characters are allowed. If you specify a string, all users whose user names begin with the string are displayed. For example, if you specify the string `MAR`, all user names that begin with `MAR` are displayed. If no user exists whose name matches the specified string, an informational message tells you that no processes were found.

If you omit the *username* parameter, a list of all interactive, subprocess, and batch users is displayed.

## Qualifiers

### **/BATCH** **/NOBATCH**

Displays all batch users in the OpenVMS Cluster environment. To restrict the display to users on specific nodes, use the **/BATCH** qualifier with the **/NODE** qualifier. When you use the **/NOBATCH** qualifier, all batch users are excluded from the display.

### **/CLUSTER**

Displays the specified user names on all nodes in an OpenVMS Cluster environment.

### **/EXACT**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify a search string that must match the search string exactly and must be enclosed with quotation marks (" ").

If you specify the **/EXACT** qualifier without the **/SEARCH** qualifier, exact search mode is enabled when you set the search string with the Find (**E1**) key.

### **/FULL**

Displays the user name, the node name, the process name, the process identification (PID) code, terminal names (both virtual and physical), and port information of all interactive, subprocess, and batch users on the system.

### **/HEADING (default)** **/NOHEADING**

Displays a heading line above the system output. When you use the **/NOHEADING** qualifier, the heading line is excluded from the display.

### **/HIGHLIGHT[=keyword]**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify the type of highlighting you want when a search string is found. When a string is found, the entire line is highlighted. You can use the following keywords: **BOLD**, **BLINK**, **REVERSE**, and **UNDERLINE**. **BOLD** is the default highlighting.

### **/INTERACTIVE** **/NOINTERACTIVE**

Displays all interactive processes held by users in the OpenVMS Cluster environment. To restrict the display to users on specific nodes, use the **/INTERACTIVE** qualifier with the **/NODE** qualifier. When you use the **/NOINTERACTIVE** qualifier, all interactive processes held by users in the OpenVMS Cluster environment are excluded from the display.

### **/NETWORK** **/NONETWORK**

Displays all network users in the OpenVMS Cluster environment. To restrict the display to users on specific nodes, use the **/NETWORK** qualifier with the **/NODE** qualifier. When you use the **/NONETWORK** qualifier, all network users in the OpenVMS Cluster environment are excluded from the display.

**/NODE[=(*name*,...)]**

Displays all interactive, subprocess, and batch users on the specified node or nodes. If you enter the **/NODE** qualifier without a value, the qualifier displays all the interactive, subprocess, and batch users on the local node.

**/OUTPUT[=*filespec*]****/NOOUTPUT**

Controls where the output of the command is sent. By default, the output of the **SHOW USERS** command is sent to the current SYS\$OUTPUT device (usually your terminal). To send the output to a file, use the **/OUTPUT** qualifier followed by a file specification.

The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification. If you enter a partial file specification (for example, specifying only a directory), **SHOW** is the default file name and **.LIS** is the default file type.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

**/PAGE[=*keyword*]****/NOPAGE (default)**

Controls the display of user information on the screen.

You can use the following keywords with the **/PAGE** qualifier:

| Keyword           | Description                                                                               |
|-------------------|-------------------------------------------------------------------------------------------|
| CLEAR_SCREEN      | Clears the screen before each page is displayed.                                          |
| SCROLL            | Displays information one line at a time.                                                  |
| SAVE[= <i>n</i> ] | Enables screen navigation of information, where <i>n</i> is the number of pages to store. |

The **/PAGE=SAVE** qualifier allows you to navigate through screens of information. The **/PAGE=SAVE** qualifier stores up to 5 screens of up to 255 columns of information. When you use the **/PAGE=SAVE** qualifier, you can use the following keys to navigate through the information:

| Key Sequence                                                              | Description                                                 |
|---------------------------------------------------------------------------|-------------------------------------------------------------|
| Up arrow key, <b>Ctrl/B</b>                                               | Scroll up one line.                                         |
| Down arrow key                                                            | Scroll down one line.                                       |
| Left arrow key                                                            | Scroll left one column.                                     |
| Right arrow key                                                           | Scroll right one column.                                    |
| Find ( <b>E1</b> )                                                        | Specify a string to find when the information is displayed. |
| Insert Here ( <b>E2</b> )                                                 | Scroll right one half screen.                               |
| Remove ( <b>E3</b> )                                                      | Scroll left one half screen.                                |
| Select ( <b>E4</b> )                                                      | Toggle 80/132 column mode.                                  |
| Prev Screen ( <b>E5</b> )                                                 | Get the previous page of information.                       |
| Next Screen ( <b>E6</b> ), <b>Return</b> ,<br><b>Enter</b> , <b>Space</b> | Get the next page of information.                           |

| Key Sequence       | Description                                      |
|--------------------|--------------------------------------------------|
| <b>F10, Ctrl/Z</b> | Exit. (Some utilities define these differently.) |
| <b>Help (F15)</b>  | Display utility help text.                       |
| <b>Do (F16)</b>    | Toggle the display to oldest/newest page.        |
| <b>Ctrl/W</b>      | Refresh the display.                             |

The **/PAGE** qualifier is not compatible with the **/OUTPUT** qualifier.

### **/SEARCH="string"**

Use with the **/PAGE=SAVE** qualifier to specify a string that you want to find in the information being displayed. Quotation marks are required for the **/SEARCH** qualifier, if you include spaces in the text string.

You can also dynamically change the search string by pressing the Find key (**E1**) while the information is being displayed. Quotation marks are not required for a dynamic search.

### **/SUBPROCESS**

### **/NOSUBPROCESS**

Displays all subprocess users in the OpenVMS Cluster environment. To restrict the display to users on specific nodes, use the **/SUBPROCESS** qualifier with the **/NODE** qualifier. When you use the **/NOSUBPROCESS** qualifier, all subprocess users in the OpenVMS Cluster environment are excluded from the output.

### **/WRAP**

### **/NOWRAP (default)**

Use with the **/PAGE=SAVE** qualifier to limit the number of columns to the width of the screen and to wrap lines that extend beyond the width of the screen to the next line.

The **/NOWRAP** qualifier extends lines beyond the width of the screen and can be seen when you use the scrolling (left and right) features provided by the **/PAGE=SAVE** qualifier.

## Examples

#### 1. \$ SHOW USERS

```
OpenVMS User Processes at 12-MAY-2001 10:37 AM
Total number of users = 4,  number of processes = 14
```

| Username    | Node   | Interactive | Subprocess | Batch |
|-------------|--------|-------------|------------|-------|
| S_SKONETSKI | BBBBBB | 1           |            |       |
| WISNIEWSKI  | XXXXXX | 4           | 2          |       |
| HIBBITS     | AAAAAA | 1           | 4          |       |
| VAXMAN      | AAAAAA | 2           |            |       |

The **SHOW USERS** command in this example displays the user names and node names of all current interactive, subprocess, and batch users on the system.

#### 2. \$ SHOW USERS/NOHEADING/OUTPUT=SYSUSERS.DAT

```
$ TYPE SYSUSERS.DAT
```

|             |        |   |   |
|-------------|--------|---|---|
| S_SKONETSKI | BBBBBB | 1 |   |
| WISNIEWSKI  | XXXXXX | 4 | 2 |

|         |        |   |   |
|---------|--------|---|---|
| HIBBITS | AAAAAA | 1 | 4 |
| VAXMAN  | AAAAAA | 2 |   |

The **SHOW USERS** command in this example displays the user names and node names of all current interactive, subprocess, and batch users on the system without the heading text using the **/NOHEADING** qualifier. Using the **/OUTPUT** qualifier, you can write the output to a file for processing or later review.

3. \$ SHOW USERS \*LES\*

OpenVMS User Processes at 12-MAY-2001 10:41 AM  
Total number of users = 3, number of processes = 10

| Username   | Node   | Interactive | Subprocess | Batch |
|------------|--------|-------------|------------|-------|
| THALES     | MILETS | —           | —          | 1     |
| PRAXITELES | LESBOS | 5           | 2          |       |
| PERICLES   | ISLAND | 1           |            |       |

The **SHOW USERS** command in this example displays the user name and node names of all users whose user names contain the string LES.

4.

\$ SHOW USERS/FULL/NODE=AAAAAA

OpenVMS User Processes at 9-JUN-2001 02:23 PM  
Total number of users = 3, number of processes = 3

| Username     | Node   | Process Name | PID      | Terminal              |
|--------------|--------|--------------|----------|-----------------------|
| DJONES       | AAAAAA | Aaaaaa_fta2: | 2180012D | FTA2:                 |
| DYSLI        | AAAAAA | DYSLI        | 2180011A | FTA1:                 |
| SINDBY       | AAAAAA | SINDBY       | 2180011E | RTA1: (JJJJJ::SINDBY) |
| <tag>(login) | B4B4   | _WSA1        | 3100009F |                       |

The **SHOW USERS** command in this example displays the user name, the local node, the process name, the process identification (PID) number, the terminal names (both virtual and physical), and port information for all interactive, subprocess, and batch users on system AAAAAA. A user name of <LOGIN> indicates that someone is in the process of logging in.

5. \$ SHOW USERS /NODE=(AAAAAA,BBBBBB,MMMMMM)

OpenVMS User Processes at 9-JUN-2001 02:23 PM  
Total number of users = 5, number of processes = 7

| Username | Node   | Process Name | PID      | Terminal                 |
|----------|--------|--------------|----------|--------------------------|
| BRICKLEY | BBBBBB | BRICKLEY     | 21E0009E | RTA1: (CBREEZ::BRICKLEY) |
| DCLDCT   | MMMMMM | Mmmmmm_rta1: | 2020015D | RTA1: (MMMMMM::DJOHNSON) |
| SMITH    | AAAAAA | Aaaaaa_fta2: | 2180012D | FTA2:                    |
| PETERSON | MMMMMM | Mmmmmm_fta1: | 2020013E | FTA1:                    |
| PRESTON  | MMMMMM | Mmmmmm_rta3: | 20200184 | RTA3: (DDRSND::PRESTON)  |
| PRUSS    | AAAAAA | PRUSS        | 2180011E | RTA1: (IVOK::PRUSS)      |
| RABAHY   | AAAAAA | RABAHY       | 2180011A | FTA1:                    |

The **SHOW USERS** command in this example displays the user name and node name for all interactive, batch, and subprocess users on the nodes AAAAAA, BBBBBB, and MMMMMM.

## SHOW WORKING\_SET

**SHOW WORKING\_SET** — Displays the working set limit, quota, and extent (in pagelets and CPU-specific pages) assigned to the current process. This information also can be output in bytes.

## Format

**SHOW WORKING\_SET**

## Parameters

None.

## Qualifier

**/OUTPUT[=*filespec*]**

**/NOOUTPUT**

Controls where the output of the command is sent. If you do not enter the qualifier, or if you enter the **/OUTPUT** qualifier without a file specification, the output is sent to the current process default output stream or device, identified by the logical name SYS\$OUTPUT.

If you enter the **/OUTPUT** qualifier with a partial file specification (for example, specifying only a directory), **SHOW** is the default file name and **.LIS** the default file type. The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

## Examples

```
1. $ SHOW WORKING_SET
Working Set (pagelets)  /Limit= 2000  /Quota= 4000 /Extent= 6000
Adjustment enabled    Authorized Quota= 4000  Authorized Extent= 6000
Working Set (8Kb pages) /Limit= 125   /Quota= 250  /Extent= 375
                        Authorized Quota= 250   Authorized Extent= 375
```

This example shows the **SHOW WORKING\_SET** command on Alpha. The process has a working set limit of 2000 pagelets (125 pages) and a quota of 4000 pagelets (250 pages), and the current quota is equal to the authorized limit (4000 pagelets; 250 pages). It also shows that the current process has a working set extent of 6000 pagelets (375 pages) and that the current extent is equal to the authorized limit (6000 pagelets; 375 pages). A pagelet is 512 bytes.

```
2. $ SHOW WORKING_SET
Working Set (pagelets)  /Limit=3632  /Quota=8192  /Extent=524288
Adjustment enabled      Authorized Quota=8192  Authorized
Extent=524288

Working Set (8Kb pages) /Limit=227   /Quota=512   /Extent=32768
                        Authorized Quota=512   Authorized Extent=32768

$ SET PROCESS/UNITS=BYTES
$ SHOW WORKING_SET
Working Set (bytes)     /Limit=1.77MB  /Quota=4MB   /Extent=256MB
Adjustment enabled      Authorized Quota=4MB   Authorized Extent=256MB
```

This example shows the same display, first in bits and then in bytes.

```
3. $ SHOW WORKING_SET
Working Set             /Limit= 180   /Quota= 350           /Extent=1200
Adjustment enabled     Authorized Quota= 350  Authorized Extent=1200
```

This example shows the **SHOW WORKING\_SET** command. The process has a working set limit of 180 pages, a quota of 350 pages, and the quota is equal to the authorized limit (350 pages). It also shows that the current process has a working set extent of 1200 and that the current extent is equal to the authorized limit (1200).

## SORT

**SORT** — Invokes the Sort/Merge utility, which reorders the records in a file into a defined sequence and creates either a new file of the reordered records or an address file by which the reordered records can be accessed.

### Format

**SORT** *input-filespec*[,...] *output-filespec*

### Description

For more information about the Sort/Merge utility, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#SORT_CH) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#SORT\_CH] or online help.

## SPAWN

**SPAWN** — Creates a subprocess of the current process. Portions of the current process context are copied to the subprocess. **The RESOURCE\_WAIT state is required to spawn a process. Requires TMPMBX (temporary mailbox) or PRMMBX (permanent mailbox) privilege. The SPAWN command does not manage terminal characteristics. The SPAWN and ATTACH commands cannot be used if your terminal has an associated mailbox.**

### Format

**SPAWN** [*command-string*]

### Parameter

*command-string*

Specifies a command string of less than 132 characters that is to be executed in the context of the created subprocess. When the command completes execution, the subprocess terminates and control returns to the parent process. If both a command string and the **/INPUT** qualifier are specified, the specified command string executes before additional commands are obtained from the **/INPUT** qualifier.

If the command string contains apostrophe substitution, the apostrophe substitution is performed in the context of the parent command line interpreter (CLI); other phases of substitution are performed in the context of the subprocess CLI.

### Description

The **SPAWN** command creates a subprocess of your current process with the following attributes copied from the parent process:

- All global symbols except \$RESTART, \$SEVERITY, \$STATUS
- All local symbols defined for the current command procedure level
- Key definitions
- The current keypad state
- The current prompt string
- All process logical names and logical name tables except those explicitly marked CONFINE or those created in executive or kernel mode
- Default disk and directory
- Current **SET MESSAGE** settings
- Current process privileges
- Control and verification states

Note that some attributes, such as the process's current command tables, are *not* copied.

When the subprocess is created, the process-permanent open files and any image or procedure context are *not* copied from the parent process. The subprocess is set to command level 0 (DCL level with the current prompt).

If you do not specify the **/PROCESS** qualifier, the name of this subprocess is composed of a portion of the parent process name and a unique number. For example, if the parent process name is SKONETSKI, the subprocess names can be SKONETSKI\_123, SKONETSKI\_4732, and so on.

The LOGIN.COM file of the parent process is not executed for the subprocess because the context is copied separately, allowing quicker initialization of the subprocess. When the **/WAIT** qualifier is in effect, the parent process remains in hibernation until the subprocess terminates or returns control to the parent by way of the **ATTACH** command.

More than one process simultaneously attempts to use the same input or output stream in the following circumstances:

- When several processes share that stream and you terminate a subprocess to which you are not currently attached
- When you terminate a process that is not spawned from the process to which you are currently attached

You should use the **LOGOUT** command to terminate the subprocess and return to the parent process. You can also use the **ATTACH** command to transfer control of the terminal to another process in the subprocess tree, including the parent process. (The **SHOW PROCESS/SUBPROCESSES** command displays the processes in the subprocess tree and points to the current process.)

---

## Note

Because a tree of subprocesses can be established using the **SPAWN** command, you must be careful when terminating any process in the tree. When a process is terminated, all subprocesses below that point in the tree are terminated automatically.

---

Qualifiers used with the **SPAWN** command must directly follow the command verb. The command string parameter begins after the last qualifier and continues to the end of the command line.

## Qualifiers

**/CARRIAGE\_CONTROL**

**/NOCARRIAGE\_CONTROL**

Determines whether carriage-return and line-feed characters are prefixed to the subprocess's prompt string. By default, **SPAWN** copies the current setting of the parent process.

**/CLI=*cli-filespec***

**/NOCLI**

Specifies the name of a command language interpreter (CLI) to be used by the subprocess. The default CLI is the same as the parent process (defined in SYSUAF). If you specify the **/CLI** qualifier, the attributes of the parent process are copied to the subprocess.

The CLI you specify must be located in SYS\$SYSTEM and have the file type .EXE.

**/INPUT=*filespec***

Specifies an input file containing one or more DCL commands to be executed by the spawned subprocess. The file type defaults to .COM. The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification. Once processing of the input file is complete, the subprocess is terminated. If both a command string and the **/INPUT** qualifier are specified, the specified command string executes before additional commands are obtained from the **/INPUT** qualifier. If neither is specified, SYS\$INPUT is assumed (in which case a **SPAWN/NOWAIT** command is aborted if **Ctrl/Y** is pressed to abort something running in your parent process).

You cannot explicitly specify non-record-oriented, process-permanent files (NRO PPFs) with the **/INPUT** qualifier. The system displays an error message when it encounters such a file as the value for the **/INPUT** qualifier.

Note that when NRO PPFs are used as implicit input (that is, the **/INPUT** qualifier is not specified and SYS\$INPUT is a NRO PPF), the **SPAWN** command can succeed, as shown in the following table:

| Process Type   | SYS\$INPUT | Implicit Input |
|----------------|------------|----------------|
| Interactive    | NRO PPF    | SYS\$COMMAND   |
| Noninteractive | NRO PPF    | Null device    |
| Any            | Any other  | SYS\$INPUT     |

If SYS\$INPUT is a terminal, it cannot have an associated terminal mailbox.

**/KERNEL\_THREAD\_LIMIT=*n***

Sets the limit of the number of kernel threads that can be created in the new process. If the value specified is higher than the SYSGEN parameter MULTITHREAD, an error message is returned. Specifying the value 0 makes the process use the systemwide limit set by the MULTITHREAD parameter.

**/KEYPAD (default)****/NOKEYPAD**

Copies keypad key definitions and the current keypad state from the parent process. By default, if you have established key definitions or states with the **DEFINE/KEY** or the **SET KEY** command, these settings are copied to the subprocess. Use the **/NOKEYPAD** qualifier if you do not want the key settings to be copied.

**/LOG (default)****/NOLOG**

Displays the assigned subprocess name and any messages indicating transfer of control between processes.

**/LOGICAL\_NAMES (default)****/NOLOGICAL\_NAMES**

Copies process logical names and logical name tables to the subprocess. By default, all process logical names and logical name tables are copied to the subprocess except those explicitly marked **CONFINE** or created in executive or kernel mode.

**/NOTIFY****/NONOTIFY (default)**

Controls whether a message is broadcast to your terminal notifying you that your subprocess has completed or aborted. This qualifier should not be used unless you specify the **/NOWAIT** qualifier. The **/NOTIFY** qualifier cannot be specified when the **SPAWN** command is executed from within a noninteractive process.

Note that messages broadcast as a result of using the **/NOTIFY** qualifier are considered to be DCL messages. Therefore, if **SET BROADCAST=NODCL** is in effect, all such notification messages are suppressed.

**/OUTPUT=filespec**

Specifies the output file to which the results of the **SPAWN** operation are written. The asterisk (\*) and the percent sign (%) wildcard characters cannot be used in the file specification. (Do not specify **SYS\$COMMAND** as a file specification for the **/OUTPUT** qualifier when using the **/NOWAIT** qualifier; both parent and subprocess output will be displayed simultaneously on your terminal.)

---

**Caution**

If you include a version number in the filespec argument of the **/OUTPUT** qualifier, and that version of the specified file already exists, the existing file is replaced with the new output.

You cannot explicitly specify non-record-oriented, process-permanent files (NRO PPFs) with the **/OUTPUT** qualifier. The system displays an error message when it encounters such a file as the value for the **/OUTPUT** qualifier.

Note that when NRO PPFs are used as implicit output, the **SPAWN** command can succeed, as shown in the following table:

| Process Type | SYS\$OUTPUT | Implicit Output                                                                    |
|--------------|-------------|------------------------------------------------------------------------------------|
| Any          | NRO PPF     | Mailbox transmitting records for parent to write to its current SYS\$OUTPUT device |

| Process Type | <b>SY\$OUTPUT</b> | Implicit Output |
|--------------|-------------------|-----------------|
| Any          | Any other         | SY\$OUTPUT      |

If you omit the **/OUTPUT** qualifier, output is written to the current SY\$OUTPUT device.

**/PRIVILEGES={CURRENT|AUTHORIZED}**

Determines whether the spawned process inherits the current process' current or authorized privileges as its authorized privileges. By default, the authorized privilege mask for the subprocess is taken from the current privileges of its creator. (This corresponds to **/PRIVILEGES=CURRENT.**) If the **/PRIVILEGES=AUTHORIZED** qualifier is specified, the subprocess' authorized privileges will be taken from the caller's authorized privileges.

**/PROCESS=***subprocess-name*

Specifies the name of the subprocess to be created. If you omit the **/PROCESS** qualifier, a unique process name is assigned with the same base name as the parent process and a unique number.

The default subprocess name format is *username\_n*. If you specify a process name that already exists, an error message is displayed. If the **/LOG** qualifier has been specified, the assigned name of the subprocess is displayed.

---

## Note

Prior to OpenVMS Version 7.3-1, if no process name was supplied, the system constructed a name by appending *\_n* to the user name, where *n* was the next available nonduplicate integer for any process currently in the system. For example, the first spawned process from user SYSTEM would be called SYSTEM\_1, the second, SYSTEM\_2, and so on. The next available number was chosen as soon as a gap was found.

Starting with OpenVMS Alpha Version 7.3-1, a random number is chosen to append to the user name. In addition, starting with OpenVMS Version 8.3, the chosen number has, by default, a maximum value of 65535 instead of the former maximum value of 255. Therefore, the first processes that are spawned from user SYSTEM might be SYSTEM\_7376, SYSTEM\_9, SYSTEM\_47124, and so on.

Some applications might rely on the prior methods of assigning subprocess names. The DCL\_CTLFLAGS system parameter allows you to configure the system as necessary.

The rationale for changing from sequential to random number generation is that determining the next available open sequential number slot is very expensive in terms of performance. The mechanism attempts to create the process by incrementing names until it finds one that is unique. When several subprocesses already exist, the cost of creating the subprocess in the same OpenVMS group, the cost multiplies because process names must be unique throughout the group.

The use of random number generation results in a very high probability of finding a unique name on the first try, because it is unlikely that the same number is already in use. This greatly reduces the cost of process creation, and applications that rely on spawned subprocesses might see a dramatic performance improvement as a result of this change.

For more information, see the relevant section in the [VSI OpenVMS System Management Utilities Reference Manual, Volume 2: M-Z](https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/#d0e36924) [<https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/#d0e36924>].

---

**/PROMPT[=*string*]**

Specifies the prompt string for DCL to use in the subprocess. The default is the prompt of the parent process.

The string can consist of more than one character. All valid ASCII characters can be used in the string. The string must be enclosed in quotation marks ( " ") if it contains spaces, special characters, or lowercase characters. Otherwise, letters are automatically converted to uppercase, and leading and trailing spaces are removed.

If no string is specified, the dollar sign (\$) DCL default prompt string is used for the subprocess.

**/SYMBOLS (default)****/NOSYMBOLS**

Determines whether global and local symbols (except \$RESTART, \$SEVERITY, and \$STATUS) are passed to the subprocess. \$RESTART, \$SEVERITY, and \$STATUS symbols are *never* passed to the subprocess.

**/TABLE=*command-table***

Specifies the name of an alternate command table to be used by the subprocess.

**/TRUSTED****/NOTRUSTED**

Indicates that the **SPAWN** command input originates in a trusted command procedure. **SPAWN** commands are not allowed in CAPTIVE accounts. The **/TRUSTED** qualifier provides a way for properly written captive command procedures to perform **SPAWN** operations when the command input originates in the captive command procedure where it can be trusted. For more information about trusted command procedures, see the [VSI OpenVMS Guide to System Security \[https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/\]](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/).

**/WAIT (default)****/NOWAIT**

Requires that you wait for the subprocess to terminate before you enter another DCL command. The **/NOWAIT** qualifier allows you to enter new commands while the subprocess is running. (Use the **/OUTPUT** qualifier with the **/NOWAIT** qualifier to avoid displaying both parent and subprocess output on the terminal simultaneously.)

Note that specifying the **/NOWAIT** qualifier causes both input and output to be shared with the parent process. If the input device is a terminal, control characters, such as **Ctrl/T** or **Ctrl/Y**, also affect all subprocesses sharing the input device. The **Ctrl/Y** control character, for example, interrupts all such subprocesses.

This problem may be avoided by specifying **/INPUT=NL:**

## Example

```
$ RUN MYPROG
.
.
.
```

```
$ Ctrl/Y
$ SPAWN MAIL
%DCL-S-SPAWNED, process SKONETSKI_272 spawned
%DCL-S-ATTACHED, terminal now attached to process SKONETSKI_272
MAIL> READ
.
.
.
MAIL> EXIT
%DCL-S-RETURNED, control returned to process SKONETSKI
$ CONTINUE
```

The **SPAWN** command in this example allows you to enter the OpenVMS Mail utility (**MAIL**) without terminating the currently running program. After you exit from Mail, control is returned to the parent process.

## START/CPU

**START/CPU** — Starts the specified secondary processor or processors (and any associated vector processors). The **/CPU** qualifier is required. **Applies only to OpenVMS multiprocessing systems. Requires CMKRNL(change mode to kernel) privilege.**

### Format

**START/CPU** [*cpu-id* [, ... ]]

### Parameter

*cpu-id* [, ... ]

Specifies a decimal value representing the identity of a processor in an OpenVMS multiprocessing system. On an Alpha 7000 system, the CPU ID is the backplane slot number of the processor. If you do not specify a CPU ID and do not include the **/ALL** qualifier, the **START/CPU** command selects a single available processor to join the multiprocessing system.

## Description

The **START/CPU** command starts a secondary processor in a OpenVMS multiprocessing system.

You can issue a **START/CPU** command only for processors in the STOPPED or TIMEOUT state, as represented by the **SHOW CPU** command; otherwise, the **START/CPU** command has no effect.

## Qualifiers

**/ALL**

Selects all remaining processors in the system's available set to join the multiprocessing system.

**/DEFAULT\_CAPABILITIES**

Eliminates all previous capability (user and system) modifications for the specified CPU and reinitializes them with the values in the global initialization variable `SCH$GL_DEFAULT_CPU_CAP`.

Normally, user capabilities survive CPU shutdowns and restarts (not reboots), making the downtime as transparent to the user as possible. The CPU user capability bits are only initialized from `SCH$GL_DEFAULT_CPU_CAP` at the first boot of the CPU. (The system capability bits, however, are reinitialized to their defaults taken from `SCH$GL_DEFAULT_CPU_CAP`.)

However, there may be times when the CPU needs to be returned to a known, consistent state. The `/DEFAULT_CAPABILITIES` qualifier mimics the behavior of the initial bootstrap of the CPU.

### **/POWER[=ON] (Alpha/Integrity servers only)**

Powers on the CPU prior to bringing the CPU into the active set.

Supported only on AlphaServer GS series systems.

## **Examples**

1. `$ START/CPU`

The **START/CPU** command in this example selects a single inactive processor from the set of those processors that are currently available but inactive. When it completes its initialization, the selected processor becomes part of the system's active set and is capable of scheduling and executing processes.

2. `$ START/CPU 4,7`

The **START/CPU** command in this example selects the processors with CPU IDs 4 and 7, if they are currently available and inactive. When they complete initialization, these processors become part of the system's active set and are capable of scheduling and executing processes.

3. `$ START/CPU/ALL`

The **START/CPU/ALL** command in this example selects all remaining inactive and available processors. When they complete initialization, these processors become part of the system's active set and are capable of scheduling and executing processes.

## **START/NETWORK**

**START/NETWORK** — Starts or restarts the specified network service on the local node. The `/NETWORK` qualifier is required.

### **Format**

**START/NETWORK** *network-service*

### **Parameter**

*network-service*

Specifies the name of the network service to be started or restarted.

### **Description**

The **START/NETWORK** command causes a network service to begin executing on the local node.

Use the **STOP/NETWORK** command to pause the network.

## Example

```
$ START/NETWORK DECnet
```

This command starts the DECnet network service.

## START/QUEUE

**START/QUEUE** — Starts or restarts the specified queue after it has been initialized. You also can use this command to change the options of the specified queue. The **/QUEUE** qualifier is required. **Requires manage (M) access to the queue.**

## Format

```
START/QUEUE queue-name [ : ]
```

## Parameter

*queue-name* [ : ]

Specifies the name of the queue to be started or restarted.

## Description

The **START/QUEUE** command restarts a queue that has been stopped or paused. You must create the queue with the **INITIALIZE/QUEUE** command before you can use the **START/QUEUE** command. To create and start the queue at the same time, use the **INITIALIZE/QUEUE/START** command.

If the specified queue is an autostart queue, the **START/QUEUE** command activates the queue for autostart. The queue begins processing jobs when autostart is enabled with the **ENABLE AUTOSTART/QUEUES** command for any node on which the queue can run.

You can specify with the **START/QUEUE** command most qualifiers that can be used with the **INITIALIZE/QUEUE** command. The defaults for the **START/QUEUE** qualifiers depend on the qualifiers specified when the queue was initialized. For example, the default for **/JOB\_LIMIT** with **INITIALIZE/QUEUE** is 1. However, if the queue you are altering was initialized with a job limit of 3, and if you do not specify the **/JOB\_LIMIT** qualifier with the **START/QUEUE** command, the job limit remains at 3 for that queue.

Values or options specified with qualifiers on the **START/QUEUE** command override the values or options of those same qualifiers that were specified when the queue was initialized.

If the specified queue is running when you enter the **START/QUEUE** command, the system returns an error message. To change the options of a running queue, use the **SET QUEUE** command. To change queue options that cannot be altered with the **SET QUEUE** command, use the following procedure:

1. Stop the queue with the **STOP/QUEUE/NEXT** command.
2. Restart the queue with the **START/QUEUE** or **INITIALIZE/QUEUE/START** command, specifying the appropriate qualifiers for the options you desire.

The **/TOP\_OF\_FILE**, **/BACKWARD**, **/FORWARD**, **/SEARCH**, **/ALIGN**, and **/NEXT** qualifiers are effective only when restarting an output execution queue from a paused state. They do not apply to queues that are stopped or to batch queues. When you specify more than one of the first five of these qualifiers, the print symbiont processes them in the following order:

1. **/TOP\_OF\_FILE**
2. **/BACKWARD**
3. **/FORWARD**
4. **/SEARCH**
5. **/ALIGN**

## Qualifiers

**/ALIGN[=(*option*[,...])]**

Prints alignment pages to aid in aligning printer forms. Use this qualifier only when restarting an output execution queue from a paused state.

After the alignment is complete, the queue enters a paused state until you restart it by reentering the **START/QUEUE** command. Printing resumes from the point where alignment data started; that is, the task is backspaced over the pages printed for alignment.

Possible options are as follows:

| Option      | Description                                                                                                                                                                                                                                                                                |
|-------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>MASK</b> | Specifies that input data is masked by replacing alphabetic characters with x's and numbers with 9s; nonalphanumeric characters are not masked. Mask characters allow you to prevent the printing of sensitive information. If you omit the <b>MASK</b> option, data is printed unaltered. |
| <i>n</i>    | Specifies the number of alignment pages to print. The value of <i>n</i> can be from 1 to 20. By default, one page of alignment data is printed.                                                                                                                                            |

**/AUTOSTART\_ON=(*node*::[*device*][,...])**

Designates the queue as an autostart execution queue and specifies the node, or node and device, on which the queue can be located. Both *node* and *device* must be specified for output queues. For batch queues, only *node* is applicable.

In an OpenVMS Cluster, you can specify more than one node (or node and device) on which a queue can run, in the preferred order in which nodes should claim the queue. This allows the queue to fail over to another node if the node on which the queue is running leaves the cluster.

For autostart queues, the **START/QUEUE** command activates the queue for autostart. The queue will begin processing jobs when the **ENABLE AUTOSTART/QUEUES** command is entered for a node on which the queue can run.

This qualifier cannot be used with the **/ON** or **/GENERIC** qualifier; however, you can specify the **/AUTOSTART\_ON** qualifier for a queue previously created or started with the **/ON** qualifier. Doing so overrides the **/ON** option and makes the queue an autostart queue.

For more information about autostart queues, see the chapter about managing queues in the [VSI OpenVMS System Manager's Manual, Volume 1: Essentials](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#_6017QUEUE_MGR) [[https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#\\_6017QUEUE\\_MGR](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#_6017QUEUE_MGR)].

### **/BACKWARD=*n***

Restarts a print queue *n* pages before the current page; *n* defaults to 1. If you omit the page value, printing resumes at the top of the current page. Use this qualifier only when restarting an output execution queue from a paused state.

---

### **Note**

Using the **START/QUEUE/BACKWARD=*n*** command to restart a print job that uses Fortran carriage control and that was printed with the **/NOFEED** qualifier can have unexpected results, in particular:

- The page positioning in the restarted job may not be correct: the output may not begin at the top of the page specified by *n*.
  - The output from the print job may be preceded by extra meaningless information.
- 

### **/BASE\_PRIORITY=*n***

Specifies the base process priority at which jobs are initiated from a batch execution queue. By default, if you omit the qualifier, jobs are initiated at the same priority as the base priority established by DEFPRI at system generation (usually 4). The base priority specifier can be any decimal value from 0 to 15.

### **/BLOCK\_LIMIT=(*lowlim*,*uplim*)**

#### **/NOBLOCK\_LIMIT**

Limits the size of print jobs that can be processed on an output execution queue. This qualifier allows you to reserve certain printers for certain size jobs. You must specify at least one of the parameters.

The *lowlim* parameter is a decimal number referring to the minimum number of blocks that are accepted by the queue for a print job. If a print job is submitted that contains fewer blocks than the *lowlim* value, the job remains pending until the block limit for the queue is changed. After the block limit for the queue is decreased sufficiently, the job is processed.

The *uplim* parameter is a decimal number referring to the maximum number of blocks that are accepted by the queue for a print job. If a print job is submitted that exceeds this value, the job remains pending until the block limit for the queue is changed. After the block limit for the queue is increased sufficiently, the job is processed.

If you specify only an upper limit for jobs, you can omit the parentheses. For example, **/BLOCK\_LIMIT=1000** means that only jobs with 1000 blocks or less are processed in the queue. To specify only a lower job limit, you must use a null string (") to indicate the upper specifier. For example, **/BLOCK\_LIMIT=(500,")** means any job with 500 or more blocks is processed in the queue. You can specify both a lower and upper limit. For example, **/BLOCK\_LIMIT=(200,2000)** means that jobs with less than 200 blocks or more than 2000 blocks are not processed in the queue.

The **/NOBLOCK\_LIMIT** qualifier cancels the previous setting established by the **/BLOCK\_LIMIT** qualifier for the queue.

**/CHARACTERISTICS**=(*characteristic*[,...])  
**/NOCHARACTERISTICS**

Specifies one or more characteristics for processing jobs on an execution queue. If a queue does not have all the characteristics that have been specified for a job, the job remains pending. If you specify only one characteristic, you can omit the parentheses. Each time you specify the **/CHARACTERISTICS** qualifier, all previously set characteristics are canceled. Only the characteristics specified with the qualifier are established for the queue.

Queue characteristics are installation specific. The characteristic parameter can be either a value from 0 to 127 or a characteristic name that has been defined by the **DEFINE/CHARACTERISTIC** command.

The **/NOCHARACTERISTICS** qualifier cancels any settings previously established by the **/CHARACTERISTICS** qualifier for the queue.

**/CLOSE**

Prevents jobs from being entered in the queue through **PRINT** or **SUBMIT** commands or as a result of requeue operations. To allow jobs to be entered, use the **/OPEN** qualifier. Whether a queue accepts or rejects new job entries is independent of the queue's state (such as paused, stopped, or stalled). When a queue is marked closed, jobs executing continue to execute. Jobs already pending in the queue continue to be candidates for execution.

**/CPUDEFAULT**=*time*

Defines the default CPU time limit for jobs in this batch execution queue. You can specify time as delta time, 0, INFINITE, or NONE. You can specify up to 497 days of delta time.

If the queue does not have a specified CPUMAXIMUM time limit and the value established in the user authorization file (UAF) has a specified CPU time limit of NONE, either the value 0 or the keyword INFINITE allows unlimited CPU time. If you specify NONE, the CPU time value defaults to the value specified either in the UAF or by the **SUBMIT** command (if included). CPU time values must be greater than or equal to the number specified by the system parameter PQL\_MCPULM.

For information on specifying delta times, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic Date. For more information on specifying CPU time limits, see the "CPU Time Limit Specifications and Actions" table for the **INITIALIZE/QUEUE** command in the [VSI OpenVMS DCL Dictionary: A-M](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_119) [https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\_119].

**/CPUMAXIMUM**=*time*

Defines the default CPU time limit for all jobs in this batch execution queue. You can specify time as delta time, 0, INFINITE, or NONE. You can specify up to 497 days of delta time.

If the queue does not have a specified CPUMAXIMUM time limit and the value established in the UAF has a specified CPU time limit of NONE, either the value 0 or the keyword INFINITE allows unlimited CPU time. If you specify NONE, the CPU time value defaults to the value specified either in the UAF or by the **SUBMIT** command (if included). CPU time values must be greater than or equal to the number specified by the system parameter PQL\_MCPULM. The time cannot exceed the CPU time limit set by the **/CPUMAXIMUM** qualifier.

For information on specifying delta times, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT]

or the online help topic *Date*. For more information on specifying CPU time limits, see the "CPU Time Limit Specifications and Actions" table for the **INITIALIZE/QUEUE** command in the *VSI OpenVMS DCL Dictionary: A-M* [[https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\\_119](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_119)].

**/DEFAULT=(option[,...])**  
**/NODEFAULT**

Establishes defaults for certain options of the **PRINT** command. Defaults are specified by the list of options. If you specify only one option, you can omit the parentheses. After you set an option for the queue with the **/DEFAULT** qualifier, you do not have to specify that option in your **PRINT** commands. If you do specify these options in your **PRINT** command, the values specified with the **PRINT** command override the values established for the queue with the **/DEFAULT** qualifier.

You cannot use the **/DEFAULT** qualifier with the **/GENERIC** qualifier.

Possible options are as follows:

| Option                         | Description                                                                                                                                                                                                                                                                                                                                          |
|--------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| [NO]BURST[= <i>keyword</i> ]   | Controls whether two file flag pages with a burst bar between them are printed preceding output. If you specify the value <b>ALL</b> (default), these flag pages are printed before each file in the job. If you specify the value <b>ONE</b> , these flag pages are printed once before the first file in the job.                                  |
| [NO]FEED                       | Specifies whether a form feed is inserted automatically at the end of a page.                                                                                                                                                                                                                                                                        |
| [NO]FLAG[= <i>keyword</i> ]    | Controls whether a file flag page is printed preceding output. If you specify the value <b>ALL</b> (default), a flag page is printed before each file in the job. If you specify the value <b>ONE</b> , a flag page is printed once before the first file in the job.                                                                                |
| FORM= <i>type</i>              | Specifies the default form for an output execution queue. If a job is submitted without an explicit form definition, this form is used to process the job. If no form type is explicitly specified with the <b>FORM</b> keyword, the system assigns the form "DEFAULT" to the queue. See also the description of the <b>/FORM_MOUNTED</b> qualifier. |
| [NO]TRAILER[= <i>keyword</i> ] | Controls whether a file trailer page is printed following output. If you specify the value <b>ALL</b> (default), a trailer page is printed after each file in the job. If you specify the value <b>ONE</b> , a trailer page is printed once after the last file in the job.                                                                          |

When you specify the **BURST** option for a file, the **[NO]FLAG** option does not add or subtract a flag page from the two flag pages that are printed preceding the file. For information on establishing mandatory queue options, see the description of the **/SEPARATE** qualifier. For more information on specifying default queue options, see the relevant section in the *VSI OpenVMS System Manager's Manual, Volume 1: Essentials* [[https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#\\_6017QUEUE\\_MGR](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#_6017QUEUE_MGR)].

**/DESCRIPTION=*string***  
**/NODESCRIPTION**

Specifies a string of up to 255 characters that is used to provide operator-supplied information about the queue.

Enclose strings containing lowercase letters, blanks, or other non alphanumeric characters (including spaces) in quotation marks (" ").

The **/NODESCRIPTION** qualifier removes any descriptive text that may be associated with the queue.

**/DISABLE\_SWAPPING**  
**/NODISABLE\_SWAPPING**

Controls whether batch jobs executed from a queue can be swapped in and out of memory.

**/ENABLE\_GENERIC**  
**/NOENABLE\_GENERIC**

Specifies whether files queued to a generic queue that does not specify explicit queue names with the **/GENERIC** qualifier can be placed in this execution queue for processing. For more information, see the description of the [/GENERIC](#) qualifier.

**/FORM\_MOUNTED=type**

Specifies the mounted form for an output execution queue.

If no form type is explicitly specified, the system assigns the form "DEFAULT" to the queue.

If the stock of the mounted form does not match the stock of the default form, as indicated by the **/DEFAULT=FORM** qualifier, all jobs submitted to this queue without an explicit form definition enter a pending state and remain pending until the stock of the mounted form of the queue is identical to the stock of the form associated with the job.

If a job is submitted with an explicit form and the stock of the explicit form is not identical to the stock of the mounted form, the job enters a pending state and remains pending until the stock of the mounted form of the queue is identical to the stock of the form associated with the job.

To specify the form type, use either a numeric value or a form name that has been defined by the **DEFINE/FORM** command. Form types are installation-specific. You cannot use the **/FORM\_MOUNTED** qualifier with the **/GENERIC** qualifier.

**/FORWARD=n**

Advances the specified number of pages before resuming printing the current file in the current job; the default is 1. If you omit the page value, printing resumes at the top of the next page. Use this qualifier only when restarting an output execution queue from a paused state.

**/GENERIC[=(queue-name[,...])]**  
**/NOGENERIC**

Specifies a generic queue. Also specifies that jobs placed in this queue can be moved for processing to compatible execution queues. The **/GENERIC** qualifier optionally accepts a list of target execution queues that have been previously defined. For a generic batch queue, these target queues must be batch execution queues. For a generic output queue, these target queues must be output execution queues, but can be of any type (printer, server, or terminal). For example, a generic printer queue can feed a mixture of printer and terminal execution queues.

Use the **/GENERIC** qualifier to change the list of target nodes for a generic queue. The queue must have been initialized as a generic queue with the **INITIALIZE/QUEUE/GENERIC** command.

If you do not specify any target execution queues with the **/GENERIC** qualifier, jobs can be moved to any execution queue that (1) is initialized with the **/ENABLE\_GENERIC** qualifier, and (2) is the same type (batch or output) as the generic queue.

To define the queue as a generic batch or output queue, you use the **/GENERIC** qualifier with either the **/BATCH** or the **/DEVICE** qualifier. If you specify neither the **/BATCH** nor the **/DEVICE** qualifier on creation of a generic queue, by default the queue becomes a generic printer queue.

### **/JOB\_LIMIT=*n***

Specifies the number of batch jobs that can be executed concurrently from the queue. Specify a number in the range 0 to 255.

### **/LIBRARY=*filename*** **/NOLIBRARY**

Specifies the file name for the device control library. When you initialize an output execution queue, you can use the **/LIBRARY** qualifier to specify an alternate device control library. You can use only a file name as the parameter of the **/LIBRARY** qualifier. The system always assumes that the file is located in SYS\$LIBRARY and that the file type is .TLB.

### **/NEXT**

Aborts the currently suspended print job and begins processing of the first pending job in the queue. Use this qualifier only when restarting an output execution queue from a paused state.

### **/NO\_INITIAL\_FF** **/NONO\_INITIAL\_FF (default)**

Specifies whether a form feed should be sent to a printer device when a queue starts. To suppress the initial form feed, use the **/NO\_INITIAL\_FF** qualifier.

The **/NONO\_INITIAL\_FF** qualifier sends a form feed to the output device to ensure that the paper is at the top of a page before printing begins.

### **/ON=[*node::*]*device*[:]** (printer, terminal, server queue) **/ON=*node::*** (batch queue)

Specifies the node or device, or both, on which this execution queue is located. For batch execution queues, you can specify only the node name. For output execution queues, you can include both the node name and the device name.

The node name is used only in VAXcluster systems; it must match the node name specified by the system parameter SCSNODE for the VAX computer on which the queue executes.

You cannot use the **/ON** qualifier with the **/AUTOSTART\_ON** or **/GENERIC** qualifier; however, you can specify the **/ON** qualifier for a queue previously created or started with the **/AUTOSTART\_ON** qualifier. Doing so overrides the **/AUTOSTART\_ON** qualifier and makes the queue a nonautostart queue.

### **/OPEN**

Allows jobs to be entered in the queue through **PRINT** or **SUBMIT** commands or as the result of requeue operations. To prevent jobs from being entered in the queue, use the **/CLOSE** qualifier.

Whether a queue accepts or rejects new job entries is independent of the queue's state (such as paused, stopped, or stalled).

**/OWNER\_UIC=*uic***

Requires manage (M) access to the queue.

Enables you to change the user identification code (UIC) of the queue. Specify the UIC by using standard format as described in the relevant section in the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC_SECTION) [[https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC\\_SECTION](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC_SECTION)].

**/PROCESSOR=*filename*****/NOPROCESSOR**

Requires OPER (operator) privilege to change the file name from the one with which the queue was initialized.

Allows you to specify your own print symbiont for an output execution queue. You can use any valid file name as a parameter of the **/PROCESSOR** qualifier. The system supplies the device and directory name SYS\$SYSTEM and the file type .EXE. If you use this qualifier for an output queue, it specifies that the symbiont image to be executed is SYS\$SYSTEM:*filename*.EXE.

By default, SYS\$SYSTEM:PRTSMB.EXE is the symbiont image associated with an output execution queue.

The **/NOPROCESSOR** qualifier cancels any previous setting established by the **/PROCESSOR** qualifier, and causes SYS\$SYSTEM:PRTSMB.EXE to be used.

**/PROTECTION= (*ownership[:access]*,...)**

Requires OPER (operator) privilege, or control (C) and execute (E) access to the queue.

Specifies the protection of the queue.

- Specify the *ownership* parameter as system (S), owner (O), group (G), or world (W).
- Specify the *access* parameter as read (R), submit (S), manage (M), or delete (D). A null access specification means no access.

If you include only one protection code, you can omit the parentheses.

For more information on specifying protection codes, see the relevant section in the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#PROTECT_CODE_DETAILS) [[https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#PROTECT\\_CODE\\_DETAILS](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#PROTECT_CODE_DETAILS)]. For more information on controlling queue operations through UIC-based protection, see the relevant section in the [VSI OpenVMS System Manager's Manual, Volume 1: Essentials](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#SECURITY) [<https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#SECURITY>].

**/RAD=*n***

Specifies the RAD number on which to run batch jobs assigned to the queue. The RAD value is validated as a positive integer between 0 and the value returned by the \$GETSYI item code, SYI\$\_RAD\_MAX\_RADS.

RAD is supported on AlphaServer GS series systems and starting from OpenVMS Version 8.4, support is extended to NUMA capable Integrity servers.

**/RECORD\_BLOCKING****/NORECORD\_BLOCKING**

Determines whether the symbiont can concatenate (or block together) output records for transmission to the output device. If you specify the **/NORECORD\_BLOCKING** qualifier, the symbiont sends each formatted record in a separate I/O request to the output device. For the standard OpenVMS print symbiont, record blocking can have a significant performance advantage over single-record mode.

**/RETAIN[=*option*]****/NORETAIN**

Holds jobs in the queue in a retained status after they have executed. The **/NORETAIN** qualifier enables you to reset the queue to the default. Possible options are as follows:

| Option | Description                                         |
|--------|-----------------------------------------------------|
| ALL    | Holds all jobs in the queue after execution.        |
| ERROR  | Holds in the queue only jobs that fail to complete. |

A user can request a job retention option for a job by specifying the **/RETAIN** qualifier with the **PRINT**, **SUBMIT**, or **SET ENTRY** command. However, the job retention option you specify for a queue overrides any job retention option requested by a user for a job in that queue.

**/SCHEDULE=[NO]SIZE**

Specifies whether pending jobs in an output queue are scheduled for printing based on the size of the job. When the **/SCHEDULE=SIZE** qualifier is in effect, shorter jobs are printed before longer ones. When the **/SCHEDULE=NOSIZE** qualifier is in effect, jobs are printed in the order they were submitted, regardless of size.

If you enter this command while there are pending jobs in any queue, its effect on future jobs is unpredictable.

**/SEARCH="search-string"**

Specifies that printing is to resume at the page containing the specified string. The search for the string moves forward, beginning on the page following the current page. During the search, consecutive tabs and spaces are treated as a single space, and character case is ignored. The string can be from 1 to 63 characters and must be enclosed in quotation marks (" "). Use this qualifier only when restarting an output execution queue from a paused state.

**/SEPARATE=(*option*[,...])****/NOSEPARATE**

Specifies the mandatory queue options, or job separation options, for an output execution queue. Job separation options cannot be overridden by the **PRINT** command.

You cannot use the **/SEPARATE** qualifier with the **/GENERIC** qualifier.

The job separation options are as follows:

| Option    | Description                                                                                                  |
|-----------|--------------------------------------------------------------------------------------------------------------|
| [NO]BURST | Specifies whether two job flag pages with a burst bar between them are printed at the beginning of each job. |

| Option                            | Description                                                                                                                                                                                                                                                                                                                                                                                                                         |
|-----------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| [NO]FLAG                          | Specifies whether a job flag page is printed at the beginning of each job.                                                                                                                                                                                                                                                                                                                                                          |
| [NO]TRAILER                       | Specifies whether a job trailer page is printed at the end of each job.                                                                                                                                                                                                                                                                                                                                                             |
| [NO]RESET=( <i>module</i> [,...]) | Specifies one or more device control library modules that contain the job reset sequence for the queue. The specified modules from the queue's device control library (by default SYS\$LIBRARY:SYSDEVCTL) are used to reset the device each time a job reset occurs. The RESET sequence occurs after any file trailer and before any job trailer. Thus, all job separation pages are printed when the device is in its RESET state. |

When you specify **/SEPARATE=BURST**, the [NO]FLAG separation option does not add or subtract a flag page from the two flag pages that are printed preceding the job.

For information on establishing queue options that can be overridden, see the description of the [/DEFAULT](#) qualifier.

For more information on specifying mandatory queue options, see the relevant section in the [VSI OpenVMS System Manager's Manual, Volume 1: Essentials](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#_6017QUEUE_MGR) [https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#\_6017QUEUE\_MGR].

## **/TOP\_OF\_FILE**

Resumes printing at the beginning of the file that was current when the output execution queue paused. Use this qualifier only when restarting an output execution queue from a paused state.

## **/WSDEFAULT=*n***

Defines for a batch job a working set default, the default number of physical pages that the job can use. The value set by this qualifier overrides the value defined in the user authorization file (UAF) of any user submitting a job to the queue.

You also can specify this qualifier for an output execution queue. Used in this context, the **/WSDEFAULT** qualifier establishes the working set default of the symbiont process for an execution queue when the symbiont process is created.

Specify the value of *n* as a number of 512-byte pagelets on Alpha. Note that the operating systems rounds up this value to the nearest CPU-specific page so that the actual amount of physical memory allowed may be larger than the specified amount on Alpha.

If you specify the value 0 or NONE, the working set default value defaults to the value specified in the UAF or by the **SUBMIT** command (if included).

For more information about the way a working set default affects batch jobs, see *Table 9, "Working Set Default, Extent, and Quota Decision"*.

## **/WSEXTENT=*n***

Defines for the batch job a working set extent, the maximum amount of physical memory that the job can use. The job uses the maximum amount of physical memory only when the system has excess free pages. The value set by this qualifier overrides the value defined in the user authorization file (UAF) of any user submitting a job to the queue.

You also can specify this qualifier for an output execution queue. Used in this context, the **/WSEXTENT** qualifier establishes the working set extent of the symbiont process for an output execution queue when the symbiont process is created.

Specify the value of *n* as a number of 512-byte pagelets on Alpha. Note that the operating system rounds up this value to the nearest CPU-specific page so that the actual amount of physical memory allowed may be larger than the specified amount on Alpha.

If you specify the value 0 or NONE, the working set extent value defaults to the value specified in the UAF or by the **SUBMIT** command (if included).

For more information about the way a working set extent affects batch jobs, see *Table 9, "Working Set Default, Extent, and Quota Decision"*.

### **/WSQUOTA=*n***

Defines for a batch job a working set quota, the amount of physical memory that is guaranteed to the job. The value set by this qualifier overrides the value defined in the user authorization file (UAF) of any user submitting a job to the queue.

You also can specify this qualifier for an output execution queue. Used in this context, the **/WSQUOTA** qualifier establishes the working set quota of the symbiont process for an output execution queue when the symbiont process is created.

Specify the value of *n* as a number of 512-byte pagelets on Alpha. Note that the operating system rounds up this value to the nearest CPU-specific page so that the actual amount of physical memory allowed may be larger than the specified amount on Alpha.

If you specify the value 0 or NONE, the working set quota value defaults to the value specified in the UAF or by the **SUBMIT** command (if included).

Working set default, working set quota, and working set extent values are included in each user record in the system UAF. You can specify working set values for individual jobs or for all jobs in a given queue. The decision table (*Table 9, "Working Set Default, Extent, and Quota Decision"*) shows the action taken for different combinations of specifications that involve working set size and working set quota values.

**Table 9. Working Set Default, Extent, and Quota Decision**

| Value Specified by the SUBMIT Command? | Value Specified for the Queue? | Action Taken                                             |
|----------------------------------------|--------------------------------|----------------------------------------------------------|
| No                                     | No                             | Use the UAF value.                                       |
| No                                     | Yes                            | Use value for the queue.                                 |
| Yes                                    | Yes                            | Use smaller of the two values.                           |
| Yes                                    | No                             | Compare specified value with UAF value; use the smaller. |

## Examples

1. \$ STOP/QUEUE LPA0  
\$ START/QUEUE/TOP\_OF\_FILE LPA0

The **STOP/QUEUE** command in this example suspends the job that is currently executing on the printer queue LPA0 and places that queue in the paused state. The **START/QUEUE** command releases the queue from the paused state. The **/TOP\_OF\_FILE** qualifier causes the job that was suspended to resume printing at the beginning of the file rather than at where it was interrupted.

```
2. $ INITIALIZE/QUEUE LPA0
    .
    .
    .
    $ START/QUEUE/DEFAULT=FLAG LPA0
```

The **INITIALIZE/QUEUE** command in this example initializes the queue named LPA0. Later, the **START/QUEUE** command starts the queue. The **/DEFAULT** qualifier requests that a flag page precede each file in each job.

```
3. $ START/QUEUE/DEFAULT=FORM=LN01_PORTRAIT LN01_PRINT
```

The **START/QUEUE** command in this example restarts the LN01\_PRINT queue with the default form LN01\_PORTRAIT.

```
4. $ INITIALIZE/QUEUE/START/GENERIC=(A,B) MYQUEUE
    .
    . [new printers X and Y are brought in at a later date]
    .
    $ STOP/QUEUE/NEXT MYQUEUE
    $ START/QUEUE/GENERIC=(X,Y) MYQUEUE
```

This example changes the list of target nodes for a generic queue. Note that the queue was previously initialized as a generic queue.

```
5. $ START/QUEUE/RAD=1 BATCHQ1

    $ SHOW QUEUE/FULL BATCHQ1
    Batch queue BATCHQ1, idle, on QUEBID::
      /BASE_PRIORITY=4 /JOB_LIMIT=3 /OWNER=[SYSTEM]
      /PROTECTION=(S:M,O:D,G:R,W:S) /RAD=1
```

This example modifies BATCHQ1 to run all assigned jobs on RAD 1 of QUEBID, and readies the queue to accept jobs for processing.

## START/QUEUE/MANAGER

**START/QUEUE/MANAGER** — Starts the clusterwide queue manager for the queuing system and opens that queue manager's queue database files. The **/QUEUE** qualifier is optional, but the **/MANAGER** qualifier is required. By default, the command affects the default queue manager, SYSS\$QUEUE\_MANAGER. Specify the **/NAME\_OF\_MANAGER** qualifier to start a queue manager other than the default. For more information, see the chapter on the queue manager in the [VSI OpenVMS System Manager's Manual, Volume 1: Essentials](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#_6017QUEUE_MGR) [https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#\_6017QUEUE\_MGR]. Requires **OPER** (operator) and **SYSNAM** (system logical name) privileges.

## Format

**START/QUEUE/MANAGER** [*dirspec*]

## Parameter

### *dirspec*

Specifies the directory location to contain the system queue and journal files of the queue database. The queue file has a file type of QMAN\$QUEUES and contains queue definitions. The journal file has a file type of QMAN\$JOURNAL and contains job and other information that lets the queue manager to return to its last known state should a system be stopped unexpectedly. These files must reside in the same directory.

The default location of the queue and journal files is SYS\$COMMON:[SYSEXE]. The optional *dirspec* parameter is used only for specifying an alternate location for the queue and journal files. The specification must include at least the device and directory name. The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the directory specification.

The directory you specify must be available to all nodes that can run the queue manager. If the directory specification is a concealed logical name, it must be identically defined on all nodes in the cluster.

The location of the queue and journal files is stored in the master file of the queue database. You do not have to respecify the directory location with subsequent **START/QUEUE/MANAGER** commands.

For information about changing the location of any of the queue database files, see the chapter on the queue manager in the *VSI OpenVMS System Manager's Manual, Volume 1: Essentials* [[https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#\\_6017QUEUE\\_MGR](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#_6017QUEUE_MGR)].

## Description

The **START/QUEUE/MANAGER** command has the following uses:

- Enter the command **START/QUEUE/MANAGER/NEW\_VERSION** to create the queue database and initially start a queue manager. See the description of the [/NEW\\_VERSION](#) qualifier for more information. Once the queue manager has been started, it will remain running unless it is explicitly stopped with the **STOP/QUEUE/MANAGER/CLUSTER** command.
- If the **STOP/QUEUE/MANAGER/CLUSTER** command has been executed, enter the **START/QUEUE/MANAGER** command to restart a queue manager.
- In an OpenVMS Cluster, enter the **START/QUEUE/MANAGER** command with the [/ON](#) qualifier to modify the list of preferred nodes on which a queue manager can run. See the description of the [/ON](#) qualifier for more information.
- In an OpenVMS Cluster, enter the **START/QUEUE/MANAGER** command to ensure that a queue manager process is executing on the most preferred, available node. If the queue manager is not running on the most preferred, available node, the queue manager will be moved to that node without interruption of service. If you are using the default node list (\*), the queue manager will not move. For more information, see the description of the [/ON](#) qualifier.

If the queue manager is in a location other than the default, and in OpenVMS Cluster environments with multiple system disks, you must define the logical name QMAN\$MASTER. For instructions, see the chapter about the queue manager and queue database in the *VSI OpenVMS System Manager's Manual, Volume 1: Essentials* [[https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#\\_6017QUEUE\\_MGR](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#_6017QUEUE_MGR)].

If a queue manager does not start when you enter the **START/QUEUE/MANAGER** command, you will receive the following message:

```
%JBC-E-QMANNOTSTARTED, queue manager could not be started
```

If you see this message, search the operator log file `SYSS$MANAGER:OPERATOR.LOG` (or look on the operator console) for messages from the facilities `QUEUE_MANAGE` and `JOB_CONTROL` for information about the problem, as follows:

```
$ SEARCH SYSS$MANAGER:OPERATOR.LOG /WINDOW=5 QUEUE_MANAGE, JOB_CONTROL
```

## Qualifies

### **/ADD**

Creates an additional queue manager in the existing queue database. If the named queue manager already exists, the request will be rejected.

### **/NAME\_OF\_MANAGER=*name***

Creates a non-default queue manager. The required name value may be up to 31 characters long and may be a logical. The name will serve as the identifier for the queue manager process and the portion of the database that it is managing.

### **/NEW\_VERSION**

### **/NONEW\_VERSION (default)**

Specifies that a new (empty) version of the queue database is to be created. This qualifier is required when initially creating and starting the queuing system.

If you specify this qualifier and a queue database already exists, the new master and queue files of the queue database supersede existing versions of those files; however, the journal file of the existing queue database is deleted. Jobs and other information are lost.

### **/ON=(*node*[,...])**

In an OpenVMS Cluster, specifies the nodes on which a clusterwide queue manager can run. The default value for the node list is the asterisk (\*) wildcard character, meaning that all nodes in the cluster are eligible to run the queue manager. If the node on which the queue manager is running leaves the cluster, the queue manager can automatically fail over to any available node in the cluster. However, to specify a preferred order in which the nodes should claim the queue manager, or to limit the nodes which can run it, you must specify the **/ON** qualifier.

The node list you specify is stored in the queue database. Anytime the **START/QUEUE/MANAGER** command is entered and neither the **/NEW\_VERSION** nor **/ON** qualifier is specified, the **/ON** list stored in the queue database remains unchanged.

For highest availability, specify the asterisk (\*) wildcard character as the last node in the node list to indicate that any remaining unlisted node can claim the queue manager, with no preferred order. If you do not specify the asterisk (\*) wildcard character last in the node list, the queue manager can only fail over if one of the nodes in the list is available; however, if you want to exclude certain nodes from being eligible to run the queue manager, you cannot use the asterisk (\*) wildcard character. You cannot specify the asterisk (\*) wildcard character as part of a node name.

Anytime the **START/QUEUE/MANAGER** command is entered (with or without the **/ON** qualifier), the job controller will check to see if one or more preferred queue manager nodes was currently or previously specified with the **/ON** qualifier. If one or more preferred nodes was specified, and the

queue manager is running on a node other than the first available node of those specified, the queue manager process is moved from its current node and restarted on the first available preferred node. Despite the transition, queues on the running nodes are not stopped. All requests to the queuing system, for example, **PRINT**, **SUBMIT**, and **SHOW ENTRY** requests, will complete as expected.

## Examples

1. 

```
$ START/QUEUE/MANAGER/NEW_VERSION
$ SHOW QUEUE
%JBC-E-NOSUCHQUEUE, no such queue
```

The **START/QUEUE/MANAGER** command in this example starts the queue manager and creates the queue and journal files in the default location, SYSSCOMMON:[SYSEXE]. Because the asterisk (\*) wildcard character is used by default as the value for the list of nodes on which the queue manager can run, the queue manager can fail over to any available node in the cluster.

This command starts the default queue manager SYSSQUEUE\_MANAGER because the **/NAME\_OF\_MANAGER** qualifier is not specified.

Both the SYSSCOMMON:[SYSEXE] location and the value for the **/ON** qualifier (which is \* by default in this example) are stored in the queue database for future reference. The newly created queue database contains no queues or jobs. The **SHOW QUEUE** command shows that no queues are defined on this cluster.

2. 

```
$ START/QUEUE/MANAGER/NEW_VERSION -
_$ /ON=(SATURN,VENUS,NEPTUN,*) DUA5:[SYSQUE]
```

The **START/QUEUE/MANAGER** command in this example creates the queue and journal files on the cluster-accessible disk volume DUA5, in directory SYSQUE. You must mount the disk before you enter the **START/QUEUE/MANAGER** command.

The **/ON** qualifier specifies that the queue manager should run first on node SATURN. If SATURN leaves the cluster, the queue manager will attempt to fail over to VENUS. If VENUS is not available, the queue manager will attempt to fail over to NEPTUN. If NEPTUN is not available, the queue manager will fail over to any other available node in the cluster.

3. 

```
$ START/QUEUE/MANAGER/NEW_VERSION -
_$ /ON=(SATURN,VENUS,NEPTUN,*) DUA5:[SYSQUE])
.
.
.
$ START/QUEUE/MANAGER
```

The **START/QUEUE/MANAGER** command in this example creates the queue database as shown in the previous example. Suppose the queue manager started on node SATURN.

Later, SATURN is removed from the cluster, and the queue manager fails over to node VENUS. When SATURN rejoins the cluster, the second **START/QUEUE/MANAGER** command in the example is entered to move the queue manager back to node SATURN.

The second **START/QUEUE/MANAGER** command does not specify the DUA5:[SYSQUE] parameter value or the **/ON** qualifier and its node list because those previously supplied pieces of information are stored in the queue database. The queue manager continues to use the queue and journal files found at the location stored in its database. The **/ON** list, stored as a result of the previous **START/QUEUE/MANAGER** command, also remains unchanged.

```
4. $ START/QUEUE/MANAGER DUA4:[SYSQUE]
    %JBC-E-QMANNOTSTARTED, queue manager could not be started
    $ SEARCH SYS$MANAGER:OPERATOR.LOG /WINDOW=5 QUEUE_MANAGE,JOB_CONTROL
    %%%%%%%%%% OPCOM 14-DEC-2001 18:55:18.23 %%%%%%%%%%
    Message from user QUEUE_MANAGE on QMUNGR
    %QMAN-E-OPENERR, error opening DUA4:[SYSQUE]SYS$QUEUE_MANAGER.QMAN
    $QUEUES;

    %%%%%%%%%% OPCOM 14-DEC-2001 18:55:18.29 %%%%%%%%%%
    Message from user QUEUE_MANAGE on QMUNGR
    -RMS-F-DEV, error in device name or inappropriate device type for
    operation

    %%%%%%%%%% OPCOM 14-DEC-2001 18:55:18.31 %%%%%%%%%%
    Message from user QUEUE_MANAGE on QMUNGR
    -SYSTEM-W-NOSUCHDEV, no such device available
    $ START/QUEUE/MANAGER DUA5:[SYSQUE]
```

In this example, the first **START/QUEUE/MANAGER** command specifies device DUA4: as the location of the queue and journal files. The error message indicates that the queue manager does not start. The **SEARCH** command searches the operator log file for relevant messages, and reveals that device DUA4: does not exist. The second **START/QUEUE/MANAGER** command specifies the correct device name, DUA5:.

## START/ZONE

**START/ZONE** — Adds a zone to the running VAXft system. For more information on the **START/ZONE** command, see the VAXft systems documentation. **Applies only to the VAXft system. Requires CMKRNL (change mode to kernel) privilege.**

### Format

**START/ZONE**

## STOP

**STOP** — Terminates execution of a command, an image, a command procedure, a command procedure that was interrupted by a **Ctrl/Y** function, or a detached process or subprocess. **Requires GROUP privilege to stop other processes in the same group. Requires WORLD privilege to stop processes outside your group.**

### Format

**STOP** [*process-name*]

### Parameter

*process-name*

Requires that the process be in your group.

Specifies the name of the process to be deleted. The process name can have from 1 to 15 alphanumeric characters. If the *process-name* includes spaces or lowercase letters, enclose the name in quotation marks (" ") to preserve the correct spelling.

The specified process must have the same group number in its user identification code (UIC) as the current process; you cannot use the *process-name* parameter to stop a process outside of your group. To stop a process outside of your group, you must use the qualifier **/IDENTIFICATION=*pid***.

The process name is incompatible with the **/IDENTIFICATION** qualifier; if you use the **/IDENTIFICATION** qualifier, the process name is ignored. If you include neither the *process-name* parameter nor the **/IDENTIFICATION** qualifier with the **STOP** command, the image executing in the current process is terminated.

## Description

The **STOP** command causes an abnormal termination of the image that is currently executing. If the image has declared user-mode exit-handling routines using calls to the \$DCLEXH system service, by default these exit handlers are not invoked. If execution of exit-handling routines is required, use the **EXIT** command or the **STOP/EXIT** command to terminate the image so that the mode-specific exit handlers are invoked.

If the **STOP** command is executed from a noninteractive process (such as a batch job), the process terminates.

Note that when an image has been interrupted by a **Ctrl/Y** function and subsequently the DCL **RUN** command or a non-CLI-based DCL verb is entered, the interrupted image is terminated. However, in this case, exit-handling routines execute before the next image is run. For more information about process and image rundown processing, see the *VSI OpenVMS User's Manual* [<https://docs.vmssoftware.com/vsi-openvms-user-s-manual/>] or the *VSI OpenVMS Programming Concepts Manual, Volume I* [<https://docs.vmssoftware.com/vsi-openvms-programming-concepts-manual-volume-i/>] and *Volume II* [<https://docs.vmssoftware.com/vsi-openvms-programming-concepts-manual-volume-ii/>].

If you press **Ctrl/Y** to interrupt a command procedure and then enter the **STOP** command, or if the **STOP** command is executed in a command procedure, all command levels are unstacked and control returns to command level 0 (DCL level with the \$ prompt).

If you specify a process name or process identification (PID) code, the **STOP** command terminates the image currently executing in the specified process and deletes the process. If the process is noninteractive, no notification of the deletion occurs and the log file for the job is not printed.

## Qualifiers

### **/IDENTIFICATION=*pid***

Specifies the system-assigned process identification (PID) code. When you create a process with the **RUN** command, the **RUN** command displays the PID code of the newly created process. The **/IDENTIFICATION** qualifier can be used in place of the process name parameter.

You can omit any leading zeros in specifying the PID code.

### **/IMAGE [/IDENTIFICATION=*pid*] [*process-name*]**

Calls the \$FORCEX system service to stop the image of the target process specified in the process id or process name that is currently executing. The target process is not deleted.

If you omit the **/IDENTIFICATION** qualifier and the process name, the **STOP/IMAGE** command is identical to the **STOP** command.

**/EXIT[=*access-mode*] (default)**  
**/NOEXIT**

Specifies an option to call exit handlers prior to deletion of the process.

The following table describes the access mode options:

| Mode            | Description                                                                                      |
|-----------------|--------------------------------------------------------------------------------------------------|
| EXECUTIVE_MODE  | Execute executive and more privileged mode exit handlers (default, if no access mode specified). |
| KERNEL_MODE     | Execute kernel mode exit handlers.                                                               |
| SUPERVISOR_MODE | Execute supervisor and more privileged mode exit handlers.                                       |
| USER_MODE       | Execute user and more privileged mode exit handlers.                                             |

## Examples

```
1. $ RUN MYPROG
    .
    .
    .
Ctrl/Y
Interrupt
$ STOP
```

The **RUN** command in this example begins executing the image MYPROG. Subsequently, the **Ctrl/Y** function interrupts the execution. The **STOP** command then terminates the image.

```
2. $ @TESTALL
    .
    .
    .
Ctrl/Y
Interrupt
$ STOP
```

The **@** (execute procedure) command in this example executes the procedure TESTALL.COM. Subsequently, the **Ctrl/Y** function interrupts the procedure. The **STOP** command then returns control to the DCL command interpreter.

```
3. $ RUN/PROCESS_NAME=LIBRA  LIBRA
    %RUN-S-PROC_ID, identification of created process is 0013340D
    .
    .
    .
$ STOP LIBRA
```

The **RUN** command in this example creates a subprocess named LIBRA to execute the image LIBRA.EXE. Subsequently, the **STOP** command causes the image to exit and deletes the process.

```
4. $  ON ERROR THEN STOP
```

.  
. .  
.

In a command procedure, the **ON** command establishes a default action when any error occurs in the execution of a command or program. The **STOP** command stops all command levels. If this **ON** command is executed in a command procedure, which in turn is executed from within another procedure, control does not return to the outer procedure, but to DCL command level 0.

5. \$ STOP/EXIT

Terminates the process and runs exit handlers beginning at executive mode.

6. \$ STOP/IMAGE/ID=12345678

Terminates the current user image being executed by process 12345678.

## STOP/CPU

**STOP/CPU** — Stops the specified secondary processor or processors (and any associated vector processors). The **/CPU** qualifier is required. **Applies only to OpenVMS multiprocessing systems. Requires CMKRNL(change mode to kernel) privilege.**

### Format

**STOP/CPU** [*cpu-id*[ , ... ]]

### Parameter

*cpu-id*[ , ... ]

Specifies a decimal value representing the identity of a processor in an OpenVMS multiprocessing system. On an Alpha 7000 system, the CPU ID is the backplane slot number of the processor. If you do not specify a CPU ID, the **STOP/CPU** command selects a processor in the current active set to stop.

### Description

The **STOP/CPU** command removes a secondary processor from the active set in an OpenVMS multiprocessing system. If the secondary processor is not executing a process when the **STOP/CPU** command is issued, it enters the STOPPED state. If the secondary is executing a process at the time, it continues to execute the current process until it attempts to schedule another process. When this occurs, the secondary enters the STOPPED state.

The OpenVMS operating system subjects a processor to a set of checks when it is the object of a **STOP/CPU** command. As a result, you may not be permitted to stop certain processors that are vital to the functioning of the system. In these cases, there is usually a process in the system that can execute only on the processor you intend to stop. You can determine this by issuing a **SHOW CPU/FULL** command. In unusual circumstances, you can bypass the checking mechanism by using the **/OVERRIDE\_CHECKS** qualifier in the command.

The **STOP/CPU** command has no effect if its object processor is already in the STOPPED state when it is issued.

## Qualifiers

### **/ALL**

Stops all eligible secondary processors in the system's active set.

### **/ASSIGN=option (Alpha/Integrity servers only)**

Assigns specified processors to the hard partition node after they are stopped.

| Option             | Description                                                                                                                                                          |
|--------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| \$\$HARD_PARTITION | The configuration tree hard partition node. All instances running in the hard partition defined by this node have visibility and access to CPUs owned at this level. |

Supported only on AlphaServer systems that support partitioning.

### **/MIGRATE (Alpha/Integrity servers only)**

Transfers ownership of the CPU from the current instance to another soft partition.

| Option               | Description                                                                                                                                                                          |
|----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>instance_name</i> | The name of any valid running instance in the current hard partition.                                                                                                                |
| <i>partitionID</i>   | The numeric ID of any partition(reflected in the configuration tree) in the current hard partition. An operating system instance is not required to be running with this identifier. |

Supported only on AlphaServer systems that support partitioning.

### **/OVERRIDE\_CHECKS**

Directs the **STOP/CPU** command to bypass a series of OpenVMS scheduling checks that determine whether the specified processor is eligible for removal from the active set.

Note that this is not an unconditional operation; other CPU load or configuration constraints may prevent the specified processor from being stopped.

### **/POWER=OFF (Alpha/Integrity servers only)**

Powers down the CPU after it is removed from the active set. The CPU will be powered down while still owned by the instance, prior to any assignments.

The **/POWER** qualifier cannot be used in conjunction with the **/MIGRATE** qualifier.

Supported only on AlphaServer GS series systems.

## Examples

1. \$ STOP/CPU

The **STOP/CPU** command in this example selects a processor and removes it from the multiprocessing system's active set.

2. `$ STOP/CPU 4,7`

The **STOP/CPU** command in this example selects the processors with CPU IDs 4 and 7 and removes them from the multiprocessing system's active set.

3. `$ STOP/CPU/OVERRIDE_CHECKS 8`

The **STOP/CPU/OVERRIDE\_CHECKS** command in this example overrides some OpenVMS scheduling states that ordinarily prevent the operation and stops the processor with the CPU ID of 8. Then it is removed from active participation in the multiprocessing system.

4. `$ STOP/CPU/ALL`

The **STOP/CPU/ALL** command in this example stops all eligible secondary processors in the active set and removes them from the multiprocessing system.

5. `$ STOP/CPU/MIGRATE=WFGLXE 5`

The **STOP/CPU/MIGRATE** command in this example removes CPU 5 from the current instance's active set and transfers ownership to instance WFGLXE in the current hard partition.

6. `$ STOP/CPU/ASSIGN=$$HARD 6`

The **STOP/CPU/MIGRATE** command in this example removes CPU 6 from the current instance's active set and transfers ownership to the hard partition node in the configuration tree. The CPU is immediately available for assignment for any instance within the hard partition defined by that node.

## STOP/NETWORK

**STOP/NETWORK** — Stops the specified network service on the local node. The **/NETWORK** qualifier is required.

### Format

**STOP/NETWORK** *network-service*

### Parameter

*network-service*

Specifies the name of the network service that you want to halt.

### Description

The **STOP/NETWORK** command causes the specified network to stop executing on the local node.

Use the **START/NETWORK** command to release the network from the paused state.

### Example

```
$ STOP/NETWORK DECnet
```

The **STOP/NETWORK** command in this example stops the current network service.

# STOP/QUEUE

**STOP/QUEUE** — The **STOP/QUEUE** command causes the specified execution queue to pause. All jobs currently executing in the queue are suspended (until the queue is restarted with the **START/QUEUE** command), and no new jobs are initiated. The **/QUEUE** qualifier is required. **Requires manage (M) access to the queue.**

## Format

**STOP/QUEUE** *queue-name* [ : ]

## Parameter

*queue-name* [ : ]

Specifies the name of the queue that you want to pause.

## Description

The **STOP/QUEUE** command causes the specified queue to pause. All jobs currently executing in the queue are suspended. No new jobs are initiated.

Use the **START/QUEUE** command to release the queue from the paused state. When you restart the queue, any jobs that were executing resume executing at the point where they left off, unless you use the **/BACKWARD**, the **/FORWARD**, the **/SEARCH**, or the **/TOP\_OF\_FILE** qualifier to restart a print job at a different place.

For information about how to stop a queue, see the following commands:

[STOP/QUEUE/ABORT](#)

[STOP/QUEUE/ENTRY](#)

[STOP/QUEUE/MANAGER/CLUSTER](#)

[STOP/QUEUE/NEXT](#)

[STOP/QUEUE/REQUEUE](#)

[STOP/QUEUE/RESET](#)

[STOP/QUEUES/ON\\_NODE](#)

## Examples

1. \$ STOP/QUEUE LPA0

The **STOP/QUEUE** command in this example suspends the current print job in the queue LPA0 and places that queue in the paused state.

2. \$ STOP/QUEUE JADE\_PRINT  
\$ START/QUEUE/TOP\_OF\_FILE JADE\_PRINT

The **STOP/QUEUE** command in this example suspends the job that is currently printing on the printer queue JADE\_PRINT and places that queue in the paused state. The **START/QUEUE** command releases the queue from the paused state. The **/TOP\_OF\_FILE** qualifier causes the job that was suspended to resume printing at the beginning of the file rather than at where it was interrupted.

# STOP/QUEUE/ABORT

STOP/QUEUE/ABORT — Aborts a job that is printing or processing on an output queue, deletes it from the queue, and begins processing the first pending job in the queue. The **/QUEUE** qualifier is optional, but the **/ABORT** qualifier is required. **Requires delete (D) access to the current job.**

## Format

**STOP/QUEUE/ABORT** *queue-name* [ : ]

## Parameter

*queue-name* [ : ]

Specifies the name of the queue containing the job you want to abort.

## Description

When you abort a print job, the print job completes the page that is currently printing. Then the job is removed from the queue. If the output queue has been set up to put trailing pages at the end of jobs, a trailer page is printed after the current page is completed. For information on how a batch job is aborted, see the description of the [STOP/QUEUE/ENTRY](#) command.

Use the **STOP/QUEUE/ABORT** command to abort the current print job and to delete it from the queue. You do not specify a job entry number with the **/ABORT** qualifier, because output queues can have only one current job at a time.

Use the **STOP/QUEUE/ENTRY** command to abort one or more batch jobs that are executing currently on a queue and to delete them from the queue. To stop a batch job, you must specify an entry number because batch queues, unlike print queues, can have more than one job executing at the same time. (You also can use the **STOP/QUEUE/ENTRY** command to abort a print job that is printing or processing currently on a queue, and to delete it from the queue.)

Use the **STOP/QUEUE/REQUEUE** command to stop batch or print jobs and to requeue them. Use the **DELETE/ENTRY** command to delete an entry that is queued and awaiting execution.

---

## Note

If you enter the **STOP/QUEUE/ABORT** command accidentally for a malfunctioning queue, enter the **STOP/QUEUE/RESET** command to stop the queue in an orderly fashion.

---

## Examples

```
$ STOP/QUEUE/ABORT LPA0
```

This example aborts the current print job on the queue LPA0. The print symbiont begins to process the first pending job in the queue. Assuming there is no problem with the printer, the current page of the file completes printing. If the printer queue has been set up to put trailer pages at the end of jobs, a trailer page is printed after the current page is completed.

For batch queues an entry number must be provided. To abort a batch job, use the **STOP/QUEUE/ENTRY** command.

# STOP/QUEUE/ENTRY

STOP/QUEUE/ENTRY — Aborts one or more jobs that are executing on a batch queue or printing on an output queue, deletes them from the queue, and begins processing the first pending job in the queue. The **/QUEUE** qualifier is optional, but the **/ENTRY** qualifier is required. **Requires delete (D) access to the specified job.**

## Format

**STOP/QUEUE/ENTRY**=(*entry-number*[ , ... ] ) [*queue-name*[ : ] ]

## Parameters

*entry-number*[ , ... ]

Specifies the entry number (or a list of entry numbers) of jobs to be deleted. If you specify only one entry number, you can omit the parentheses. If you do not specify a queue name, you can delete entries from multiple queues.

The system assigns a unique entry number to each queued print or batch job in the system. By default, the **PRINT** and **SUBMIT** commands display the entry number when they successfully queue a job for processing. These commands also create or update the local symbol \$ENTRY to reflect the entry number of the most recently queued job. To find a job's entry number, enter the **SHOW ENTRY** or the **SHOW QUEUE** command.

*queue-name*[ : ]

Specifies the name of the queue that contains the jobs that you want to abort. The queue name can refer either to the queue to which the job was submitted or to the queue where the job is executing. The *queue-name* parameter is optional syntax; however, when you specify a queue name, the OpenVMS system uses it to verify an entry in the specific queue before stopping and deleting the entry.

## Description

When you abort a batch job, the system tries to stop the job in an orderly fashion by closing any open files and sending a message to the log file. For information on how a print job is aborted, see the description of the [STOP/QUEUE/ABORT](#) command.

Use the **STOP/QUEUE/ENTRY** command to abort one or more batch jobs that are executing currently on a queue and to delete them from the queue. To stop a batch job, you must specify an entry number because batch queues, unlike print queues, can have more than one job executing at the same time. (You also can use the **STOP/QUEUE/ENTRY** command to abort a print job that is currently printing or processing on a queue and to delete it from the queue.)

Use the **STOP/QUEUE/REQUEUE** command to stop batch or print jobs and to requeue them. Use the **DELETE/ENTRY** command to delete an entry that is queued and is awaiting execution.

---

## Note

If you enter the **STOP/QUEUE/ENTRY** command accidentally for a malfunctioning queue, enter the **STOP/QUEUE/RESET** command to stop the queue in an orderly fashion.

---

## Example

```
$ STOP/QUEUE/ENTRY=365 SYS$BATCH
```

The **STOP/QUEUE/ENTRY** command in this example aborts batch job number 365 currently executing on the SYS\$BATCH queue and begins the first pending job in the queue.

## STOP/QUEUE/MANAGER/CLUSTER

**STOP/QUEUE/MANAGER/CLUSTER** — Shuts down the queue manager on a standalone node or an OpenVMS Cluster. The **/QUEUE** qualifier is optional, but the **/MANAGER** and **/CLUSTER** qualifiers are required on both standalone and clustered systems. By default, the command affects the default queue manager, SYS\$QUEUE\_MANAGER. Specify the **/NAME\_OF\_MANAGER** qualifier to shut down a queue manager other than the default. **Requires OPER (operator) and SYSNAM (system logical name) privileges.**

## Format

**STOP/QUEUE/MANAGER/CLUSTER**

## Parameters

None.

## Description

The **STOP/QUEUE/MANAGER/CLUSTER** command notifies the queue manager to perform the following on the standalone node or on all nodes in the cluster:

- Abort all of the current jobs that cannot be restarted, and requeue all of the current restartable jobs on the queue manager
- Stop all of the execution queues on the queue manager
- Disable the autostart feature for all of the queue manager's autostart queues
- Close the queue manager's queue and journal files

Once the **STOP/QUEUE/MANAGER/CLUSTER** command is entered, the affected queue manager process remains stopped, and requests to the queuing system are denied until the DCL command **START/QUEUE/MANAGER** is entered.

## Qualifier

**/NAME\_OF\_MANAGER=name**

Specifies the name of the queue manager process to be stopped. If the **/NAME\_OF\_MANAGER** qualifier is omitted, the default queue manager name SYS\$QUEUE\_MANAGER is used. For more information, see the chapter about the queue manager in the *VSI OpenVMS System Manager's Manual, Volume 1: Essentials* [[https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#\\_6017QUEUE\\_MGR](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#_6017QUEUE_MGR)].

## Example

```
$ STOP/QUEUE/MANAGER/CLUSTER
```

The **STOP/QUEUE/MANAGER/CLUSTER** command in this example stops the queue manager process, SYSS\$QUEUE\_MANAGER. The process remains stopped and requests to SYSS\$QUEUE\_MANAGER will be denied until the **START/QUEUE/MANAGER** command is entered.

This command stops the default queue manager SYSS\$QUEUE\_MANAGER because the **/NAME\_OF\_MANAGER** qualifier is not specified.

## STOP/QUEUE/NEXT

**STOP/QUEUE/NEXT** — Stops the specified queue after all executing jobs have completed processing. No new jobs are initiated. The **/QUEUE** qualifier is optional, but you must specify the **/NEXT** qualifier. **Requires manage (M) access to the queue.**

## Format

```
STOP/QUEUE/NEXT queue-name [ : ]
```

## Parameter

*queue-name* [ : ]

Specifies the name of the queue that you want to stop.

## Description

The **STOP/QUEUE/NEXT** command stops the queue after it allows any current jobs to complete execution. No new jobs are initiated.

You should use the **STOP/QUEUE/NEXT** command before deassigning, deleting, or merging a queue, as this command allows all currently executing jobs to complete processing before changes are made to the queue. You might also use this command to stop a queue if you need to perform planned service on a printing device. Use the **START/QUEUE** command to restart the queue.

For autostart queues, the **STOP/QUEUE/NEXT** command stops the queue and makes it inactive for autostart, so it will not be automatically started. For this reason, you might use this command to prevent an autostart queue from being accidentally restarted when a printing device needs to undergo planned service. Use the **START/QUEUE** command to reactivate the queue for autostart.

## Examples

```
1. $ STOP/QUEUE/NEXT LASER_PRINT
```

In this example, the **STOP/QUEUE/NEXT** command prepares to stop the queue LASER\_PRINT. The currently printing job is allowed to complete, but no new job is allowed to initiate. Once the current job has finished, the queue is stopped.

If LASER\_PRINT is an autostart queue, it will not be automatically started until you enter the **START/QUEUE** command.

```
2. $ STOP/QUEUE/NEXT BATCH_1
   $ SHOW QUEUE/ALL BATCH_1
   Batch queue BATCH_1, stopped, on JADE::
   $ DELETE/QUEUE BATCH_1
```

This example shows how to delete the batch queue BATCH\_1. First, the **STOP/QUEUE/NEXT** command is entered, which stops the queue after jobs currently executing on the queue are completed. Second, the **SHOW QUEUE/ALL** command is entered to ensure that no jobs are pending in the queue. The screen display shows that no jobs are pending. Finally, the **DELETE/QUEUE** command is entered to delete the queue BATCH\_1.

## STOP/QUEUE/REQUEUE

**STOP/QUEUE/REQUEUE** — Stops the current jobs on the specified queue and requeues them for later processing. The queue does not stop; processing of the first pending job in the queue begins. The **/QUEUE** qualifier is optional, but the **/REQUEUE** qualifier is required. The **/ENTRY** qualifier is required to requeue batch jobs. **Requires delete (D) access to the current or specified job.**

### Format

```
[=queue-name] queue-name[:][=queue-name] /ENTRY=(entry-  
number[, ...])queue-name[:]
```

### Parameters

***queue-name*[:]**

Specifies the name of the queue that contains the jobs that you want to stop. When you specify a queue name as a parameter for the **/REQUEUE** qualifier, the jobs are requeued to that queue; otherwise, the jobs are requeued in the current queue.

***entry-number*[, ...]**

Specifies the entry number (or a list of entry numbers) of the jobs you want to requeue. If you specify only one entry number, you can omit the parentheses.

The system assigns a unique entry number to each queued print or batch job in the system. By default, the **PRINT** and **SUBMIT** commands display the entry number when they successfully queue a job for processing. These commands also create or update the local symbol \$ENTRY to reflect the entry number of the most recently queued job. To find a job's entry number, enter the **SHOW ENTRY** or **SHOW QUEUE** command.

### Description

The **STOP/QUEUE/REQUEUE** command causes the system to requeue the jobs for later processing or for execution in the queue. If the print symbiont has sent checkpoint information about a print job to the job controller, printing resumes at the last checkpoint recorded, unless you enter the **SET ENTRY/NOCHECKPOINT** command before the job is reinitiated. Batch jobs generally restart at the beginning; however, batch jobs that contain **SET RESTART\_VALUE** commands run only those portions of the job that have not completed successfully.

Use the **STOP/QUEUE/ABORT** command to stop a current print job without requeueing it. Use the **STOP/QUEUE/ENTRY** command to stop a current batch job without requeueing it. You also

can use the **STOP/QUEUE/ENTRY** command to stop a print job without requeueing it. Use the **DELETE/ENTRY** command to delete an entry that is queued and is waiting to be executed or processed.

---

## Note

If you enter the **STOP/QUEUE/REQUEUE** command accidentally for a malfunctioning queue, enter the **STOP/QUEUE/RESET** command to stop the queue in an orderly fashion.

---

## Qualifiers

### **/ENTRY=(entry-number[,...])**

Specifies the entry number of one or more jobs you want to abort. If you specify only one entry number, you can omit the parentheses.

The system assigns a unique entry number to each queued print or batch job in the system. By default, the **PRINT** and **SUBMIT** commands display the entry number when they successfully queue a job for processing. These commands also create or update the local symbol \$ENTRY to reflect the entry number of the most recently queued job. To find a job's entry number, enter the **SHOW ENTRY** or the **SHOW QUEUE** command.

You must use the **/ENTRY** qualifier when you enter the **STOP/QUEUE/REQUEUE** command for a batch queue. Entry numbers specified must match entry numbers of executing jobs.

### **/HOLD**

Places the aborted job or jobs in a hold state for later release with the **SET ENTRY/RELEASE** or **SET ENTRY/NOHOLD** command.

### **/PRIORITY=*n***

Requires OPER (operator) or ALTPRI (alter privilege) privilege to raise the priority value above the value of the system parameter MAXQUEPRI.

Changes the priority of the requeued job or jobs. The parameter *n* can be from 0 to 255; the default value of the *n* parameter is the same as the priority value that the job or jobs had when they were stopped.

Generally, the **/PRIORITY** qualifier is used to lower the priority of a job or jobs, which ensures that the job or jobs runs when the queue contains no other jobs. No privilege is needed to set the priority lower than the MAXQUEPRI value.

### **/REQUEUE=[queue-name]**

Specifies a queue where current jobs are to be requeued. If you do not specify the *queue-name* parameter, the jobs are requeued in the current queue.

## Examples

1. \$ **STOP/QUEUE/REQUEUE=LPB0 LPA0**

In this example, the current print job on queue LPA0 is stopped and requeued to queue LPB0. If the print symbiont sent checkpoint information about the print job to the job controller, printing resumes on LPB0 at the last checkpoint recorded.

2. (wide)  
\$ STOP/QUEUE/REQUEUE/HOLD LPA0  
.  
.  
.  
\$ SET ENTRY 254/RELEASE

In this example, the current print job on LPA0 is suspended and placed in the hold state. Later, when you enter the **SET ENTRY** command with the **/RELEASE** qualifier, the job is released from the hold state and is rescheduled to print on queue LPA0. If the print symbiont sent checkpoint information about the print job to the job controller, printing resumes at the last checkpoint.

3. \$ STOP/QUEUE/REQUEUE/ENTRY=758 SYS\$BATCH

In this example, batch job number 758 is stopped and queued for later processing on SYS\$BATCH. If the batch job has been programmed with appropriate **SET RESTART\_VALUE** commands, those portions of the job that have completed successfully are not rerun.

## STOP/QUEUE/RESET

**STOP/QUEUE/RESET** — Abruptly stops the queue and returns control to the system. Any jobs that cannot be restarted are aborted immediately. The **/QUEUE** qualifier is optional, but you must specify the **/RESET** qualifier. **Requires manage (M) access to the queue.**

### Format

**STOP/QUEUE/RESET** *queue-name* [ : ]

### Parameter

*queue-name* [ : ]

Specifies the name of the queue you want to reset.

### Description

The **STOP/QUEUE/RESET** command stops the queue as soon as the system receives the command. The queue manager requests termination for all executing jobs, but aborts or requeues executing jobs without waiting for termination status to be received. Current jobs that can be restarted are queued for processing. Current jobs that cannot be restarted are aborted and must be resubmitted for processing. (Print jobs are restartable by default. Batch jobs are restartable if submitted with the **SUBMIT/RESTART** command.) Use the **START/QUEUE** command to restart the queue.

For autostart queues, the **STOP/QUEUE/RESET** command stops the queue and makes it inactive for autostart, so it will not be automatically started. For this reason, you might use this command to prevent an autostart queue from being automatically restarted when a printing device fails and needs to be serviced. Use the **START/QUEUE** command to reactivate the queue for autostart.

### Examples

1. \$ INITIALIZE/QUEUE/AUTOSTART\_ON=MYNODE::LPA0/START LPA0  
\$ ENABLE AUTOSTART/QUEUES/ON\_NODE=MYNODE  
.

```
.  
.  
$ STOP/QUEUE/RESET LPA0  
$ START/QUEUE LPA0
```

The **INITIALIZE/QUEUE** command in this example creates an autostart output queue named LPA0. The **/START** qualifier activates the queue for autostart, and the **ENABLE AUTOSTART/QUEUES** command causes the queue to begin executing.

Suppose the printer LPA0 : : runs out of paper. The **STOP/QUEUE/RESET** command abruptly stops the queue LPA0. The current print job stops immediately and is requeued. The **STOP/QUEUE/RESET** command also makes the queue inactive for autostart, so it will not be restarted while the printer's paper is being resupplied.

After the printer is loaded with paper, the **START/QUEUE** command makes the queue active for autostart and allows the queue manager to automatically start it again.

## 2. \$ STOP/QUEUE/RESET TEXTBATCH

The **STOP/QUEUE/RESET** command in this example stops the batch queue TEXTBATCH. Any current jobs that were submitted with the **/RESTART** qualifier are requeued for processing when the queue is restarted. Users might want to resubmit current jobs that were not originally submitted with the **/RESTART** qualifier.

# STOP/QUEUES/ON\_NODE

**STOP/QUEUES/ON\_NODE** — Stops all queues on the specified node. This command is useful if you want to stop a set of queues on a node with a single command (for example, before shutting down a node), but do not want to stop a queue manager throughout an OpenVMS Cluster. The **/QUEUES** qualifier is optional, but the **/ON\_NODE** qualifier is required. **Requires OPER (operator) privilege.**

## Format

**STOP/QUEUES/ON\_NODE** [=node]

## Parameters

None.

## Description

The **STOP/QUEUES/ON\_NODE** command notifies the queue manager to perform the following tasks:

- Abort all current jobs that cannot be restarted (in all of that queue manager's execution queues on the appropriate node), and requeue all current restartable jobs.
- Stop all of that queue manager's execution queues on the appropriate node. Force any of that queue manager's autostart queues on the node to fail over to the next available node in the queue's failover list (if any) on which autostart is enabled.
- Prevent any of that queue manager's autostart queues from failing over to the node.

By default, this command affects the node from which it is entered. Specify a nodename with the **/ON\_NODE** qualifier to stop queues on a different node.

By default, the command affects autostart queues managed by the default queue manager, `SYSS$QUEUE_MANAGER`. Specify the `/NAME_OF_MANAGER` qualifier to disable autostart of a different queue manager's autostart queues (on the node).

The **STOP/QUEUES/ON\_NODE** command affects all autostart and nonautostart execution queues on the appropriate node that are managed by the queue manager. Autostart queues stopped as a result of this command remain active for autostart and will be restarted when the **ENABLE AUTOSTART** command is entered for the affected node or a node to which the queue can fail over. Nonautostart queues stopped as a result of this command must each be started with a **START/QUEUE** command specifying the queue name.

If you are using autostart queues, you might want to enter the **DISABLE AUTOSTART/QUEUES** command. For more information on the relationship between **DISABLE AUTOSTART/QUEUES** and **STOP/QUEUES/ON\_NODE**, see the relevant section in the *VSI OpenVMS System Manager's Manual, Volume 1: Essentials* [[https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#STOPQ\\_SHUTDOWN](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#STOPQ_SHUTDOWN)].

The **STOP/QUEUES/ON\_NODE** command is included in the shutdown command procedure `SYSS$SYSTEM:SHUTDOWN.COM`. If you shut down a node without using `SHUTDOWN.COM`, you might want to enter the **STOP/QUEUES/ON\_NODE** command first. For more information on stopping queues before shutting down a node, see the relevant section in the *VSI OpenVMS System Manager's Manual, Volume 1: Essentials* [[https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#\\_6017QUEUES](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#_6017QUEUES)].

## Qualifier

**/NAME\_OF\_MANAGER=name**

Specifies the name of the queue manager controlling the queues you want to stop.

If the `/NAME_OF_MANAGER` qualifier is omitted, then the default queue manager name `SYSS$QUEUE_MANAGER` is used. For more information on multiple queue managers, see the relevant section in the *VSI OpenVMS System Manager's Manual, Volume 1: Essentials* [[https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#\\_6017QUEUES](https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-1-essentials/#_6017QUEUES)].

## Examples

1. `$ STOP/QUEUES/ON_NODE`

The **STOP/QUEUES/ON\_NODE** command in this example stops all queues on the node from which it is entered. The autostart feature is disabled on this node for all autostart queues.

However, the queue manager process continues to run and schedules jobs as requested for execution on its unstopped queues on other nodes in the OpenVMS Cluster.

This command only affects queues managed by the default queue manager `SYSS$QUEUE_MANAGER` because the `/NAME_OF_MANAGER` qualifier is not specified.

2. `$ INITIALIZE/QUEUE-  
_$/AUTOSTART_ON=(JADE::,RUBY::,OPAL::)/BATCH/START BATCH_1  
$ENABLE AUTOSTART/QUEUES/ON_NODE=JADE  
$ENABLE AUTOSTART/QUEUES/ON_NODE=RUBY  
.  
.`

```
.  
$ STOP/QUEUES/ON_NODE=JADE  
$ SHOW QUEUE BATCH_1  
Batch queue BATCH_1, idle, on RUBY::
```

The **INITIALIZE/QUEUE** command in this example creates the autostart queue BATCH\_1 capable of running on node JADE, RUBY, or OPAL. The **/START** qualifier activates the queue for autostart. The first **ENABLE AUTOSTART/QUEUES** command enables autostart of all autostart queues on node JADE, causing the queue BATCH\_1 to begin processing on that node. The second **ENABLE AUTOSTART/QUEUES** command enables autostart for all autostart queues on node RUBY.

Later, suppose node JADE needs to be removed from the cluster. The **STOP/QUEUES/ON\_NODE** command in the example stops all queues on node JADE without stopping the clusterwide queue manager, and causes the autostart queue BATCH\_1 to failover to node RUBY, the next available node in its failover list. Because the **STOP QUEUES/ON\_NODE** command disables autostart, the **ENABLE AUTOSTART/QUEUES** command must be executed on node JADE when it reboots for autostart queues to run on that node in the future.

This command only affects queues managed by the default queue manager SYS\$QUEUE\_MANAGER because the **/NAME\_OF\_MANAGER** qualifier is not specified.

## STOP/ZONE

**STOP/ZONE** — Removes a zone from a running VAXft system. For more information on the **STOP/ZONE** command, see the VAXft systems documentation. **Applies only to the VAXft system. Requires CMKRNL (change mode to kernel) privilege.**

### Format

**STOP/ZONE** *zone-id*

## SUBMIT

**SUBMIT** — Queues one or more files containing command procedures to a batch queue. **Requires submit (S) access to the queue.**

### Format

**SUBMIT** *filespec[,...]*

### Parameter

*filespec[,...]*

Specifies one or more files containing command procedures. The asterisk (\*) and the percent sign (%) wildcard characters are allowed in the directory specification, file name, file type, and version number fields. The default file type is that of the preceding file. If no previous file specification contains an explicit file type, the default file type is .COM.

If you specify more than one file, separate the file specifications with either commas (,) or plus signs (+).

If you specify a node name, you must use the **/REMOTE** qualifier.

## Description

The **SUBMIT** command places the specified files in a batch queue for subsequent execution. By default, this queue is **SYSSBATCH**. All files queued by a single **SUBMIT** command are processed serially as one job. By default, the name of the batch job is the name of the first file specified in the **SUBMIT** command.

The system assigns a unique entry number to each batch job in the queue. When you enter the **SUBMIT** command, by default, the system displays the job name, the queue name, the entry number, and the job status.

The system automatically creates or updates the local symbol **\$ENTRY** when a **SUBMIT** command completes successfully. The value of **\$ENTRY** is a string that identifies the entry number of the most recently queued job. If you want to refer to a job's entry number later, store the value of **\$ENTRY** in another symbol.

After you queue a batch job, the version of the file submitted is processed, even if a newer version of the file is created before the batch job runs. Also, another file with the same name and version number as the file queued cannot be substituted for the file that was submitted.

When the system executes a command procedure submitted to a batch queue, it creates a detached process to execute the commands. This process receives the owner's disk and directory defaults and the same resource quotas and privileges that were given to the owner's interactive process when you logged in.

If multiple procedures are submitted, the job terminates as soon as any procedure exits with an error or severe (fatal) error status.

In an OpenVMS Cluster environment, you should periodically keep the cluster in time synchronization using the **SET TIME/CLUSTER** command because the differences in system times between nodes in an OpenVMS Cluster may vary. This variance may cause a job to begin executing a little before or after the specified time because the redundancy built into the batch and print system allows more than one job controller in the cluster to receive a timer asynchronous system trap (AST) for the job and, thus, to schedule it for execution.

## Batch Job Output

By default, all output from each command procedure in a batch job is written to a log file. This log file is queued for printing on **SYSPRINT** when the batch job finishes. By default, this log file is deleted after it is printed. When you stop a batch job by using the **STOP/QUEUE/ENTRY**, the **STOP/IDENTIFICATION**, or the **DELETE/ENTRY** command, the log file is not queued for printing.

For information on how to change the system's handling of the log file, see the descriptions of the [/LOG\\_FILE](#), [/PRINTER](#), and [/KEEP](#) qualifiers.

## Qualifiers

**/AFTER=*time***  
**/NOAFTER**

Requests that the job be held until after a specific time. If the specified time has passed already, the job is processed immediately.

You can specify time as either absolute time or as a combination of absolute and delta times. For complete information on specifying time values, see the relevant section in the *VSI OpenVMS User's Manual* [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\\_AND\\_TIME\\_SECT](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT)] or the online help topic Date.

In an OpenVMS Cluster, a batch job submitted to execute at a specific time may begin execution a little before or after the requested time. This occurs when the clocks of the member systems in the OpenVMS Cluster are not synchronized. For example, a job submitted using the DCL command **SUBMIT /AFTER=TOMORROW** may execute at 11:58 P.M. relative to the host system's clock.

This problem can occur in a cluster even if a job is run on the same machine from which it was submitted, because the redundancy built into the batch/print system allows more than one job controller in the cluster to receive a timer asynchronous system trap (AST) for the job and, thus, to schedule it for execution. Moreover, this behavior is exacerbated if the batch job immediately resubmits itself to run the next day using the same **SUBMIT** command. This can result in having multiple instances of the job executing simultaneously because TOMORROW (after midnight) might be only a minute or two in the future.

A solution to this problem is to place the **SUBMIT** command in a command procedure that begins with a **WAIT** command, where the delta-time specified in the **WAIT** command is greater than the maximum difference in time between any two systems in the cluster. Use the **SHOW TIME** command on each system to determine this difference in time. Use the **SYSMAN** command **CONFIGURATION SET TIME** to synchronize clocks on the cluster. For complete information on the **SYSMAN** command **CONFIGURATION SET TIME**, see the relevant section in the *VSI OpenVMS System Management Utilities Reference Manual, Volume 2: M-Z* [<https://docs.vmssoftware.com/vsi-openvms-system-management-utilities-reference-manual-volume-ii-m-z/#d0e30791>].

## **/BACKUP** **/NOBACKUP**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/BACKUP** qualifier selects files according to the dates of their most recent backups. This qualifier is incompatible with the **/CREATED**, **/EXPIRED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

## **/BEFORE[=time]** **/NOBEFORE**

Selects only those files dated prior to the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: **BOOT**, **LOGIN**, **TODAY** (default), **TOMORROW**, or **YESTERDAY**. Specify one of the following qualifiers with the **/BEFORE** qualifier to indicate the time attribute to be used as the basis for selection: **/BACKUP**, **/CREATED** (default), **/EXPIRED**, or **/MODIFIED**.

For complete information on specifying time values, see the relevant section in the *VSI OpenVMS User's Manual* [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\\_AND\\_TIME\\_SECT](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT)] or the online help topic Date.

## **/BY\_OWNER[=uic]** **/NOBY\_OWNER**

Selects only those files whose owner user identification code (UIC) matches the specified owner UIC. The default UIC is that of the current process.

Specify the UIC by using standard UIC format as described in the relevant section in the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC_SECTION) [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC\_SECTION].

**/CHARACTERISTICS=(*characteristic*[,...])**

Specifies the name or numbers of one or more characteristics to be associated with the job. Characteristics can refer to such things as color of ink. If you specify only one characteristic, you can omit the parentheses.

A characteristic's number must range from 0 to 127. To see which characteristics have been defined for your system, use the **SHOW QUEUE/CHARACTERISTICS** command. To see which characteristics are associated with a particular queue, use the **SHOW QUEUE/FULL** command.

A job can be executed on a queue only if none, some, or all of the characteristics associated with the queue also are associated with the job, that is, the job's characteristics must be a subset of the queue's characteristics. However, if any of the characteristics associated with the job are not associated with the queue, the job remains pending until one or more of the following occurs:

- The characteristics specified with the queue are changed to make the job's characteristics a subset of the queue's characteristics (using, for example, the **SET QUEUE/CHARACTERISTICS** command).
- The characteristics specified with the job are changed to make the job's characteristics a subset of the queue's characteristics (using, for example, the **SET ENTRY/CHARACTERISTICS** command).
- The job is moved to a queue on which all the job's characteristics have been specified (using, for example, the **SET ENTRY/REQUEUE** command).
- The job is deleted (using, for example, the **DELETE/ENTRY** command).

**/CLI=*filename***

Specifies the command language interpreter (CLI) to be used to process the job. The file specification assumes the device name SYS\$SYSTEM: and the file type .EXE (SYS\$SYSTEM:*filename*.EXE). The default CLI is that defined in the user authorization file (UAF).

**/CONFIRM**

**/NOCONFIRM (default)**

Controls whether a request is issued before each submit operation to confirm that the operation should be performed on that file. The following responses are valid:

|      |       |               |
|------|-------|---------------|
| YES  | NO    | QUIT          |
| TRUE | FALSE | <b>Ctrl/Z</b> |
| 1    | 0     | ALL           |

**Return**

You can use any combination of uppercase and lowercase letters for word responses. You can abbreviate word responses to one or more letters (for example, T, TR, or TRU for TRUE), but these abbreviations must be unique. Affirmative answers are YES, TRUE, and 1. Negative answers include: NO, FALSE, 0, and pressing **Return**. Entering QUIT or pressing **Ctrl/Z** indicates that you want to stop processing the command at that point. When you respond by entering ALL, the

command continues to process, but no further prompts are given. If you type a response other than one of those in the list, DCL issues an error message and redisplay the prompt.

**/CPUTIME=*time***

Defines a CPU time limit for the batch job. You can specify time as delta time, 0, INFINITE, or NONE. If the queue on which the job executes has a defined CPUMAXIMUM value, the smaller of the **SUBMIT** command and queue values is used. If the queue on which the job executes does not have a specified maximum CPU time limit, the smaller of the **SUBMIT** command and user authorization file (UAF) values is used. If the queue on which the job executes does not have a specified maximum CPU time limit and the UAF has a specified CPU time limit of NONE, either the value 0 or the keyword INFINITE allows unlimited CPU time. If you specify the keyword NONE, the specified queue or UAF value is used. CPU time values must be greater than or equal to the number specified by the system parameter PQL\_MCPULM. For more information on specifying CPU time limits, see the "CPU Time Limit Specifications and Actions" table for the **INITIALIZE/QUEUE** command in the *VSI OpenVMS DCL Dictionary: A-M* [[https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\\_119](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_119)].

**/CREATED (default)****/NOCREATED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/CREATED** qualifier selects files based on their dates of creation. This qualifier is incompatible with the **/BACKUP**, **/EXPIRED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

**/DELETE****/NODELETE (default)**

Positional qualifier.

Controls whether files are deleted after processing. If you specify the **/DELETE** qualifier after the **SUBMIT** command name, all files in the job are deleted after processing. If you specify the **/DELETE** qualifier after a file specification, only that file is deleted after it is processed.

For the **/DELETE** qualifier to work, the protection code on the input files must allow delete (D) access to the user identification code (UIC) of the user submitting the job. If delete (D) access is not allowed, or if any file in the command parameter list cannot be opened as input, command processing stops and no batch job is created.

**/EXCLUDE=(*filespec*[,...])****/NOEXCLUDE**

Excludes the specified files from the submit operation. You can include a directory but not a device in the file specification. The asterisk (\*) and the percent sign (%) wildcard characters are allowed in the file specification. If you specify only one file, you can omit the parentheses.

**/EXPIRED****/NOEXPIRED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/EXPIRED** qualifier selects files according to their expiration dates. (The expiration date is set with the **SET FILE/EXPIRATION\_DATE** command.) The **/EXPIRED** qualifier is incompatible with the **/BACKUP**, **/CREATED**, and **/MODIFIED** qualifiers, which also allow you to select files according

to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

**/HOLD****/NOHOLD (default)**

Controls whether the job is made available for immediate processing. The **/HOLD** qualifier holds the job until it is released by the **SET ENTRY/RELEASE** or the **SET ENTRY/NOHOLD** command.

**/IDENTIFY (default)****/NOIDENTIFY**

Displays the job name, the queue name, the entry number, and the status of the job when it is queued.

**/KEEP****/NOKEEP**

Controls whether the log file is deleted after it is printed; the **/NOKEEP** qualifier is the default unless the **/NOPRINTER** qualifier is specified.

**/LOG\_FILE[=*filespec*]****/NOLOG\_FILE**

Names the log file. The asterisk (\*) and the percent sign (%) wildcard characters are not allowed in the file specification.

When you use the **/LOG\_FILE** qualifier, the system writes the batch job's output to the file you specify. If you use the **/NOLOG\_FILE** qualifier, no log file is created. By default, a log file is created, is written to the directory defined by the logical name SYS\$LOGIN in the UAF, and is given the batch job's name as its file name with a file type of .LOG.

You can use the **/LOG\_FILE** qualifier to write the log file to a different device. Logical names in the file specification are translated in the context of the process that submits the job. The process executing the batch job must have access to the device on which the log file will reside.

If you omit the **/LOG\_FILE** qualifier and specify the **/NAME** qualifier, the log file is written to a file having the same file name as that specified by the **/NAME** qualifier with the file type .LOG. When you omit the **/LOG\_FILE** qualifier, the job-name value used with the **/NAME** qualifier must be a valid file name.

**/MODIFIED****/NOMODIFIED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/MODIFIED** qualifier selects files according to the dates on which they were last modified. This qualifier is incompatible with the **/BACKUP**, **/CREATED**, and **/EXPIRED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time modifiers, the default is the **/CREATED** qualifier.

**/NAME=*job-name***

Names the job (and possibly the batch job log file). The job name must be 1 to 39 alphanumeric characters. If characters other than alphanumeric characters, underscores (\_), or dollar signs (\$) are used in the name, enclose the name in quotation marks (" "). The default job name is the name of the first file in the job.

If you omit the **/LOG\_FILE** qualifier, the job-name value must be a valid file name. The **SHOW ENTRY** and **SHOW QUEUE/FULL** commands display the job name.

**/NOTE=text**

Specifies a message string of up to 255 characters. This message string appears as part of the display on a **SHOW QUEUE/FULL** command and can thus be used to convey information concerning a job. The message specified with the **/NOTE** qualifier is also printed on the flag page of the log file (if printed).

**/NOTIFY****/NONOTIFY (default)**

Controls whether a message is broadcast to your terminal session when the job is completed or aborted.

**/PARAMETERS=(parameter[,...])**

Provides the values of up to eight optional parameters (equated to the symbols P1 to P8, respectively, for each command procedure in the job). The symbols are local to the specified command procedure.

Commas (,) separate individual parameters. If you specify only one parameter, you can omit the parentheses.

If the parameter contains spaces, special characters, or lowercase characters, enclose it in quotation marks. The size of the parameter can be from 1 to 255 characters.

**/PRINTER[=queue-name] (default)****/NOPRINTER**

Queues the job log file for printing when your job is completed. The **/PRINTER** qualifier allows you to specify a particular print queue; the default print queue is **SYSPRINT**. If you specify the **/NOPRINTER** qualifier, the **/KEEP** qualifier is assumed.

When batch and output queues are managed by the same queue manager, the queue manager checks to ensure that the queue specified on the **SUBMIT/PRINTER** command is an output queue and that the user has access to the output queue. These checks are not made if the batch queue specified by the **SUBMIT** command and the output queue specified by the **/PRINTER** qualifier are managed by different queue managers.

If you explicitly specify an output queue for the log file when submitting a batch job, be sure the queue you specify with the **/PRINTER** qualifier is an output queue and not a batch queue. Also, be sure that you have access to the output queue.

**/PRIORITY=n**

Requires **OPER** (operator) or **ALTPRI** (alter privilege) privilege to specify a priority greater than the queue's maximum scheduling priority.

Specifies the job-scheduling priority for the batch job with respect to other jobs in the same queue. The value of *n* is an integer in the range of 0 to 255, where 0 is the lowest priority and 255 is the highest.

The default value is the value of the system parameter **DEFQUEPRI**. No privilege is needed to set the priority lower than the queue's maximum scheduling priority, which is the value of the system parameter **MAXQUEPRI**.

The **/PRIORITY** qualifier has no effect on the job's process execution priority. The job's process execution priority is determined by the base priority attribute of the **INITIALIZE/QUEUE/BASE\_PRIORITY** command.

**/QUEUE=queue-name[:]**

Identifies the batch queue on which the job is entered. The default queue is SYS\$BATCH.

**/RAD=n**

Specifies the RAD number on which the submitted batch job is to execute.

When a job is submitted to a batch queue that does not have a RAD setting, the job will execute using the RAD specified. If the batch queue has a RAD setting, the job will execute using the RAD specified on the queue.

When you specify a RAD on a batch job, the job controller creates the process with the \$CREPRC *home\_rad* argument set to the RAD value on the job. If the RAD specified on the job is invalid on the target system, the job fails to execute and the job controller outputs a message to the operator console indicating that a bad RAD was specified. If the bad RAD value matches the RAD setting on the batch queue, the batch queue is stopped and the job remains in the queue.

RAD is supported on AlphaServer GS series systems and starting from OpenVMS Version 8.4, support is extended to NUMA capable Integrity servers.

**/REMOTE**

Queues the job to SYS\$BATCH on the remote node specified. When you use the **/REMOTE** qualifier, you *must* include the node name in the file specification.

Note that, unlike submitting a job on a local node, multiple command procedures queued by a single **SUBMIT/REMOTE** command are considered separate jobs.

You can specify only the following qualifiers with the **/REMOTE** qualifier:

|                 |                 |                  |                  |
|-----------------|-----------------|------------------|------------------|
| <b>/BACKUP</b>  | <b>/BEFORE</b>  | <b>/BY_OWNER</b> | <b>/CONFIRM</b>  |
| <b>/CREATED</b> | <b>/EXCLUDE</b> | <b>/EXPIRED</b>  | <b>/MODIFIED</b> |
| <b>/SINCE</b>   |                 |                  |                  |

**/RESTART**

**/NORESTART (default)**

Indicates whether the job restarts after a system failure or after a **STOP/QUEUE/REQUEUE** command.

**/RETAIN=option**

Specifies the circumstances under which you want your jobs to be retained in a queue. When a job is retained in the queue, you can issue the **SHOW QUEUE** command after the job completes to see the status of the job. Without job retention, no record of a job is left in a queue after a job completes.

Use the following options to specify job retention:

- **ALWAYS** – Holds the job in the queue regardless of the job's completion status.

- **DEFAULT** – Holds the job in the queue as specified by the queue's retention policy.
- **ERROR** – Holds the job in the queue only if the job completes unsuccessfully.
- **UNTIL=*time-value*** – Holds the job in the queue for the specified length of time, regardless of the job's completion status.

---

## Note

You cannot specify a **/NORETAIN** qualifier with the **SUBMIT** command (as system managers can with the commands **INITIALIZE/QUEUE**, **START/QUEUE**, and **SET QUEUE**); however, you can specify **/RETAIN=DEFAULT** with the **SUBMIT** command. The default option holds the job in the queue as specified by the queue's retention policy. If the system manager has not specified retention for the queue, the job is not retained.

---

## How Job Retention Is Determined

Although you can specify job retention options for your own jobs, the job retention option you specify may be overridden by the job retention option of the queue on which your job executed. If you submit or print a job to a generic queue, the generic queue's job retention setting may also override the job retention option you specify. This section describes how job retention is determined.

An execution queue's job retention setting takes precedence over a generic queue's job retention setting; however, if the job's completion status does not match the job retention setting (if any) on the execution queue, then the generic queue's job retention setting attempts to control job retention. If the job's completion status does not match the job retention setting (if any) on the generic queue, then the user-specified job retention setting is used. Jobs submitted directly to execution queues are not affected by job retention settings on generic queues.

If the execution queue's retention setting applies, the job is retained on the execution queue. Likewise, if the generic queue's retention setting applies, the job is retained on the generic queue. If the user-specified setting applies, the job is retained in the queue to which it was submitted.

The following example describes how the queue manager determines job retention:

Suppose you submit a job to a generic queue and specify **/RETAIN=ALWAYS**, and the job completes successfully.

First, the queue manager compares the job's completion status to the execution queue's retention setting. Suppose the queue is set with **/RETAIN=ERROR** (retains only jobs that complete unsuccessfully). The job is not retained in the execution queue because the error condition was not met.

The queue manager then compares the job's completion status to the generic queue's retention setting. Suppose the generic queue has no retention setting. The queue manager's comparison again fails to retain the job.

Finally, the queue manager compares the job's completion status to the retention setting you specified for the job. This comparison reveals that the job should be retained. Because the user-specified setting leads the queue manager to retain the job, the job is held in the queue to which the job was submitted – in this case, the generic queue.

For more information on types of queues, see the **INITIALIZE/QUEUE** command in the [VSI OpenVMS DCL Dictionary: A-M](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_119) [https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\_119]. For more information on setting retention options for queues, see the

**START/QUEUE** or **SET QUEUE** command, or the **INITIALIZE/QUEUE** command in the [VSI OpenVMS DCL Dictionary: A-M](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_119) [https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\_119].

### Timed Retention

Timed retention, which you specify using the **UNTIL=***time-value* option, allows you to retain a job in the queue only as long as you need it. This eliminates the need to delete the job from the queue later.

For example, the following command retains the job MYFILE in the queue until 7:31 on December 14, when the job will automatically be deleted from the queue:

```
$ SUBMIT/RETAIN=UNTIL=14-DEC-2001:07:31:0.0 MYFILE.COM
```

However, depending on the queue's job retention policy, the job might be retained indefinitely. The job retention policy set on the queue takes precedence over the user-specified job retention setting. Because system managers cannot specify timed job retention for a queue, any jobs retained as a result of a queue's setting are retained indefinitely.

If you specify the **/RETAIN=UNTIL=***time-value* option, you must supply a time value. The time value is first interpreted as a delta time, then as a combination time, and finally as an absolute time. If you specify a delta time, the delta begins when the job completes. For example, if you specify **SUBMIT/RETAIN=UNTIL="3:00"**, the job will be retained for three hours after the job completes. For information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT].

### **/SINCE[=time]** **/NOSINCE**

Selects only those files dated on or after the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: **BOOT**, **JOB\_LOGIN**, **LOGIN**, **TODAY** (default), **TOMORROW**, or **YESTERDAY**. Specify one of the following qualifiers with the **/SINCE** qualifier to indicate the time attribute to be used as the basis for selection: **/BACKUP**, **/CREATED** (default), **/EXPIRED**, or **/MODIFIED**.

For complete information about specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic **Date**.

### **/STYLE=keyword**

Specifies the file name format for display purposes.

The valid keywords for this qualifier are **CONDENSED** and **EXPANDED**. Descriptions are as follows:

| Keyword             | Description                                                                                                                                                                           |
|---------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CONDENSED (default) | Displays the file name representation of what is generated to fit into a 255-length character string. This file name may contain a DID or FID abbreviation in the file specification. |
| EXPANDED            | Displays the file name representation of what is stored on disk. This file name does not contain any DID or FID abbreviations.                                                        |

The keywords **CONDENSED** and **EXPANDED** are mutually exclusive. This qualifier specifies which file name format is displayed in the output message, along with the confirmation if requested.

File errors are displayed with the **CONDENSED** file specification unless the **EXPANDED** keyword is specified.

See the relevant section in the *VSI OpenVMS User's Manual* [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE\\_ACCESS](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE_ACCESS)] for more information.

#### **/SYMLINK=keyword**

The valid keywords for this qualifier are **[NO]WILDCARD** and **[NO]ELLIPSIS**. Descriptions are as follows:

| <b>Keyword</b>    | <b>Description</b>                                                               |
|-------------------|----------------------------------------------------------------------------------|
| <b>WILDCARD</b>   | Indicates that symlinks are enabled during wildcard searches.                    |
| <b>NOWILDCARD</b> | Indicates that symlinks are disabled during directory wildcard searches.         |
| <b>ELLIPSIS</b>   | Equivalent to <b>WILDCARD</b> (included for command symmetry).                   |
| <b>NOELLIPSIS</b> | Indicates that symlinks are matched for all wildcard fields except for ellipsis. |

If the file named in the **SUBMIT** command is a symlink, the command operates on the symlink target.

#### **/USER=username**

Requires **CMKRN**L (change mode to kernel) privilege and read (R) and write (W) access to the user authorization file (UAF).

Allows you to submit a job on behalf of another user. The job runs exactly as if that user had submitted it. The job runs under that user's user name and user identification code (UIC), and accounting information is logged to that user's account. By default, the user identification comes from the requesting process. The username qualifier value can be any user name that is validated on your system. The name must be 1 to 12 alphanumeric characters.

#### **/WSDEFAULT=n**

Defines for a batch job a working set default, the default number of physical pages that the job can use. If the queue on which the job executes has a nonzero default working set, the smaller of the specified job and queue values is used. If the queue on which the job executes has a working set default of 0, the smaller of the specified job and UAF values (value established in the user authorization file) is used.

Specify the value of *n* as a number of 512-byte pagelets on Alpha. Note that OpenVMS systems round up this value to the nearest CPU-specific page so that the actual amount of physical memory allowed may be larger than the specified amount on Alpha. If you specify the value 0 or **NONE**, the specified queue or UAF value is used. Working set default values must range between the numbers specified by the system parameters **PQL\_MWSDEFAULT** and **WSMAX**.

#### **/WSEXTENT=n**

Defines for the batch job a working set extent, the maximum amount of physical memory that the job can use. The job uses the maximum amount of physical memory only when the system has excess free pages. If the queue on which the job executes has a nonzero working set extent, the smaller of the specified job and queue values is used. If the queue on which the job executes

has a working set extent of 0, the smaller of the specified job and the value established in the user authorization file (UAF) is used.

Specify the value of *n* as a number of 512-byte pagelets on Alpha. Note that OpenVMS systems round up this value to the nearest CPU-specific page so that the actual amount of physical memory allowed may be larger than the specified amount on Alpha. If you specify the value 0 or NONE, the specified queue or UAF value is used. Working set extent values must range between the numbers specified by the system parameters PQL\_MWSEXTENT and WSMAX.

### **/WSQUOTA=*n***

Defines for the batch job a working set quota, the amount of physical memory that the job is guaranteed. If the queue on which the job executes has a nonzero working set quota, the smaller of the specified job and queue values is used. If the queue on which the job executes has a working set quota of 0, the smaller of the specified job or the value established in the user authorization file (UAF) is used.

Specify the value of *n* as a number of 512-byte pagelets on Alpha. Note that OpenVMS systems round up this value to the nearest CPU-specific page so that the actual amount of physical memory allowed may be larger than the specified amount on Alpha. If you specify the value 0 or NONE, the specified queue or UAF value is used. Working set quota values must range between the numbers specified by the system parameters PQL\_MWSQUOTA and WSMAX.

## **Examples**

1. \$ SUBMIT/AFTER=16:30 TRANSLATE  
Job TRANSLATE (queue SYS\$BATCH, entry 1401) holding until 14-DEC-2001  
16:30

In this example, the command procedure TRANSLATE.COM is submitted to SYS\$BATCH. The procedure is executed at 4:30 P.M. or later. When the batch job completes, the log file TRANSLATE.LOG is queued to SYS\$PRINT for printing and is deleted.

2. \$ SUBMIT /PARAMETERS=(TXT,DOC,MEM) BACKUP, AVERAGE, RUNMASTER  
Job BACKUP (queue SYS\$BATCH, entry 416) pending

In this example, the **SUBMIT** command enters three command procedures in a single job. The job is given three parameters: P1 is equated to the string TXT, P2 to the string DOC, and P3 to the string MEM. After the procedure BACKUP.COM is executed, the procedures AVERAGE.COM and RUNMASTER.COM are executed.

3. \$ SUBMIT/NAME=BATCH24/HOLD TESTALL  
Job BATCH24 (queue SYS\$BATCH, entry 467) holding

In this example, the **SUBMIT** command enters the procedure TESTALL.COM as a batch job and specifies that the job be held for later processing. The job is not released until the **SET ENTRY/RELEASE** command is entered. The **/NAME** qualifier requests that the batch job be identified as BATCH24.

4. \$ SUBMIT TEST.COM  
Job TEST (queue SYS\$BATCH, entry 493) pending  
\$ BATCH\_JOB = \$ENTRY  
.  
.  
.  
\$ DELETE/ENTRY='BATCH\_JOB'

In this command sequence, the `$ENTRY` symbol is used to refer to a particular job in the queue file. The **SUBMIT** command creates a batch job to run the command procedure `TEST.COM`. In addition, the **SUBMIT** command defines `$ENTRY` as a local symbol whose value is the entry number of the job (493 in this example). The second statement assigns the value `$ENTRY` to the local symbol `BATCH_JOB`. The last line of the example deletes the job by using the symbol `BATCH_JOB` to identify it.

- ```
5. $ DEFINE JUNE WORKZ:[SCHREURS]ANNUAL_REPORT.COM
   $ SUBMIT JUNE
   Job ANNUAL_REPORT (queue SYS$BATCH, entry 229) started on ZOO_BATCH
```

In this example, the logical name `JUNE` is created and equated to `ANNUAL_REPORT.COM` with the **DEFINE** command. Using the logical name `JUNE`, the user submits `ANNUAL_REPORT.COM` to the batch queue. Note that the system translates the logical name `JUNE` to `ANNUAL_REPORT.COM` before `ANNUAL_REPORT.COM` is submitted to the batch queue. Also, the log file produced is named `ANNUAL_REPORT.COM` rather than `JUNE.COM`.

Note also that the job is submitted to the generic queue `SYS$BATCH`, but runs on the execution queue `ZOO_BATCH`.

- ```
6. $ SUBMIT/HOLD/QUEUE=ANYRADQ /RAD=1 TEST.COM
   Job TEST (queue ANYRADQ, entry 23) holding

$ SHOW ENTRY/FULL 23
Entry  Jobname      Username      Blocks  Status
-----
    23  TEST        SYSTEM              Holding
On idle batch queue ANYRADQ
Submitted 24-JUL-2001 14:19:37.44 /KEEP /NOPRINT /PRIORITY=100 /RAD=0
File: _$1$DKB200:[SWEENEY.CLIUTL]TEST.COM;1
```

In this example, `TEST.COM` is submitted to the queue `ANYRADQ`. There is no `RAD` setting on the `ANYRADQ` queue.

- ```
7. $ SUBMIT/HOLD/QUEUE=BATCHQ1 /RAD=1 TEST.COM
   Job TEST (queue BATCHQ1, entry 24) holding

$ SHOW ENTRY 24/FULL
Entry  Jobname      Username      Blocks  Status
-----
    24  TEST        SYSTEM              Holding
On idle batch queue BATCHQ1
Submitted 24-JUL-2001 14:23:10.37 /KEEP /NOPRINT /PRIORITY=100 /RAD=0
File: _$1$DKB200:[SWEENEY.CLIUTL]TEST.COM;2
```

In this example, the queue, `BATCHQ1`, is defined with **/RAD=0**. Therefore, use of the **SUBMIT** command creates a job that runs on `RAD 0`, even though `RAD 1` was specified.

## SUBROUTINE

**SUBROUTINE** — Defines the beginning of a subroutine in a command procedure. The **SUBROUTINE** command must be the first executable statement in a subroutine. For more information about the **SUBROUTINE** command, see the description of the **CALL** command in the [VSI OpenVMS DCL Dictionary: A–M](https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE_22) [https://docs.vmssoftware.com/vsi-openvms-dcl-dictionary-a-m/#BLUE\_22].

## Format

**SUBROUTINE**

# SYNCHRONIZE

**SYNCHRONIZE** — Holds the process issuing the command until the specified job completes execution. **Requires delete (D) access to the specified job.**

## Format

**SYNCHRONIZE** [*job-name*]

## Parameter

*job-name*

Specifies the name of the job as defined when the job was submitted. You can specify only job names that are associated with your user name. (A job is associated with the user name of the process that submits it.)

To specify a job that does not have a unique name, use the **/ENTRY** qualifier to specify the entry number. If you specify both the *job-name* parameter and the **/ENTRY** qualifier, the *job-name* parameter is ignored.

If you specify the *job-name* parameter, the command searches for a job with the specified name in the queue SYSS\$BATCH. To specify a job in a different queue, you must specify the name of the queue using the **/QUEUE** qualifier.

## Description

The **SYNCHRONIZE** command provides job synchronization by placing a process in a wait state until the specified job completes. If the specified job is not a current job in the system, the **SYNCHRONIZE** command displays an error message.

When a job specified in a **SYNCHRONIZE** command completes, the process is released from the wait state. The completion status for the **SYNCHRONIZE** command is the same as the completion status of the last command executed in the job. To make sure that you can determine the completion status when the **SYNCHRONIZE** command is part of a command procedure, include **SET NOON** before the **SYNCHRONIZE** command and **SHOW SYMBOL \$STATUS** immediately after the **SYNCHRONIZE** command.

You must specify either the *job-name* parameter or the **/ENTRY** qualifier.

## Qualifiers

**/ENTRY=entry-number**

Identifies the job by the system-assigned entry number.

The system assigns a unique entry number to each queued print or batch job in the system. By default, the **PRINT** and **SUBMIT** commands display the entry number when they successfully

queue a job for processing. These commands also create or update the local symbol **\$ENTRY** to reflect the entry number of the most recently queued job. To find a job's entry number, enter the **SHOW ENTRY** or **SHOW QUEUE** command. If you specify both the *job-name* parameter and the **/ENTRY** qualifier, the job name is ignored.

**/QUEUE=queue-name[:]**

Names the queue containing the job. If you use the **/QUEUE** qualifier, you must specify either the *job-name* parameter or the **/ENTRY** qualifier. If you specify the *job-name* parameter, the default queue is **SY\$BATCH**. If you specify the **/ENTRY** qualifier, there is no default queue. If you specify a generic queue, the command looks for the job in the generic queue and in the generic queue's target execution queues.

**/TIME\_OUT=n**

Allows the user to specify the number of seconds to wait before terminating the **SYNCHRONIZE** command when the target job is running.

## Examples

1. 

```
$ SUBMIT/NAME=PREP FORMAT/PARAMETERS=(SORT,PURGE)
Job PREP (queue SY$BATCH, entry 219) started on queue SY$BATCH
$ SUBMIT PHASER
Job PHASER (queue SY$BATCH, entry 223) started on queue SY$BATCH
```

In this example, the first **SUBMIT** command submits the command procedure **FORMAT.COM** for execution and names the job **PREP**. The second **SUBMIT** command queues the procedure **PHASER.COM**. The procedure **PHASER.COM** contains the following line:

```
$ SYNCHRONIZE PREP
```

When this line is processed, the system verifies whether the job named **PREP** exists in the default queue **SY\$BATCH**. The procedure **PHASER** is forced to wait until the job **PREP** completes execution.

2. 

```
$ SUBMIT/NAME=TIMER COMP.COM
Job TIMER (queue SY$BATCH, entry 214) started on queue SY$BATCH
$ SYNCHRONIZE /ENTRY=214
```

In this example, a batch job named **TIMER** is submitted. Then the **SYNCHRONIZE** command is entered interactively. This command places the interactive process in a wait state until entry number 214 (**TIMER**) completes. You cannot enter subsequent commands from your terminal session until the **SYNCHRONIZE** command completes and your process is released from the wait state.

3. 

```
$ SUBMIT/NAME=TIMER COMP.COM/QUEUE=BUILD_QUEUE
$ SYNCHRONIZE/QUEUE=BUILD_QUEUE TIMER
```

The batch job name **TIMER** is submitted to the queue **BUILD\_QUEUE** in this example. Then the **SYNCHRONIZE** command is entered interactively. Because the job named **TIMER** is not in the default queue **SY\$BATCH**, the **SYNCHRONIZE** command includes the **/QUEUE** qualifier to specify the queue in which the job is located.

## TYPE

**TYPE** — Displays the contents of a file or group of files on the current output device.

## Format

**TYPE** *filespec*[,...]

## Parameter

*filespec*[,...]

Specifies one or more files to be displayed. If you specify a file name and not a file type, the file type defaults to .LIS; however, you can specify a different default file type with the TYPE\$DEFAULT\_FILESPEC logical name. The **TYPE** command displays all files that satisfy the file description.

The asterisk (\*) and the percent sign (%) wildcard characters are allowed in place of the directory name, file name, file type, or file version number field. If you specify more than one file, separate the file specifications with commas (,) or plus signs (+). The files are displayed in the order listed.

## Description

When the **TYPE** command displays output, you can control the display in the following ways:

- Press **Ctrl/C** to stop the **TYPE** command for the current file that is being displayed. If you specified only one file with your **TYPE** command, or if the **TYPE** command is displaying the last file in the list, pressing **Ctrl/C** cancels the **TYPE** command. If you have specified more than one file with the **TYPE** command, pressing **Ctrl/C** causes the **TYPE** command to display the next file in the list.
- Press **Ctrl/S** to temporarily suspend the output. Press **Ctrl/Q** to resume the output display at the point of interruption.
- Press **Ctrl/O** to suppress the display but not to suspend the command processing. If you press **Ctrl/O** again before the **TYPE** command terminates, output resumes at the current point in command processing. However, if you press **Ctrl/O** when the **TYPE** command is displaying files in a list, the **TYPE** command suppresses typing the current file and begins typing the next file in the list. This behavior is an exception to normal **Ctrl/O** processing.
- Press **Ctrl/Y** to interrupt the command execution. You can enter the **CONTINUE** command after pressing **Ctrl/Y** to resume displaying the files where the interruption took place, provided you have not entered an intervening command that calls up a new image. If you press **Ctrl/Y** to stop command execution entirely, you can enter the **EXIT** command (or any other DCL command that activates an image) to run down the image.

In addition, the **/PAGE** qualifier may be used to display text one screen at a time.

The **TYPE** command opens the specified file with shared read (R) and write (W) access. Therefore, any file that has its attributes set to shared write is displayed, even if it is currently opened by another user.

You also can use the **TYPE** command to execute a command procedure on a remote node. This is useful on OpenVMS Cluster systems, for example, when you want to display the status of clusterwide services, such as queues, or when you want to display the users logged in to other nodes on the cluster. A sample command procedure follows:

```
$ @ SHOWUSERS.COM
$ if f$mode() .eqs. "NETWORK" then define/user sys$output sys$net
$ show users
```

This command procedure can be used with the **TYPE** command to display at the user's local node the users logged on to the remote node where the command procedure resides.

Specify the command procedure as a parameter to the **TYPE** command as follows:

```
$ TYPE node_name::"TASK=command_procedure"
```

where:

<i>node_name</i>	Specifies the name of the remote node on which the command procedure resides.
<i>command_procedure</i>	Specifies the file name of the command procedure to be run.

This form of the command finds the command procedure in the default DECnet account of the remote node.

To execute a command procedure in the SYS\$LOGIN directory of a particular account, use an access control string in the command, as follows:

```
$ TYPE node_name"user_name password"::"TASK=command_procedure"
```

where:

<i>user_name</i>	Specifies the user name of the account on the remote node.
<i>password</i>	Specifies the password of the account on the remote node.

## Qualifiers

### **/BACKUP**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/BACKUP** qualifier selects files according to the dates of their most recent backups. This qualifier is incompatible with the **/CREATED**, **/EXPIRED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

### **/BEFORE[=*time*]**

Selects only those files dated prior to the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: **BOOT**, **LOGIN**, **TODAY** (default), **TOMORROW**, or **YESTERDAY**. Specify one of the following qualifiers with the **/BEFORE** qualifier to indicate the time attribute to be used as the basis for selection: **/BACKUP**, **/CREATED** (default), **/EXPIRED**, or **/MODIFIED**.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic **Date**.

### **/BY\_OWNER[=*uic*]**

Selects only those files whose owner user identification code (UIC) matches the specified owner UIC. The default UIC is that of the current process.

Specify the UIC by using standard UIC format as described in the relevant section in the [VSI OpenVMS Guide to System Security](https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC_SECTION) [https://docs.vmssoftware.com/vsi-openvms-guide-to-system-security/#UIC\_SECTION].

**/CONFIRM****/NOCONFIRM (default)**

Controls whether a request is issued before each typing operation to confirm that the operation should be performed on that file. The following responses are valid:

YES	NO	QUIT
TRUE	FALSE	<b>Ctrl/Z</b>
1	0	ALL
<b>Return</b>		

You can use any combination of uppercase and lowercase letters for word responses. Word responses can be abbreviated to one or more letters (for example, T, TR, or TRU for TRUE), but these abbreviations must be unique. Affirmative answers are YES, TRUE, and 1. Negative answers include: NO, FALSE, 0, and pressing **Return**. Entering QUIT or pressing **Ctrl/Z** indicates that you want to stop processing the command at that point. When you respond by entering ALL, the command continues to process, but no further prompts are given. If you type a response other than one of those in the list, DCL issues an error message and redisplay the prompt.

**/CONTINUOUS/INTERVAL=*n***

Upon reaching the end of a file, **TYPE** waits a specified number of seconds (the default is 30) then displays any records which have been added to the file and returns to the wait state. **TYPE** continues until either **Ctrl/C** or **Ctrl/Y** is entered by the user.

**/CREATED (default)**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/CREATED** qualifier selects files based on their dates of creation. This qualifier is incompatible with the **/BACKUP**, **/EXPIRED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

**/EXACT**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify a search string that must match the search string exactly and must be enclosed with quotation marks (" ").

If you specify the **/EXACT** qualifier without the **/SEARCH** qualifier, exact search mode is enabled when you set the search string with the Find (**E1**) key.

**/EXCLUDE=(*filespec*[,...])**

Excludes the specified files from the type operation. You can include a directory but not a device in the file specification. The asterisk (\*) and the percent sign (%) wildcard characters are allowed in the file specification; however, you cannot use relative version numbers to exclude a specific version. If you specify only one file, you can omit the parentheses.

**/EXPIRED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/EXPIRED** qualifier selects files according to their expiration dates. (The expiration date is set with the **SET FILE/EXPIRATION\_DATE** command.) The **/EXPIRED** qualifier is incompatible with the

**/BACKUP**, **/CREATED**, and **/MODIFIED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time qualifiers, the default is the **/CREATED** qualifier.

**/HEADER****/NOHEADER**

Specifies whether a header line is placed at the top of each file that is displayed with the **TYPE /PAGE=SAVE** command.

**/HIGHLIGHT[=*keyword*]**

Use with the **/PAGE=SAVE** and **/SEARCH** qualifiers to specify the type of highlighting you want when a search string is found. When a string is found, the entire line is highlighted. You can use the following keywords: **BOLD**, **BLINK**, **REVERSE**, and **UNDERLINE**. **BOLD** is the default highlighting.

**/MODIFIED**

Modifies the time value specified with the **/BEFORE** or the **/SINCE** qualifier. The **/MODIFIED** qualifier selects files according to the dates on which they were last modified. This qualifier is incompatible with the **/BACKUP**, **/CREATED**, and **/EXPIRED** qualifiers, which also allow you to select files according to time attributes. If you specify none of these four time modifiers, the default is the **/CREATED** qualifier.

**/OUTPUT[=*filespec*]****/NOOUTPUT**

Controls where the output of the command is sent. If you specify the **/OUTPUT=*filespec*** qualifier, the output is sent to the specified file, rather than to the current output device, **SY\$OUTPUT**. If you do not enter the qualifier, or if you enter the **/OUTPUT** qualifier without a file specification, the output is sent to **SY\$OUTPUT**.

If you enter the **/OUTPUT** qualifier with a partial file specification (for example, **/OUTPUT=[*VAKHRAMEEV*]**), **TYPE** is the default file name and **.LIS** the default file type. The file specification cannot include the asterisk (\*) and the percent sign (%) wildcard characters.

If you enter the **/NOOUTPUT** qualifier, output is suppressed.

The **/OUTPUT** qualifier is incompatible with the **/PAGE** qualifier.

**/PAGE[=*keyword*]****/NOPAGE (default)**

Controls the display of information on the screen.

You can use the following keywords with the **/PAGE** qualifier:

Keyword	Description
<b>CLEAR_SCREEN</b>	Clears the screen before each page is displayed.
<b>SCROLL</b>	Displays information one line at a time.
<b>SAVE[=<i>n</i>]</b>	Enables screen navigation of information, where <i>n</i> is the number of pages to store.

The **/PAGE=SAVE** qualifier allows you to navigate through screens of information. The **/PAGE=SAVE** qualifier stores up to 5 screens of up to 255 columns of information. When you use the **/PAGE=SAVE** qualifier, you can use the following keys to navigate through the information:

Key Sequence	Description
<b>Up</b> arrow key, <b>Ctrl/B</b>	Scroll up one line.
<b>Down</b> arrow key	Scroll down one line.
<b>Left</b> arrow key	Scroll left one column.
<b>Right</b> arrow key	Scroll right one column.
Find ( <b>E1</b> )	Specify a string to find when the information is displayed.
Insert Here ( <b>E2</b> )	Scroll right one half screen.
Remove ( <b>E3</b> )	Scroll left one half screen.
Select ( <b>E4</b> )	Toggle 80/132 column mode.
Prev Screen ( <b>E5</b> )	Get the previous page of information.
Next Screen ( <b>E6</b> ), <b>Return</b> , <b>Enter</b> , <b>Space</b>	Get the next page of information.
<b>F10</b> , <b>Ctrl/Z</b>	Exit. (Some utilities define these differently.)
Help ( <b>F15</b> )	Display utility help text.
Do ( <b>F16</b> )	Toggle the display to oldest/newest page.
<b>Ctrl/W</b>	Refresh the display.
<b>N</b>	Display the next file (when more than one file is specified with the <b>TYPE</b> command).
<b>Q</b>	Quit displaying output from the <b>TYPE</b> command.

The **/PAGE** qualifier is not compatible with the **/OUTPUT** qualifier.

#### ***/SEARCH="string"***

Use with the **/PAGE=SAVE** qualifier to specify a string that you want to find in the information being displayed. Quotation marks are required for the **/SEARCH** qualifier, if you include spaces in the text string.

You can also dynamically change the search string by pressing the Find key (**E1**) while the information is being displayed. Quotation marks are not required for a dynamic search.

#### ***/SINCE[=time]***

Selects only those files dated on or after the specified time. You can specify time as absolute time, as a combination of absolute and delta times, or as one of the following keywords: **BOOT**, **JOB\_LOGIN**, **LOGIN**, **TODAY** (default), **TOMORROW**, or **YESTERDAY**. Specify one of the following qualifiers with the **/SINCE** qualifier to indicate the time attribute to be used as the basis for selection: **/BACKUP**, **/CREATED** (default), **/EXPIRED**, or **/MODIFIED**.

For complete information on specifying time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic Date.

#### ***/STYLE=keyword***

Specifies the file name format for display purposes while typing files.

The valid keywords for this qualifier are CONDENSED and EXPANDED. Descriptions are as follows:

Keyword	Description
CONDENSED (default)	Displays the file name representation of what is generated to fit into a 255-length character string. This file name may contain a DID or FID abbreviation in the file specification.
EXPANDED	Displays the file name representation of what is stored on disk. This file name does not contain any DID or FID abbreviations.

The keywords CONDENSED and EXPANDED are mutually exclusive. This qualifier specifies which file name format is displayed in the output message, along with the confirmation if requested.

File errors are displayed with the CONDENSED file specification unless the EXPANDED keyword is specified.

See the relevant section in the *VSI OpenVMS User's Manual* [[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE\\_ACCESS](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#FILE_ACCESS)] for more information.

#### **/SYMLINK=keyword**

The valid keywords for this qualifier are [NO]WILDCARD and [NO]ELLIPSIS. Descriptions are as follows:

Keyword	Description
WILDCARD	Indicates that symlinks are enabled during wildcard searches.
NOWILDCARD	Indicates that symlinks are disabled during directory wildcard searches.
ELLIPSIS	Equivalent to WILDCARD (included for command symmetry).
NOELLIPSIS	Indicates that symlinks are matched for all wildcard fields except for ellipsis.

If the file named in the **TYPE** command is a symlink, the command operates on the symlink target.

#### **/TAIL[=n]**

Displays the last several lines of a log file. The value, *n*, defaults to *p*-2 where *p* is the current terminal page length. You can use **TYPE/TAIL** only if all of the following criteria are true:

- File organization is sequential.
- The longest record is less than 512 bytes.
- The record format is either VAR, VFC, STM, STMCR, or STMLF (for more information, see the description of FAB\$B\_RFM in the *VSI OpenVMS Record Management Services Reference Manual* [[https://docs.vmssoftware.com/vsi-openvms-record-management-services-reference-manual/#RMS\\_RECORD\\_FORMAT\\_FIELD](https://docs.vmssoftware.com/vsi-openvms-record-management-services-reference-manual/#RMS_RECORD_FORMAT_FIELD)]).
- The file being typed is on a device that supports random access. The **TYPE/TAIL** command does not work on magnetic tape drives.

Even with this criteria, some file conditions cannot be anticipated and may not allow display of the last several lines of a log file, resulting in the following error message:

```
%TYPE-W-READERR, error reading DEVICE:[DIRECTORY]FILE.EXT;1
-SYSTEM-E-UNSUPPORTED, unsupported operation or function
```

**/WRAP****/NOWRAP (default)**

Use with the **/PAGE=SAVE** qualifier to limit the number of columns to the width of the screen and to wrap lines that extend beyond the width of the screen to the next line.

The **/NOWRAP** qualifier extends lines beyond the width of the screen and can be seen when you use the scrolling (left and right) features provided by the **/PAGE=SAVE** qualifier.

## Examples

1. \$ TYPE COMMON.DAT

In this example, the **TYPE** command requests that the file `COMMON.DAT` be displayed at the terminal.

2. \$ TYPE \*.DAT  
This is the first line in the file AA.DAT.  
.  
.  
.  
Ctrl/O  
This is the first line in the file BB.DAT.  
.  
.  
.  
Ctrl/Y  
Interrupt  
\$ STOP

In this example, the **TYPE** command contains an asterisk (\*) wildcard character in place of the file name. All files with file types of `.DAT` are scheduled for display. When **Ctrl/O** is pressed, output of the current file stops and the **TYPE** command begins displaying the next file. The **Ctrl/Y** function interrupts the command; the **STOP** command terminates the **TYPE** command.

3. \$ TYPE LETTER\*.MEM  
December 14, 2002  
.  
.  
.  
Ctrl/Y  
Interrupt  
\$ SHOW TIME  
14-DEC-2002 15:48:07  
\$ CONTINUE  
Sincerely yours,  
.  
.  
.

In this example, the **TYPE** command displays all files whose names begin with the word `LETTER` and have the file type `.MEM`. While the files are being displayed, the user presses **Ctrl/Y** to interrupt the **TYPE** operation and to display the time. After entering the **SHOW TIME** command, the user enters the **CONTINUE** command to resume the **TYPE** operation.

4. `$ TYPE/OUTPUT=SAVETEXT.TXT *.TXT`

In this example, the **TYPE** command writes all `.TXT` files in your default directory to a file called `SAVETEXT.TXT` (also in your default directory).

5. `$ TYPE MEXICO::NOTICE.TEXT/OUTPUT=TEMP.TEXT`

In this example, the **TYPE** command requests that the file `NOTICE.TEXT` at remote node `MEXICO` be written to the output file `TEMP.TEXT` on the local node, rather than to `SYSS$OUTPUT`.

6. `$ TYPE SECSYS"FILES OFFICEFIL"::"TASK=SHOWUSERS"`

```
VAX/VMS Interactive Users
14-DEC-2002 17:20:13.30
Total number of interactive users = 5
Username      Process Name      PID      Terminal
MIRANDA       Sec1                00536278  TXA1:
JESSICA       Sec2                00892674  VTA2:
EMILY         Sec3                00847326  TXA3:
ANDREW        Sec4                02643859  RTA1:
BRIAN         System Mangr       00007362  VTA1:
```

In this example, the **TYPE** command executes the command procedure `SHOWUSERS.COM` found in the `SYSS$LOGIN` directory of user `FILES` on remote node `SECSYS`. The output of the **TYPE** command then is displayed at the local node.

## UNLOCK

**UNLOCK** — The **UNLOCK** command is obsolete. Use the **SET FILE/UNLOCK** command.

## VIEW

**VIEW** — Invokes the CDA Viewer, which has a character-cell interface for viewing text files and an DECwindows Motif for OpenVMS interface for viewing compound documents and files containing graphics, images, and tabular data.

### Format

**VIEW** [*input-file*]

### Description

For more information about the **VIEW** command, see the online help.

---

### Note

The DEC CDA Base Services for DECwindows Motif for OpenVMS must be installed to use new versions of the CDA Viewer and DEC CDA Base Services converters.

---

# WAIT

**WAIT** — Places a process into a wait state for the specified amount of time. The **WAIT** command is used in a command procedure to delay processing of either the procedure itself or a set of commands in the procedure.

## Format

**WAIT** *delta-time*

## Parameter

*delta-time*

Specifies a delta time interval in the following format. (A delta time is an offset from the current time to a time in the future.)

*hour:minute:second.hundredth*

The fields on the format line indicate the following:

<i>hour</i>	Specifies an integer in the range 0 to 23.
<i>minute</i>	Specifies an integer in the range 0 to 59.
<i>second</i>	Specifies an integer in the range 0 to 59.
<i>hundredth</i>	Specifies an integer in the range 0 to 99.

The colons (:) and period (.) are required delimiters; also, the delta time must begin with the number of hours and not a colon. Note that the days field, usually included in the delta time format, must be omitted here.

For more information on specifying delta time values, see the relevant section in the [VSI OpenVMS User's Manual](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE_AND_TIME_SECT) [https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#DATE\_AND\_TIME\_SECT] or the online help topic Date.

Note that if you enter the **WAIT** command interactively, you are not prompted for a time value; however, in order for the command to have any effect, you must supply a time value.

## Description

If you enter the **WAIT** command interactively, your current process is placed in a wait state and you cannot enter any more commands until the waiting period is over. (You can, however, receive unsolicited messages from other processes.) Press **Ctrl/C** or **Ctrl/Y** to restore normal terminal interaction.

## Example

```
$ LOOP:
$ RUN KUDOS
$ WAIT 00:10
$ GOTO LOOP
```

In this example, the command procedure executes the program image KUDOS. After the **RUN** command executes the program, the **WAIT** command delays execution of the **GOTO** command for 10 minutes. Note that 00 is specified for the number of hours, because the time specification cannot begin with a

colon. After 10 minutes, the **GOTO** command executes, and the procedure transfers control to the label **LOOP** and executes the program **KUDOS** again. The procedure loops until it is interrupted or terminated.

If the procedure is executed interactively, terminate it by pressing **Ctrl/C** or **Ctrl/Y** and by entering the **STOP** command or another DCL command that runs a new image in the process. If the procedure is executed in a batch job, enter the **DELETE/ENTRY** command to terminate it.

## WRITE

**WRITE** — Writes the specified data as one record to an open file specified by a logical name. All qualifiers must precede all data item expressions.

### Format

**WRITE** *logical-name expression[,...]*

### Parameters

#### *logical-name*

Specifies the logical name assigned to the output file. Use the logical name assigned by the **OPEN** command. In interactive mode, specify the process-permanent files identified by the logical names **SYSS\$INPUT**, **SYSS\$OUTPUT**, **SYSS\$ERROR**, and **SYSS\$COMMAND**. (The **OPEN** command assigns a logical name to a file and places the name in the process logical name table.)

#### *expression[,...]*

Specifies data to be written as a single record to the output file. You can specify data items using character string expressions, which may be symbol names, character strings in quotation marks (" "), literal numeric values, or a lexical function. For more information on string expressions, see the relevant section in the [VSI OpenVMS User's Manual \[https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#SYMB\\_BLK24\]](https://docs.vmssoftware.com/vsi-openvms-user-s-manual/#SYMB_BLK24).

You can specify a list of expressions separated by commas (,); the command interpreter concatenates the items into one record and writes the record to the output file.

The maximum size of any record that can be written is less than 1024 bytes, and the value of any symbol that is specified as part of a record cannot exceed 255 characters; however, if you specify the **/SYMBOL** qualifier, the maximum record size is 2048 bytes and the value of a symbol can exceed 255 characters.

## Description

The **WRITE** command can write records to sequential, relative, or indexed files that have been opened for writing. When the **WRITE** command writes a record, it always positions the record pointer after the record just written.

To write to a file, the file must be opened by using either the **/WRITE** or the **/APPEND** qualifier with the **OPEN** command; however, the process-permanent files identified by the logical names **SYSS\$INPUT**, **SYSS\$OUTPUT**, **SYSS\$ERROR**, and **SYSS\$COMMAND** do not have to be opened explicitly to be written to.

If you do not specify the **/SYMBOL** qualifier, DCL places the command and the complete string expression (expanded if it was specified as one or more symbols) in a 1024-byte buffer. If you specify the **/SYMBOL** qualifier, DCL interprets the symbol or symbols and places the expanded string in a

separate 2048-byte buffer, and then performs the write operation. For this reason, use the **/SYMBOL** qualifier where the record contains approximately 1000 bytes or more.

## Qualifiers

### ***/ERROR=label***

Transfers control on an I/O error to the location specified by *label* (in a command procedure). If no error routine is specified and an error occurs during the writing of the file, the current ON condition action is taken. The **/ERROR** qualifier overrides any ON condition action specified. If an error occurs and control passes successfully to the target label, the reserved global symbol \$STATUS retains the error code.

### ***/SYMBOL***

Causes the expression to be interpreted and its expanded value placed in a 2048-byte (instead of a 1024-byte) buffer before the write operation is performed. If you specify multiple expressions, their values are concatenated and placed in the 2048-byte buffer. Use the **/SYMBOL** qualifier to write a very large record.

If you do not use the **/SYMBOL** qualifier, the entire command, including the expression or expressions, is placed in a 1024-byte buffer.

### ***/UPDATE***

Replaces the last record read with the record specified with the expression parameter. You must be able to read and write to a file to use the **/UPDATE** qualifier. Use the **WRITE/UPDATE** command only after a **READ** command. The **WRITE/UPDATE** command modifies the last record you have read.

With sequential files, you must replace a record with another record of the same size when you use the **WRITE/UPDATE** command.

### ***/WAIT (default)***

### ***/NOWAIT***

If you specify **/NOWAIT**, the Put service to a mailbox device uses the IO\$M\_NOW modifier, which causes the operation to complete immediately instead of synchronizing with another reader of the mailbox.

Currently this qualifier is supported on Alpha and Integrity servers only.

## Examples

1. 

```
$ WRITE SYS$OUTPUT "Beginning second phase of tests"
```

The **WRITE** command writes a single line of text to the current output device.

2. 

```
$ OPEN/APPEND OUTPUT_FILE TRNTO::DKA1:[PGM]PLAN.DAT
$ WRITE OUTPUT_FILE "BEGINNING PHASE 3"
```

In this example, the **OPEN/APPEND** command opens the file `PLAN.DAT` at the remote node `TRNTO` and positions the pointer at the end of the file. The **WRITE** command writes a record to the end of the file `PLAN.DAT`.

3. 

```
$ OPEN/WRITE OUTPUT_FILE TESTFILE.DAT
$ INQUIRE ID "Assign Test-id Number"
```

```
$ WRITE/ERROR=WRITE_ERROR OUTPUT_FILE "Test-id is ",ID
$ WRITE/ERROR=WRITE_ERROR OUTPUT_FILE ""
$ !
$ WRITE_LOOP:
.
.
.
$ GOTO WRITE_LOOP
$ END_LOOP:
$ !
$ CLOSE OUTPUT_FILE
$ PRINT TESTFILE.DAT
$ EXIT
$ !
$ WRITE_ERROR:
$ WRITE SYS$OUTPUT "There was a WRITE error."
$ CLOSE OUTPUT_FILE
$ EXIT
```

In this example, the **OPEN** command opens the file `TESTFILE.DAT`; the **INQUIRE** command requests an identification number to be assigned to a particular run of the procedure. The number entered is equated to the symbol `ID`. The **WRITE** commands write a text line concatenated with the symbol name `ID` and a blank line.

The lines between the label `WRITE_LOOP` and `END_LOOP` process information and write additional data to the file. When the processing is finished, control is transferred to the label `END_LOOP`. The **CLOSE** and **PRINT** commands at this label close the output file and queue a copy of the file to the system printer.

The label `WRITE_ERROR` is used as the target of the **/ERROR** qualifier to the **WRITE** command; if an error occurs when a record is being written, control is transferred to the label `WRITE_ERROR`.

4. 

```
$ OPEN/APPEND MYFILE [LAMPERT]TESTING.DAT
$ WRITE/SYMBOL MYFILE A,B,C
```

This example assumes that the symbols `A`, `B`, and `C` have already been defined. The **OPEN/APPEND** command opens the file `[LAMPERT]TESTING.DAT` and positions the pointer at the end of the file. The **WRITE/SYMBOL** command concatenates the values of the symbols `A`, `B`, and `C` and writes this data to a new record at the end of the file.

## XAUTH (Alpha/Integrity servers Only)

**XAUTH (Alpha/Integrity servers Only)** — Invokes the X Authority utility (`xauth`) that you can use to manage the contents of one or more X authority files. The X authority file contains information used to authorize client connections to the X display server.

### Format

```
XAUTH [-f authfile] [-options...] [command]
```

### Description

This utility is typically used to extract authorization records from one system and combine them with the records on another system, such as when granting access to additional users or enabling remote logins. The actual record entries vary depending on the authorization scheme currently in use.

In contrast to other X Window System utilities that are available with DECwindows Motif, xauth is included as a part of OpenVMS Alpha and OpenVMS Integrity servers operating systems. The xauth commands are case-insensitive and available directly from the DCL command line, xauth command line, or from a batch file.

For a complete description of xauth, see the DECwindows Motif documentation or the xauth online help.



# Appendix A. Obsolete Commands

Table A.1, "Obsolete Commands" lists the obsolete DCL commands and the current services that replace them.

**Table A.1. Obsolete Commands**

Obsolete Command	Replaced by
SET ACL	SET SECURITY/ACL
SET PROTECTION	SET SECURITY/PROTECTION
SET PROTECTION/DEVICE	SET SECURITY/PROTECTION/CLASS=DEVICE
SET UIC	Not replaced.
SHOW ACL	SHOW SECURITY
UNLOCK	SET FILE/UNLOCK



# Appendix B. Handling Numeric Values Outside the Range of DCL Integer Representation

## B.1. Preface

The OpenVMS Version 8.4 release introduces support for storage devices up to 1.98 TB in size. For customers and products that will use devices over 1 TB, some changes to DCL procedures are necessary to keep them functioning properly. If you do not plan to use storage devices over 1 TB in size, there is likely no need to change any of your DCL code related to reading or changing disk values.

The document is mainly intended to address issues with large disks but the methods used are not specific to the large disk support project.

## B.2. Introduction

Herein are some DCL examples handling retrieval and arithmetic on integer values that lie outside the DCL symbol integer limits. The document concentrates on processing values returned from the DCL \$GETDVI lexical function. The examples can be used as guidelines for your specific needs. Examples are not warranted or guaranteed to meet any specific requirement. Examples center on handling disk storage size and free storage measurement but methodologies can be more generally applied.

The example procedures are designed to clearly demonstrate the methodology. The specific operations may be more efficiently performed by complex single statement DCL commands. The document chooses ease of reading over efficiency in the examples.

### B.2.1. Problem Statement

OpenVMS system configuration and management procedures can update or monitor almost all possible system resource values with signed 32-bit longword integers. Over a period of time, a number of resource value maximums moved beyond the signed longword limit. For example, the number of virtual memory pages available to a process on OpenVMS Alpha and Integrity server systems require 64-bit integer storage for the maximum value. Unfortunately, the DCL command language stores and performs arithmetic only on 32-bit signed longwords. From the "OpenVMS User's Manual Chapter 12, Defining Symbols, Commands and Expressions":

"12.7.2 Internal Storage of Numbers

Numbers are stored internally as signed 4-byte integers, called longwords; positive numbers have values of 0 to 2147483647 and negative numbers have values of 4294967296 minus the absolute value of the number. The number -15237, for example, is stored as 4294952059. Negative numbers are converted back to minus-sign format for ASCII or decimal displays; however, they are not converted back for hexadecimal and octal displays. For example, the number -15237 appears in displays as hexadecimal FFFFC47B (decimal 4294952059) rather than hexadecimal --00003B85. "

This DCL behavior poses problems for scripts monitoring and modifying large valued resource settings on OpenVMS systems. OpenVMS version V8.4 will introduce support for large disks, up to 1.98 terabytes. We expect many DCL procedures will be adversely affected as disk block counts will now exceed the signed maximum value and appear as negative numbers in DCL integer symbols. The

F\$GETDVI lexical function items MAXBLOCK, FREEBLOCKS, EXPSIZE and VOLSIZE are typically used to return disk information. All of these F\$GETDVI items may return negative numbers on V8.4.

## B.2.2. Prerequisites

A moderate knowledge of DCL programming is required. Availability of a disk sized over 1 TB.

## B.3. DCL Examples

Some examples and procedures are included in this section to demonstrate ways to perform range checks and percentage calculations in Version 8.4 on systems with large disks.

### B.3.1. DCL code checking a value in range 0 to 2147483647

A simple method to check for a minimum value or a range with a maximum value less than 2147483647 is demonstrated here.

change:

```
IF F$GETDVI(device,"FREEBLOCKS") .GT. 100000
THEN
    ...
```

to:

```
IF F$GETDVI(device,"FREEBLOCKS") .LT. 0 .OR. -
    F$GETDVI(device,"FREEBLOCKS") .GT. 100000
THEN
    ...
```

### B.3.2. DCL code checking a value in range 0 to 4294967295

One method to check a range or size value exceeding the signed longword maximum is to convert the values to zero filled ASCII strings. After the conversion the DCL string logical operators can be used to perform the comparison.

```
$! Begin Example
$!
$ disk = P1
$ if disk .EQS. "" then disk = "SYS$LOGIN_DEVICE"
$ length      = f$length("4294967296") ! string length of 2TiB in blocks
$ maxblocks   = f$fao("!'length'ZL",F$GETDVI(disk,"MAXBLOCK"))
$ freeblocks  = f$fao("!'length'ZL",F$GETDVI(disk,"FREEBLOCKS"))
$ expsize     = f$fao("!'length'ZL",F$GETDVI(disk,"EXPSIZE"))
$ volsize     = f$fao("!'length'ZL",F$GETDVI(disk,"VOLSIZE"))
$ MinBlocks   = f$fao("!'length'ZL",500000)
$!
$ write sys$output "Results for Freeblocks='freeblocks' .comparison.
    MinBlocks='MinBlocks'"
$ write sys$output ".eqs. " + F$string((freeblocks .eqs. MinBlocks))
$ write sys$output ".nes. " + F$string((freeblocks .nes. MinBlocks))
$ write sys$output ".les. " + F$string((freeblocks .les. MinBlocks))
```

```
$ write sys$output ".ges. " + F$string((freeblocks .ges. MinBlocks))
$ write sys$output ".lts. " + F$string((freeblocks .lts. MinBlocks))
$ write sys$output ".gts. " + F$string((freeblocks .gts. MinBlocks))
$ write sys$output ""
$ write sys$output "Results for maxblocks='maxblocks' .comparison.
    volsize='volsize'"
$ write sys$output ".eqs. " + F$string((maxblocks .eqs. volsize))
$ write sys$output ".nes. " + F$string((maxblocks .nes. volsize))
$ write sys$output ".les. " + F$string((maxblocks .les. volsize))
$ write sys$output ".ges. " + F$string((maxblocks .ges. volsize))
$ write sys$output ".lts. " + F$string((maxblocks .lts. volsize))
$ write sys$output ".gts. " + F$string((maxblocks .gts. volsize))
$!
$! End example
```

### B.3.3. Checking the percentage of free blocks on a disk

Common disk management operations include calculating the unused percentage of a disk or determining if there is sufficient free space on the target disk for a copy or backup. This section provides examples on handling these particular functions on large disks.

One approach is to assume that any negative value returned on a FREEBLOCKS check means that there are sufficient free blocks to perform whatever storage operation you require.

```
IF F$GETDVI(device,"FREEBLOCKS") .LT. 0 THEN GOTO SUCCESS
```

This example demonstrates how to check if the system device has at least 5% free blocks. It calls a subroutine PERCENT\_FREE to perform the check. The subroutine scales the disk values so signed arithmetic can be performed.

```
$! begin Example
$!
$ percent_free == -1
$!
$ CALL percent_free "sys$sysdevice"
$ IF $status .AND. percent_free .gt. 0
$ then
$   if percent_free .ge. 5
$   then
$     write sys$output "Sufficient freeblocks on disk"
$   else
$     write sys$output "Warning Insufficient freeblocks on disk"
$   endif
$ else
$ write sys$output "Problem obtaining information for disk"
$ endif
$!
$ EXIT
$
$!
$   percent_free: subroutine
$ !
$ !   This subroutine will return, as an integer, the percentage of free
$ !   disk blocks for a given volume. The percentage free is given by:
$ !
$ !           (number of free blocks on the volume)
$ !   Percentage Free = ----- * 100
$ !                       (volume size in blocks)
$ !
```

```
$ !
$ !   The volume name is passed in P1 and the result is returned in the
$ !   global symbol PERCENT_FREE.  For example:
$ !
$ !       $ call percent_free "disk$test"
$ !       $ write sys$output "Free space is ", percent_free, "%"
$ !
$ !   Since DCL does signed 32 bit arithmetic, all calculations and results
$ !   are done with the sign bit (bit 31) clear.  So, for values of free
$ !   blocks and volume size larger than %x7FFFFFFF, first clear the sign
$ !   bit, divide by two (shift right one bit) and then turn on bit 30.
$ !
$       freeblocks = f$getdvi(p1,"freeblocks")
$       volsize = f$getdvi(p1,"volsize")
$ !
$       if (freeblocks .lt. 0)
$           then pipe freeblocks[31,1] = 0 ; freeblocks = freeblocks / 2 ;
$           freeblocks[30,1] = 1
$       else freeblocks = freeblocks / 2
$       endif
$ !
$       if (volsize .lt. 0)
$           then pipe volsize[31,1] = 0 ; volsize = volsize / 2 ; volsize[30,1] =
1
$       else volsize = volsize / 2
$       endif
$ !
$       if ((volsize / 100) .gt. 0)
$           then percent_free == freeblocks / (volsize / 100)
$       else percent_free == 0
$       endif
$ !
$   endsubroutine
```

### B.3.4. F\$CUNITS() lexical function description

The pre V8.4 F\$CUNITS() lexical function allowed conversion of a value of blocks to the corresponding value of bytes. The output of the lexical was automatically scaled to KB, MB, and so on depending upon the size of the resultant value. In Version 8.4 the lexical is enhanced to support bytes to blocks conversions. Additional units keyword values are introduced to allow the user to specify the resultant value scaling. The format of a F\$CUNITS lexical call is:

```
result = F$CUNITS(value, from-units, to-Units)
```

where:

value: a value in the range 1 to 4294967295

Pre V8.4:

```
from-units:  "BLOCKS"  ! optional, default is BLOCKS
to-units:    "BYTES"   ! optional, default resultant BYTES are autoscaled
```

V8.4:

```
from-units:  unit      ! optional, default is BLOCKS
to-units:    unit      ! optional, default resultant BYTES are autoscaled
```

where unit is one of:

```
"BYTES", "BLOCKS", "KB", "MB", "GB", "TB"
```

For large disks it may be more convenient to work or display values in units other than blocks.

The next example demonstrates usage of the F\$CUNITS function to convert blocks to bytes. It calculates the percent of free disk space while exercising the F\$CUNITS lexical. The example also contains an easy method to approximate the percentage.

```
$!
$ if p1 .nes. "" Then GOTO show_device_info
$ thisproc = f$environment("procedure")
$Loop:
$ disk = F$DEVICE("*, "DISK")
$ if disk .eqs. "" then EXIT
$ @'thisproc' 'disk'
$ goto Loop
$show_device_info:
$! Example:
$!
$!   Demonstrate the use of the F$CUNITS() lexical and
$!   calculate the percent free of a disk
$!
$ disk = P1
$ if P1 .eqs. "" then disk = "sys$sysdevice"
$ if .NOT. ( f$getdvi(disk, "EXISTS") .AND. -
            f$getdvi(disk, "AVL") .AND. -
            f$getdvi(disk, "MNT") ) then EXIT
$ write sys$output "Results for disk : 'disk'"
$ line = f$fao("!4(16AS)", "Units", "Total", "FREE", "Percent")
$ write sys$output line
$!
$! do direct calculation or approximation first (BLOCKS)
$!
$ TotalSize = f$fao("!UL", f$getdvi(disk, "MAXBLOCK"))
$ FreeSize = f$fao("!UL", f$getdvi(disk, "FREEBLOCKS"))
$ TotalDisplay = TotalSize
$ FreeDisplay = FreeSize
$ if f$length(TotalSize) .lt. 7 then GOTO No_approximation
$ TotalSize = f$extract(0, 7, f$fao("!10ZL", f$getdvi(disk, "MAXBLOCK")))
$ FreeSize = f$extract(0, 7, f$fao("!10ZL", f$getdvi(disk, "FREEBLOCKS")))
$!
$No_approximation:
$ uindex = -1
$ units = "BLOCKS, KB, MB, GB, TB"
$!
$! show approximation
$!
$ unit = "Approx"
$!
$ GOTO Compute_Percent
$!
$Fcunits_display:
$!
$Get_Unit:
$!-----
$ unit = f$element(uindex, "", units)
$ if unit .eqs. "" then EXIT
$!
```

```
$ TotalSize = f$cunits(f$string(f$fao("!UL",f
$getdvi(disk,"MAXBLOCK"))),"BLOCKS",unit) - "'unit'"
$ FreeSize = f$cunits(f$string(f$fao("!UL",f
$getdvi(disk,"FREEBLOCKS"))),"BLOCKS",unit) - "'unit'"
$!
$ TotalDisplay = TotalSize
$ FreeDisplay = FreeSize
$!
$! for unit >= gigabytes retain the fractional value
$!
$ if uindex .lt. 4 then goto Edit_Units_002
$!
$ if f$locate(".",TotalSize) .eq. f$length(TotalSize)
$ then
$     TotalSize = TotalSize + "00"
$ else
$     TotalSize = TotalSize - "."
$ endif
$ if f$locate(".",FreeSize) .eq. f$length(FreeSize)
$ then
$     FreeSize = FreeSize + "00"
$ else
$     FreeSize = FreeSize - "."
$ endif
$!
$ GOTO Compute_Percent
$!
$Edit_Units_002:
$!
$! For units < Gigabytes truncate any fraction
$!
$ if f$locate(".",TotalSize) .lt. f$length(TotalSize)
$ then
$     TotalSize = f$extract(0,f$length(TotalSize)-3,TotalSize)
$ endif
$!
$ if f$locate(".",FreeSize) .lt. f$length(FreeSize)
$ then
$     FreeSize = f$extract(0,f$length(FreeSize)-3,FreeSize)
$ endif
$!
$Compute_Percent:
$!
$! check for overflow on percentage calculation
$!
$ PCTfree = -1
$ if (((f$integer(FreeSize)*100)/100) .ne. f$integer(FreeSize)) .OR. -
    f$length(FreeSize) .gt. 8 .OR f$length(TotalSize) .gt. 8
$ then
$     PCTfree = "Overflow"
$ else
$     if TotalSize .eq. 0 .OR. FreeSize .eq. 0
$     then
$         PCTfree = 0
$     else
$         PCTfree = f$integer( (FreeSize*100) / TotalSize)
$     endif
$ endif
```

```
$!  
$ line = f$fa0("!4(16AS)",Unit, TotalDisplay, FreeDisplay, f  
$string(PCTfree))  
$ write sys$output line  
$!  
$ uindex = uindex + 1  
$ GOTO Get_Unit  
$!  
$ EXIT  
$!
```

#### B.4 Identifying Suspect DCL Code

This section describes some ways to identify DCL code and source code modules that may not function correctly when accessing devices over 1TB size.

##### B.4.1 DCL Code Search Example

This example demonstrates a simple search to identify DCL code lines that definitely need to be addressed. DCL code may supply lexical items as symbols or split lexical calls into multiple lines and this procedure will not identify such cases.

```
$ search := search/numbers/wind=1/MATCH=AND/statistics  
$ filespec = 'your_filespec'  
$!  
$! The results of the search command on the next 3 lines  
$! show DCL command lines that MUST be addressed on systems  
$! accessing disks over 1tb.  
$ search 'filespec' "F$GETDVI","MAXBLOCK"  
$ search 'filespec' "F$GETDVI","VOLSIZE"  
$ search 'filespec' "F$GETDVI","EXPSIZE"  
$!  
$! The results of the search command on the next line  
$! show DCL command lines that should be changed on  
$! systems accessing disks over 1tb.  
$! The DCL command is likely to return a value that will  
$! not fit in a signed longword.  
$ search 'filespec' "F$GETDVI","FREEBLOCKS"
```

## B.4. Identifying Suspect DCL Code

This section describes some ways to identify DCL code and source code modules that may not function correctly when accessing over 1 TB devices.

### B.4.1. DCL Code Search Example

This example demonstrates a simple search to identify DCL code lines that definitely need to be addressed. DCL code may supply lexical items as symbols or split lexical calls into multiple lines and this procedure will not identify such cases.

```
$ search := search/numbers/wind=1/MATCH=AND/statistics  
$ filespec = 'your_filespec'  
$!  
$! The results of the search command on the next 3 lines  
$! show DCL command lines that MUST be addressed on systems  
$! accessing disks over 1tb.  
$ search 'filespec' "F$GETDVI","MAXBLOCK"
```

```
$ search 'filespec' "F$GETDVI","VOLSIZE"
$ search 'filespec' "F$GETDVI","EXPSIZE"
$!
$! The results of the search command on the next line
$! show DCL command lines that should be changed on
$! systems accessing disks over 1tb.
$! The DCL command is likely to return a value that will
$! not fit in a signed longword.
$ search 'filespec' "F$GETDVI","FREEBLOCKS"
```