



VMS Software

# VSI Apache Web Server 2.4-65 (based on Apache HTTP Server) Release Notes

**Publication Date:** September 2025

**Operating Systems:** VSI OpenVMS Alpha Version 8.4-2L2 or higher  
VSI OpenVMS IA-64 Version 8.4-2L1 or higher  
VSI OpenVMS x86-64 Version 9.2-3 or higher

**Kit Names:** VSI-AXPVMS-APACHEWS-V0204-65-1.PCSI  
VSI-I64VMS-APACHEWS-V0204-65-1.PCSI  
VSI-X86VMS-APACHEWS-V0204-65-1.PCSI

## Table of Contents

1. Introduction .....	3
2. Apache HTTP Server Documentation .....	3
3. Summary of New Features in V2.4-65 .....	3
4. Important Changes .....	5
4.1. Fixed Vulnerability Issues .....	8
5. Known Issues and Restrictions in V2.4 .....	8
6. Requirements .....	9
7. Before Beginning the Installation .....	10
8. Installing APACHEWS .....	11
9. Configuring the Web Server .....	13
10. Enabling and Disabling SSL .....	14
11. Building Dynamically Loadable Modules .....	15

# 1. Introduction

VMS Software Inc. (VSI) are pleased to provide you with a new VSI-supported version of Secure Web Server for OpenVMS. This release of Secure Web Server for OpenVMS is based on Apache HTTP Server Version 2.4.65 from the Apache Software Foundation and represents a significant update from previous versions, providing many new features and numerous enhancements. Enhancements include reduced memory utilization and more flexible configuration, and there are a variety of new loadable modules providing new and enhanced functionality in areas such as session management, request filtering, and rate limiting. Secure Web Server for OpenVMS Version 2.4 also provides improved support for the development of custom loadable modules.

For a detailed description of new features and enhancements in Apache HTTP Server 2.4, please refer to [http://httpd.apache.org/docs/2.4/new\\_features\\_2\\_4.html](http://httpd.apache.org/docs/2.4/new_features_2_4.html) (note that not all new features are provided in the version for OpenVMS). For a description of changes and enhancements specific to the 2.4.65 release, see [https://downloads.apache.org/httpd/CHANGES\\_2.4.65](https://downloads.apache.org/httpd/CHANGES_2.4.65).

## 2. Apache HTTP Server Documentation

For information about the Apache web server, see the Apache HTTP Server Version 2.4 documentation at <https://httpd.apache.org/docs/2.4/>.

After installing the APACHEWS on your OpenVMS system you can also view the web server documentation at <http://your.hostname/manual>, where *your.hostname* is that server host name (or IP address) and port number applicable to your installation.

## 3. Summary of New Features in V2.4-65

This release of APACHEWS for OpenVMS is based on Apache HTTP Server Version 2.4.65 from the Apache Software Foundation and includes Secure Sockets Layer (SSL) MOD\_SSL and OpenSSL based on OpenSSL 3.0.13. Accordingly, this release of APACHEWS for OpenVMS supports higher levels of encryption than those provided by previous versions, ensuring greater levels of security for clients connecting to your web server on OpenVMS. This release also includes various minor fixes as described in [https://downloads.apache.org/httpd/CHANGES\\_2.4.65](https://downloads.apache.org/httpd/CHANGES_2.4.65) and elsewhere in this document, along with the following new functionality:

- The module MOD\_PROXY was updated to support single-threaded builds.
- The OpenVMS-specific authentication module MOD\_AUTHNZ\_OPENVMS can now optionally authenticate users (username and password) using the SYS\$ACMW system service, thereby making it possible to authenticate OpenVMS users that are configured to use ACME LDAP or similar providers for user authentication. In order to enable this facility, it is necessary to define the logical name APACHE\$AUTH\_USE\_ACM (to anything) in LOGIN.COM for the web server account.
- LDAP-related modules now use the new OpenLDAP client API, providing better security and enhanced functionality. It should be noted that these modules are statically linked with the OpenLDAP client libraries, and it is therefore not necessary to install OpenLDAP for VSI OpenVMS in order to make use of this new feature.
- The module MOD\_SOCACHE\_REDIS is included in this release, allowing the high-performance Redis object cache to be used for caching various data such as SSL session information. Redis may be installed on the same OpenVMS system as the web server or reside on another server that is accessible from the system hosting the web server.

- The module MOD\_WSGI is included in this release, and can be used in conjunction with Python 3.10 for VSI OpenVMS to create powerful Python-based web applications using the WSGI (Web Server Gateway Interface) framework. It should be noted that the MOD\_WSGI module is available only for Integrity at this time.

For a full list of new features and new and changed modules in Apache HTTP Server Version 2.4.65, see [https://httpd.apache.org/docs/2.4/new\\_features\\_2\\_4.html](https://httpd.apache.org/docs/2.4/new_features_2_4.html). This release also addresses various security-related CVE's and other such matters. For a complete list of these changes, see [http://www.apache.org/dist/httpd/CHANGES\\_2.4](http://www.apache.org/dist/httpd/CHANGES_2.4).

Note that not all of the new modules are provided with APACHEWS for OpenVMS. The list of modules provided with this release of APACHEWS is as follows:

MOD_ACCESS_COMPAT	MOD_ACTIONS
MOD_ALIAS	MOD_ALLOWMETHODS
MOD_ASIS	MOD_AUTHNZ_LDAP
MOD_AUTHNZ_OPENVMS	MOD_AUTHN_ANON
MOD_AUTHN_CORE	MOD_AUTHN_DBD
MOD_AUTHN_DBM	MOD_AUTHN_FILE
MOD_AUTHN_SOCACHE	MOD_AUTHZ_CORE
MOD_AUTHZ_DBD	MOD_AUTHZ_DBM
MOD_AUTHZ_GROUPFILE	MOD_AUTHZ_HOST
MOD_AUTHZ_OWNER	MOD_AUTHZ_USER
MOD_AUTH_BASIC	MOD_AUTH_DIGEST
MOD_AUTH_FORM	MOD_AUTOINDEX
MOD_BUFFER	MOD_CACHE
MOD_CACHE_DISK	MOD_CACHE_SOCACHE
MOD_CERN_META	MOD_CGI
MOD_CHARSET_LITE	MOD_DAV
MOD_DAV_FS	MOD_DBD
MOD_DEFLATE	MOD_DIR
MOD_DUMPIO	MOD_ECHO
MOD_ENV	MOD_EXPIRES
MOD_EXT_FILTER	MOD_FILE_CACHE
MOD_FILTER	MOD_HEADERS
MOD_INCLUDE	MOD_INFO
MOD_ISAPI	MOD_LBMETHOD_BYBUSYNESS
MOD_LBMETHOD_BYREQUESTS	MOD_LBMETHOD_BYTRAFFIC
MOD_LBMETHOD_HEARTBEAT	MOD_LDAP
MOD_LOGIO	MOD_LOG_CONFIG
MOD_LOG_DEBUG	MOD_MACRO
MOD_MIME	MOD_MIME_MAGIC
MOD_NEGOTIATION	MOD_OSUSCRIPT

MOD_PROXY	MOD_PROXY_AJP
MOD_PROXY_BALANCER	MOD_PROXY_CONNECT
MOD_PROXY_EXPRESS	MOD_PROXY_FCGI
MOD_PROXY_FTP	MOD_PROXY_HTTP
MOD_PROXY_SCGI	MOD_PROXY_WSTUNNEL
MOD_RATELIMIT	MOD_REMOTEIP
MOD_REQTIMEOUT	MOD_REQUEST
MOD_REWRITE	MOD_SED
MOD_SESSION	MOD_SESSION_COOKIE
MOD_SESSION_DBD	MOD_SETENVIF
MOD_SLOTMEM_SHM	MOD_SOCACHE_DBM
MOD_SOCACHE_MEMCACHE	MOD_SOCACHE_REDIS
MOD_SOCACHE_SHMCB	MOD_SPELING
MOD_SSL	MOD_STATUS
MOD_SUBSTITUTE	MOD_SUEXEC
MOD_UNIQUE_ID	MOD_UNIXD
MOD_USERDIR	MOD_USERTRACK
MOD_VERSION	MOD_VHOST_ALIAS
MOD_WSGI <sup>1</sup>	

<sup>1</sup>OpenVMS IA-64 with Python 3.8.2F only.

For details on how to configure and use these modules, refer to the documentation provided on the Apache HTTP Server web site at <https://httpd.apache.org/docs/2.4/mod/>.

## 4. Important Changes

This section summarises important differences between this release of the APACHEWS for OpenVMS and previous versions.

- Changes are required in HTTPD.CONF when upgrading from previous versions.

In APACHEWS Version 2.4, some dynamically loadable modules provided with previous releases are no longer available or are not loaded by default.

You must uncomment the modules in HTTPD.CONF to load them. To load other modules, see the file HTTPD-VMS.CONF.

- Removal of AcceptMutex and related directives

In pre-2.4 versions of Apache HTTPD, the AcceptMutex directive was used in HTTPD.CONF to specify the method used by the web server to serialize multiple child processes accepting requests on network sockets. In version 2.4, the AcceptMutex, LockFile, RewriteLock, SSLMutex, SSLStaplingMutex, and WatchdogMutexPath directives have been replaced with a single Mutex directive (for details, refer to <https://httpd.apache.org/docs/2.4/mod/core.html#mutex>).

With previous versions of the APACHEWS for OpenVMS, the value vmsd1m could be specified for AcceptMutex to instruct the web server to use the OpenVMS Distributed Lock Manager to

coordinate access to network sockets and other shared resources. For version 2.4 of the APACHEWS for OpenVMS, the Distributed Lock Manager is always used to coordinate access to network sockets and does not need to be explicitly specified unless using the DBM or shared memory cache modules, MOD\_SOCACHE\_DBM and MOD\_SOCACHE\_SHMCB, respectively.

Other permitted (non-default) values for the `Mutex` directive are:

**sem**

Causes the web server to use semaphores for coordination of access to shared resources.

**flock:/path/to/lockfile**

Instructs the web server to use file-based locking for coordination (where `/path/to/lockfile` is the directory where lock files will be created, specified in UNIX syntax).

Note that if no `Mutex` type is defined and you attempt to use any modules that require a `Mutex` to be defined, the web server will silently fail to start. It is therefore recommended that you always define a `Mutex`, even if you do not currently make use of it.

- Changes to OpenVMS authentication module

The authentication and authorization module used by Apache HTTP Server version 2.4 differs from that of previous versions. In version 2.4, it is necessary to register the specific authentication (or authorization) provider that you wish to use for a particular directory or location. This way it is possible to configure and use different providers with different directories or locations.

The following example illustrates use of the OpenVMS authentication provider for the `/test` directory:

```
<Directory /test>
  Options FollowSymLinks
  AllowOverride AuthConfig
  AuthType Basic
  AuthName "OpenVMS authentication"
  AuthBasicProvider OpenVMS
  require valid-user
</Directory>
```

We have specified an `AuthBasicProvider` of `OpenVMS` (note that the name of the provider is case-sensitive). This causes the authentication infrastructure to use the OpenVMS password checking module (included in `MOD_AUTHNZ_OPENVMS.EXE`).

Note that in order for this to work correctly, the following modules must be loaded:

```
MOD_AUTHN_CORE.EXE
MOD_AUTHZ_CORE.EXE
MOD_AUTH_BASIC.EXE
MOD_AUTHNZ_OPENVMS.EXE
```

The `MOD_AUTHZ_CORE.EXE` module is strictly only required for authorization (as opposed to authentication), but since `MOD_AUTHNZ_OPENVMS.EXE` includes functionality to handle both authentication and authorisation, it is recommended to load `MOD_AUTHZ_CORE.EXE` whenever you use the `MOD_AUTHNZ_OPENVMS.EXE` module.

It should also be noted that the OpenVMS authentication and authorization module now accepts no configuration commands (as a consequence of the changes in 2.4 affecting how authentication and authorization are handled, such commands are now superfluous). Specifically, the following directives have been removed:

- AuthOpenVMSUser
- AuthOpenVMSGroup
- Setting a value for ServerName

Upon starting the web server for the first time you see a message similar to the following:

```
"Could not reliably determine the server's fully qualified domain name,  
using myhost.mydomain.com. Set the 'ServerName' directive globally to  
suppress this message"
```

where *myhost.mydomain.com* is the value that the web server has determined for the server's fully qualified domain name)

This message is informational and will not prevent the web server from starting; however, you may want to do as the message suggests and modify your HTTPD.CONF file to explicitly specify a value for the ServerName directive in accordance with the notes included in HTTPD.CONF (edit HTTPD.CONF and search for ServerName). It is strongly recommended that you also specify a port number, as illustrated in HTTPD.CONF, as this can prevent future issues if you plan to run multiple instances of the web server or if you plan to enable SSL, which uses a different port number (the value of ServerName in HTTPD.CONF cannot be the same as that used by the SSL VirtualHost specified in SSL.CONF).

- Logical names marked for deprecation

The logical names APACHE\$BG\_PIPE\_BUFFER\_SIZE and APACHE\$MB\_PIPE\_BUFFER\_SIZE have been marked for deprecation, and site-specific command procedures using these logical names should be modified to instead use the names APR\$BG\_PIPE\_BUFFER\_SIZE and APR\$MB\_PIPE\_BUFFER\_SIZE, respectively. Use of either name is supported by this release; however the logical names with the APACHE\$ prefix will be removed from subsequent releases. This change has been made in order to better reflect the name of the software sub-system to which the logical names pertain.

- The logical name APACHE\$SSL\_DBM\_TYPE has been deprecated

This logical name could be used in previous versions to define the DBM database manager to be used by the SSL session cache with MOD\_SSL. APACHEWS Version 2.4 for OpenVMS only supports the SDBM database, therefore the logical name APACHE\$SSL\_DBM\_TYPE is not required. However, for optimal performance, it is recommended that the shared memory cyclic buffer session cache is used. For additional information on setting up the SSL session cache, see [https://httpd.apache.org/docs/2.4/mod/mod\\_ssl.html#sslsessioncache](https://httpd.apache.org/docs/2.4/mod/mod_ssl.html#sslsessioncache).

- All custom-written dynamically loaded modules must be rebuilt for Version 2.4

Most third-party modules designed for Version 2.x will otherwise work unchanged with the Apache HTTP Server version 2.4 (will only need to be recompiled); however, some modules may require changes. The document [http://httpd.apache.org/docs/2.4/developer/new\\_api\\_2\\_4.html](http://httpd.apache.org/docs/2.4/developer/new_api_2_4.html) provides details of the API changes that have been made with 2.4. Also, see the notes about building custom

modules elsewhere in this document (building modules has been made easier with this release and does not require developers to download the APACHEWS source code).

In addition to the above points that are largely specific to OpenVMS, be sure to review the document <http://httpd.apache.org/docs/2.4/upgrading.html> if you are upgrading from a previous version of the web server.

## 4.1. Fixed Vulnerability Issues

Numerous CVEs are addressed in this release. For detailed information, please visit [https://httpd.apache.org/security/vulnerabilities\\_24.html](https://httpd.apache.org/security/vulnerabilities_24.html).

## 5. Known Issues and Restrictions in V2.4

- APACHEWS will fail to start correctly if the audit server is not running. This requirement may be removed in future releases of APACHEWS.
- APACHEWS may fail to start correctly if a `Listen` directive is not specified in `HTTPD.CONF`. The symptom of this problem is that the web server appears to be running but is not listening on any TCP/IP port for client requests. Inclusion of a simple `Listen` directive such as `Listen 80` (where 80 is the desired port number) is sufficient to negate this problem. This issue will be resolved in future releases.
- Do not attempt to use APACHEWS Version 2.4 with older CSWS optional kits.

Do not use APACHEWS Version 2.4 with the following optional kits. Using these kits together causes a process crash.

- CSWS\_PERL V2.1 or earlier
- CSWS\_PHP V5.2-17A or earlier
- CSWS\_JAVA (any version)

VMS Software Inc. is working to provide updated versions of these optional kits that can be used with APACHEWS Version 2.4.

- Installing APACHEWS Version 2.4 on an ODS-2 volume may corrupt an existing installation. You must install the APACHEWS Version 2.4 kit only on an ODS-5 target volume; if you install this kit on an ODS-2 volume, the installation will fail.
- Language variant filename restrictions

Specify language variants on an OpenVMS system in the same way as you do on a UNIX system, using multiple dots in the filename. For example, the French variant of a filename is `FILENAME.HTML.FR`.

- WebDAV database manager type restriction

WebDAV support requires the SDBM database manager type. SDBM is the default and only DBM supported in this release.

Defining an alternative DBM using the logical name `APACHE$DAV_DBM_TYPE` will cause an error to be logged and the web server will fail to start. Other DBM types may be supported by future releases.



- If suEXEC is enabled in the initial configuration, APACHEWS cannot add a node in a cluster environment.

If you enable suEXEC during the initial configuration of APACHEWS or by using Option 4 (Manage suEXEC users) of the APACHEWS Configuration Menu, then Option 10 of the APACHEWS Configuration Menu (Add a node to APACHEWS in a cluster environment) will fail.

As a workaround, use Option 4 to disable suEXEC, then use Option 10 to add the node, and then use Option 4 to re-enable suEXEC.

- Option 2 in the APACHE\$MENU.COM menu (“Create an Apache instance”) fails under the following circumstances:
  - Specifying a non-existent target directory fails with the following error when the directory [.FOO] does not exist.

```
Root Location: dev:[APACHE.SPECIFIC.FOO]
%SYSTEM-W-NOSUCHFILE, no such file \_DEV0:[APACHE.SPECIFIC]FOO.DIR\
%DCL-W-UNDSYM, undefined symbol - check validity and spelling \INDID\
%DCL-W-UNDSYM, undefined symbol - check validity and spelling \INDID\
```

- Creating an instance under a name other than APACHE\$WWW fails with the following error:

```
[DDD MMM DD HH:MM:SS YYYY] [error] (13) permission denied: Unable to
create input file dev:[directory].[000000]APACHE$xyz.COM
```

- The Require user directive for user authorization must specify user names in uppercase with the MOD\_AUTHNZ\_OPENVMS module.
- The ScoreBoardFile directive is ignored.

A shared memory scoreboard is used by APACHEWS to facilitate sharing of information between parent and child processes. The ScoreBoardFile directive in HTTPD.CONF is intended to allow file-based shared memory to be used for this purpose on platforms that do not support the use of anonymous shared memory. VSI OpenVMS does support anonymous shared memory and changes made in this release to improve APACHEWS performance by reducing inter-process coordination requirements have required the ScoreBoardFile directive to be ignored.

- For certain configuration errors, APACHEWS can fail silently on start-up without logging any details of the problem to the error log file, making it problematic to diagnose the problem. In such situations it is often useful to temporarily disable APACHEWS shared process logging by defining the logical name APACHE\$SPL\_DISABLED to TRUE in APACHE\$ROOT:[000000]LOGIN.COM. This will ensure that all error messages are flushed to the error log file before the process terminates. For optimal performance be sure to re-enable shared process logging once the problem has been resolved.
- In order for the web server to use IPv6, the two logical names TCPIP\$IPV6\_STARTED and APACHE\$CAN\_USE\_IPV6 must be defined in the SYSTEM table (the logical names can be defined with any value). Having only TCPIP\$IPV6\_STARTED is not sufficient.

## 6. Requirements

The kit you are receiving has been compiled and built to operate on the operating system versions listed below. While it is highly likely that you will have no problems installing and using the kit on systems running higher versions of the operating system, we cannot say for sure that you will be so fortunate if your system is running older versions.

- VSI OpenVMS Alpha Version 8.4-2L2 or higher, VSI OpenVMS IA-64 Version 8.4-2L1 or higher, VSI OpenVMS x86-64 Version 9.2-3 or higher
- VSI TCP/IP, HPE TCP/IP Services for OpenVMS, or MultiNet TCP/IP stack
- VSI SSL3 V3.0-16 or later

---

## Note

Note that MOD\_SSL is dynamically linked with SSL3 (OpenSSL), and SSL3 must therefore be installed in order to use the module MOD\_SSL. Be aware that this is a change from previous releases of APACHEWS, which had statically linked the OpenSSL libraries with MOD\_SSL.

---

- If you wish to run Python applications under APACHEWS using MOD\_WSGI, it should be noted that this facility is currently only supported for Python 3.8.2F for VSI OpenVMS. It is envisaged that future releases of APACHEWS and MOD\_WSGI will support Python 3.10 and/or later.

## 7. Before Beginning the Installation

As noted previously, there have been a number of changes in APACHEWS 2.4 that may cause any existing configuration files (HTTPD.CONF and SSL.CONF for example) to be incompatible with the new version of the web server. If you are installing APACHEWS 2.4 on a system that does not currently have a previous version of APACHEWS installed then no additional action is required before installing the software; however if you are upgrading from a previous version then it is strongly recommended that the following steps are taken:

1. Shut down APACHEWS if running:

```
$ @SYS$STARTUP:APACHE$SHUTDOWN
```

2. Take a backup of any site-specific files that are in APACHE\$ROOT:[000000...]

3. Uninstall any earlier version of APACHEWS:

```
$ PRODUCT REMOVE APACHEWS
The following product has been selected:
    VSI I64VMS APACHEWS V2.4-54                Layered Product

Do you want to continue? [YES]

The following product will be removed from destination:
    VSI I64VMS APACHEWS V2.4-54                DISK$I64SYS:[VMS$COMMON.]

Portion done: 0%

Deleting the Apache Htdocs & Icons directory trees will remove ALL user
data stored within.

Delete the Apache Htdocs & Icons directory trees ? [NO]: YES

...10%...20%...30%...40%...50%...60%...70%...80%...90%...100%

The following product has been removed:
    VSI I64VMS APACHEWS V2.4-54                Layered Product
```

When prompted with the question to delete the Apache Htdocs and Icons directory trees, be sure to answer **YES** in order to fully remove old versions of all documentation. Note that this process will not remove any site-specific files or customized configuration files.

#### 4. Rename your existing (customized) web server configuration files.

Renaming the configuration files will allow the APACHEWS 2.4 installation process to create new initial versions of these files, to which you can then apply any customizations from your old configuration files (taking into consideration any of the differences between web server versions).

Note that after shutting down and uninstalling the web server, no Apache logical names such as `APACHE$ROOT` or `APACHE$COMMON` will be defined. In order to find and rename your customized configuration files you will instead need to take note of where the web server was installed (in the case shown above this would be `DISK$I64SYS:[VMS$COMMON.]`) and set default to the configuration directory accordingly.

For example:

```
$ SET DEFAULT DISK$I64SYS:[VMS$COMMON.APACHE.CONF]
```

## 8. Installing APACHEWS

VSI requires that you install APACHEWS 2.4 on an ODS-5 enabled disk.

Verify that the destination device is an ODS-5 volume by entering a command similar to the following (assuming `BORIS$DKA200` is the disk where you want to install APACHEWS):

```
$ show dev BORIS$DKA200:/full

Disk BORIS$DKA200:, device type HP EH0146FCBVB, is online, mounted, file-
oriented device, shareable, available to cluster, error logging is enabled.
.
.
.
Volume Status:  ODS-5, subject to mount verification, protected subsystems
enabled, file high-water marking, write-through XFC caching enabled,
write-through XQP caching enabled, special files enabled.
```

Install the APACHEWS kit by entering the following command, where `BORIS$DKA200` is the name of the ODS-5 enabled disk where you want to install APACHEWS. Be sure that you manually removed any earlier version of APACHEWS before proceeding.

```
$ PRODUCT INSTALL APACHEWS /DEST=BORIS$DKA200:[0000000]
```

For a detailed description of the features you can request with the **PRODUCT INSTALL** command when starting an installation, see the POLYCENTER Software Installation Utility User's Guide.

As the installation procedure progresses, the system displays the information similar to the following output:

```
$ PRODUCT INSTALL APACHEWS

Performing product kit validation of signed kits ...
%PCSI-I-VSIVALPASSED, validation of DKC1:[RICKR.KITSD.APACHEWS2465]VSI-I64VMS-
APACHEWS-V0204-65-1.PCSI$COMPRESSED;1 succeeded
```

```
The following product has been selected:
    VSI I64VMS APACHEWS V2.4-65                Layered Product
```

```
Do you want to continue? [YES]
```

```
Configuration phase starting ...
```

You will be asked to choose options, if any, for each selected product and for any products that may be installed to satisfy software dependency requirements.

Configuring VSI I64VMS APACHEWS V2.4-65

VMS Software Inc. & The Apache Software Foundation.

\* This product does not have any configuration options.

Execution phase starting ...

The following product will be installed to destination:

VSI I64VMS APACHEWS V2.4-65                      DISK\$I64V842L1SYS:[VMS\$COMMON.]

Portion done: 0%...10%...20%...30%...40%...50%...60%...70%...80%...90%...100%

The following product has been installed:

VSI I64VMS APACHEWS V2.4-65                      Layered Product

VSI I64VMS APACHEWS V2.4-65

Release notes are available in SYS\$HELP:APACHEWS\_2\_4\_65.release\_notes.

VMS Software Inc. highly recommends that you read these release notes.

Post-installation tasks are required.

The OpenVMS Installation and Configuration Guide gives detailed directions.  
This information is a brief checklist.

Configure OpenVMS aspects of the web server by:

```
$ @SYS$MANAGER:APACHE$CONFIG
```

If the OpenVMS username APACHE\$WWW does not exist, you will be prompted to create that username. File ownerships are set to UIC [APACHE\$WWW], etc.

After configuration, start the web server manually by entering:

```
$ @SYS$STARTUP:APACHE$STARTUP
```

Check that neither SYLOGIN.COM nor the LOGIN.COM write any output to SYS\$OUTPUT:. Look especially for a

```
$ SET TERMINAL/INQUIRE.
```

Start the web server at system boot time by adding the following lines to SYS\$MANAGER:SYSTARTUP\_VMS.COM:

```
$ file := SYS$STARTUP:APACHE$STARTUP.COM
$ if f$search("''file'") .nes. "" then @'file'
```

Shutdown the Apache server at system shutdown time by adding the following lines to SYS\$MANAGER:SYSHUTDOWN.COM:

```
$ file := SYS$STARTUP:APACHE$SHUTDOWN.COM
$ if f$search("''file'") .nes. "" then @'file'
```

Test the installation using your favorite Web browser.  
Replace host.domain in the following URL (Uniform Resource Locator) with the information for the web server just installed, configured, and started.

URL `http://host.domain/` should display the standard introductory page from the Apache Software Foundation. This has the bold text "It Works!" If you do not see this page, check the release notes.

If you'd like to use secure connections then you'll need to create a server certificate. We recommend that you start by creating a 30 day self-signed certificate using the following certificate tool:

```
$ @APACHE$COMMON:[OPENSSL.COM]OPENSSL_AUTO_CERT.COM
```

Once the certificate has been created you'll need to uncomment the following directive in the `APACHE$COMMON:[CONF]HTTPD.CONF` file to enable SSL.

```
Include /apache$root/conf/ssl.conf
```

Thank you for using the VSI Apache Web Server.

## 9. Configuring the Web Server

After you have installed the APACHEWS, you are ready to configure it. The configuration tool ensures that a user account is available to run the server and that all of the files are owned by that user. It also allows the system manager flexibility in defining options for the installation.

APACHEWS 2.4 includes a simple configuration menu that allows you to choose configuration functions. All of the functions provided by the menu can be run through the menu or independently via individual command procedures.

To run the configuration menu, enter the following command:

```
$ @APACHE$COMMON:[000000]APACHE$MENU.COM
```

Following is an example of the configuration menu:

```
Apache$Menu
1. Configure the Secure Web Server
2. Create an Apache instance
3. Delete an Apache instance
4. Manage suEXEC users
5. Run OpenSSL Certificate tool
6. Convert directory tree to Stream_LF
7. Start up an Apache instance
8. Shut down an Apache instance
9. Show status of an Apache instance
10. Add a node to APACHEWS in a cluster environment
11. Exit

Enter Menu Choice:
```

The menu choices correspond to running the following procedures or commands from the DCL command line:

1. `SYS$MANAGER:APACHE$CONFIG.COM`
2. `APACHE$COMMON:[000000]APACHE$CREATE_ROOT.COM`
3. `APACHE$COMMON:[000000]APACHE$DELETE_ROOT.COM`
4. `APACHE$COMMON:[000000]APACHE$MANAGE_SUEXEC.COM`

5. APACHE\$COMMON:[000000]APACHE\$CERT\_TOOL.COM
6. APACHE\$COMMON:[000000]APACHE\$CONVERT\_STREAMLF.COM
7. SYS\$STARTUP:APACHE\$STARTUP.COM
8. SYS\$STARTUP:APACHE\$SHUTDOWN.COM
9. SHOW SYSTEM/PROCESS=APACHE\$tag
10. APACHE\$COMMON:[000000]APACHE\$ADDNODE.COM

For example, to perform a basic configuration and start a single instance of APACHEWS, you could proceed as follows:

```
$ @SYS$MANAGER:APACHE$CONFIG.COM
```

```
Secure Web Server for OpenVMS
                        [based on Apache]
```

```
This procedure helps you define the operating environment
required to run the Secure Web Server on this system.
```

```
To operate successfully, the server processes must have read access
to the installed files and read-write access to certain other files
and directories. It is recommended that you use this procedure to
set the owner UIC on the APACHEWS files and directories to match the
server.
```

```
You should do this each time the product is installed, but it only has
to be done once for each installation on a cluster.
```

```
Set owner UIC on APACHEWS files? [YES] YES
```

```
Do you want to enable the impersonation features provided by suEXEC?
If so, the server will support running CGIs using specified usernames.
```

```
Enable suEXEC? [NO]
```

```
Setting ownership on files. This could take a minute or two. . . .
```

```
Disabling suEXEC configuration. This could take a minute or two. . . .
Configuration is complete. To start the server:
```

```
$ @SYS$STARTUP:APACHE$STARTUP.COM
```

Once you are satisfied that the web server is functioning correctly, you can re-apply any site-specific configuration details and restore any site-specific files from a previous installation, or perform any of the functions provided by the configuration menu (or individual command procedures).

## 10. Enabling and Disabling SSL

- Enabling SSL:

Generate a self-signed certificate, which is valid for 30 days. To do so, use the following certificate tool:

```
$ @APACHE$COMMON:[OPENSSL.COM]OPENSSL_AUTO_CERT.COM
```

Uncomment the following directive in the `APACHE$COMMON:[CONF]HTTPD.CONF` file and restart the web server:

```
Include /apache$root/conf/ssl.conf
```

- **Disabling SSL:**

To disable SSL, comment the following directive in the `APACHE$COMMON:[CONF]HTTPD.CONF` file:

```
Include /apache$root/conf/ssl.conf
```

## 11. Building Dynamically Loadable Modules

APACHEWS for OpenVMS is ported from the Apache HTTP Server and includes all of the standard Apache HTTP Server modules as well as some OpenVMS-specific functionality. The Apache HTTP Server architecture allows new modules to be added to the server at the following times:

- When the server is built
- Dynamically at run-time using the Apache HTTP Server Dynamic Shared Object (DSO) feature

On OpenVMS, the DSO function is performed by the `LIB$FIND_IMAGE_SYMBOL` run-time library routine. When the web server encounters a `LoadModule` directive in `HTTPD.CONF`, it calls `LIB$FIND_IMAGE_SYMBOL` (via the C RTL `dlopen()` and `dlsym()` functions) to load a shareable image and to find the necessary universal symbols.

For example:

```
LoadModule mymod_module /apache$common/modules/mod_mymod.exe
```

This directive directs the web server to activate the shareable image `MOD_MYMOD.EXE` using the universal symbol `mymod_module` to locate the relevant module data structure describing the module's internal routine entry points.

A detailed description of the module architecture and how to develop your own custom modules (or to port existing third-party developed modules) is beyond the scope of this document; however the following important points specific to OpenVMS should be noted:

1. Your C code must be compiled with the following compiler switches:

```
/POINTER_SIZE=32/DEFINE=( _USE_STD_STAT )/NAMES=( AS_IS, SHORTENED )
```

If the macro `_USE_STD_STAT` is not defined as illustrated above, the HTTP request structure passed by the web server into your module will not have the correct size and request structure fields will not be correctly aligned between the web server and your custom module code.

The names of universal symbols (function names and global variables) in the web server shareable images `APACHE$APR_SHR` and `APACHE$HTTPD_SHR` are case-sensitive and custom modules must therefore be compiled with `/NAMES=( AS_IS, SHORTENED )` and linked with appropriate use of the `CASE_SENSITIVE` linker option (see [below](#)).

2. With previous releases of APACHEWS it was necessary to have a copy of the APACHEWS code available in order to include the necessary C header files into your custom module project. This release includes the text library `APACHE$ROOT:[INCLUDE]APACHE$LIBRARY.TLB`, which

includes all of the header files that are required when developing custom modules. This library can be used as follows when compiling your module code:

```
$ cc/p_pointer_size=32/define=(_USE_STD_STAT)/names=(as_is,shortened) -  
mod_mymod.c+apache$root:[include]APACHE$LIBRARY.TLB/lib
```

3. As commented above, the names of symbols in the shareable images `APACHE$APR_SHR` and `APACHE$HTTPD_SHR` are case-sensitive. It is necessary to link your custom code with these images, taking into consideration this case sensitivity, as illustrated below:

```
$ LINK/SHARE MOD_MYMOD.OBJ, SYS$INPUT/OPT  
    CASE_SENSITIVE=YES  
    SYMBOL_VECTOR=(mymod_module=DATA)  
    APACHE$APR_SHR/share  
    APACHE$HTTPD_SHR/share
```

Note that modules are implemented as an OpenVMS shareable image and must therefore be linked with the **/SHARE** qualifier.

Your custom module shareable images must not contain any linker warnings or errors, otherwise they will not be properly loaded at run-time.